



```

VV      VV      AAAAAA  XX      XX  EEEEEEEEE  DDDDDDD  IIIIII  TTTTTTTTT  PPPPPPP  CCCCCCC
VV      VV      AAAAAA  XX      XX  EEEEEEEEE  DDDDDDD  IIIIII  TTTTTTTTT  PPPPPPP  CCCCCCC
VV      VV      AA        AA  XX      XX  EE          DD      DD  II       TT       PP       PP  CC
VV      VV      AA        AA  XX      XX  EE          DD      DD  II       TT       PP       PP  CC
VV      VV      AA        AA  XX      XX  EE          DD      DD  II       TT       PP       PP  CC
VV      VV      AA        AA  XX      XX  EE          DD      DD  II       TT       PP       PP  CC
VV      VV      AA        AA  XX      XX  EEEEEEEEE  DD      DD  II       TT       PPPPPPP  CC
VV      VV      AA        AA  XX      XX  EEEEEEEEE  DD      DD  II       TT       PPPPPPP  CC
VV      VV      AAAAAAAAAA  XX      XX  EE          DD      DD  II       TT       PP       CC
VV      VV      AAAAAAAAAA  XX      XX  EE          DD      DD  II       TT       PP       CC
VV      VV      AA        AA  XX      XX  EE          DD      DD  II       TT       PP       CC
VV      VV      AA        AA  XX      XX  EE          DD      DD  II       TT       PP       CC
VV      VV      AA        AA  XX      XX  EEEEEEEEE  DDDDDDD  III'II  TT       PP       CCCCCCC
VV      VV      AA        AA  XX      XX  EEEEEEEEE  DDDDDDD  III'III  TT       PP       CCCCCCC

```

```

LL      IIIIII  SSSSSSS
LL      IIIIII  SSSSSSS
LL      II     SS
LL      II     SS
LL      II     SS
LL      II     SS
LL      II     SSSSSS
LL      II     SSSSSS
LL      II     SS
LL      II     SS
LL      II     SS
LL      IIIIII  SSSSSSS
LL      IIIIII  SSSSSSS

```

(2)	101	Declarations
(3)	146	VAX\$EDITPC - Edit Packed to Character String
(4)	318	Description of Pattern-Specific Routines
(5)	399	Utility Subroutine (READ Next Digit)
(6)	486	EO\$INSERT - Insert Character
(7)	520	EO\$STORE_SIGN - Store Sign
(8)	543	EO\$FILL - Store Fill
(9)	572	EO\$MOVE - Move Digits
(10)	605	EO\$FLOAT - Float Sign
(11)	640	EO\$END_FLOAT - End Floating Sign
(12)	670	EO\$BLANK_ZERO - Blank Backwards When Zero
(13)	709	EO\$REPLACE_SIGN - Replace Sign When Zero
(14)	746	EO\$LOAD_XXXXXX - Load Register
(15)	805	EO\$XXXXXX_SIGNIF - Significance
(16)	831	EO ADJUST_INPUT - Adjust Input Length
(17)	861	EO\$END - End Edit
(18)	974	EDITPC_ROPRAND_FAULT - Handle Illegal Pattern Operator
(19)	1090	EDITPC_ROPRAND_ABORT - Abnormally Terminate Instruction
(20)	1153	EDITPC_ACCVIO - Reflect an Access Violation
(21)	1320	Access Violation While Reading Input Digit
(22)	1386	Access Violation While Executing Loop
(23)	1472	Access Violation in Initialization Code
(24)	1499	Simple Access Violation
(25)	1580	EDITPC_PACK - Store EDITPC Intermediate State
(26)	1691	EDITPC_RESTART - Unpack and Restart EDITPC Instruction

```

0000 1      .TITLE VAX$EDITPC - VAX-11 EDITPC Instruction Emulation
0000 2      .IDENT /V04-000/
0000 3
0000 4
0000 5      *****
0000 6      *
0000 7      * COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
0000 8      * DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
0000 9      * ALL RIGHTS RESERVED.
0000 10     *
0000 11     * THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
0000 12     * ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
0000 13     * INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
0000 14     * COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
0000 15     * OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
0000 16     * TRANSFERRED.
0000 17     *
0000 18     * THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
0000 19     * AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
0000 20     * CORPORATION.
0000 21     *
0000 22     * DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
0000 23     * SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
0000 24     *
0000 25     *
0000 26     *****
0000 27     .
0000 28
0000 29     ++
0000 30     Facility:
0000 31
0000 32     VAX-11 Instruction Emulator
0000 33
0000 34     Abstract:
0000 35
0000 36     The routines in this module emulate the VAX-11 EDITPC instruction.
0000 37     These routines can be a part of an emulator package or can be
0000 38     called directly after the input parameters have been loaded into
0000 39     the architectural registers.
0000 40
0000 41     The input parameters to these routines are the registers that
0000 42     contain the intermediate instruction state.
0000 43
0000 44     Environment:
0000 45
0000 46     These routines run at any access mode, at any IPL, and are AST
0000 47     reentrant.
0000 48
0000 49     Author:
0000 50
0000 51     Lawrence J. Kenah
0000 52
0000 53     Creation Date
0000 54
0000 55     20 September 1982
0000 56
0000 57     Modified by:

```



```

0000 101      .SUBTITLE      Declarations
0000 102
0000 103      ; Include files
0000 104
0000 105      .NOCROSS
0000 106      .ENABLE      SUPPRESSION      ; No cross reference for these
0000 107                                          ; No symbol table entries either
0000 108      EDITPC_DEF      ; Define intermediate instruction state
0000 109
0000 110      PACK_DEF      ; Stack offsets for exceptions
0000 111
0000 112      $PSLDEF      ; Define bit fields in PSL
0000 113
0000 114      .DISABLE      SUPPRESSION      ; Turn on symbol table again
0000 115      .CROSS      ; Cross reference is OK now
0000 116
0000 117      ; Equated symbols
0000 118
00000020 0000 119      BLANK = ^A''''
0000002D 0000 120      MINUS = ^A''-''
00000030 0000 121      ZERO = ^A''0''
0000 122
0000 123      ; Local macro definitions
0000 124
0000 125      .MACRO EO_READ
0000 126      RESTART_POINT
0000 127      BSBW EO_READ
0000 128      .ENDM EO_READ
0000 129
0000 130      ; External declarations
0000 131
0000 132      .DISABLE      GLOBAL
0000 133
0000 134      .EXTERNAL -
0000 135
0000 136      VAX$REFLECT_FAULT,-
0000 137      VAX$ROPRAND,-
0000 137      VAX$EDITPC_OVERFLOW
0000 138      ; PSECT Declarations:
0000 139
0000 140      .DEFAULT      DISPLACEMENT , WORD
0000 141
00000000 142      .PSECT _VAX$CODE PIC,USR,CON,REL,LCL,SHR,EXE,RD,NOWRT,LONG
0000 143
0000 144      BEGIN_MARK_POINT      RESTART

```

0000 146 .SUBTITLE VAXSEDITPC - Edit Packed to Character String


0000 147 :  
 0000 148 : Functional Description:  
 0000 149 :

0000 150 : The destination string specified by the pattern and destination  
 0000 151 : address operands is replaced by the edited version of the source  
 0000 152 : string specified by the source length and source address operands.  
 0000 153 : The editing is performed according to the pattern string starting at  
 0000 154 : the address pattern and extending until a pattern end (EO\$END) pattern  
 0000 155 : operator is encountered. The pattern string consists of one byte  
 0000 156 : pattern operators. Some pattern operators take no operands. Some  
 0000 157 : take a repeat count which is contained in the rightmost nibble of the  
 0000 158 : pattern operator itself. The rest take a one byte operand which  
 0000 159 : follows the pattern operator immediately. This operand is either an  
 0000 160 : unsigned integer length or a byte character. The individual pattern  
 0000 161 : operators are described on the following pages.

0000 162 :  
 0000 163 : Input Parameters:

0000 164 :  
 0000 165 : R0 - srclen.rw Length of input packed decimal string  
 0000 166 : R1 - srcaddr.ab Address of input packed decimal string  
 0000 167 : R3 - pattern.ab Address of table of editing pattern operators  
 0000 168 : R5 - dstaddr.ab Address of output character string  
 0000 169 :

0000 170 : Intermediate State:



0000 187 : Output Parameters:

0000 188 :  
 0000 189 : R0 - Length of input decimal string  
 0000 190 : R1 - Address of most significant byte of input decimal string  
 0000 191 : R2 - 0  
 0000 192 : R3 - Address of byte containing EO\$END pattern operator  
 0000 193 : R4 - 0  
 0000 194 : R5 - Address of one byte beyond destination character string  
 0000 195 :

0000 196 : Condition Codes:

0000 197 :  
 0000 198 : N <- source string LSS 0 (src = -0 => N = 0)  
 0000 199 : Z <- source string EQL 0  
 0000 200 : V <- decimal overflow (nonzero digits lost)  
 0000 201 : C <- significance  
 0000 202 :-

```

0000 203
0000 204 .ENABLE LOCAL_BLOCK
0000 205
0000 206 ASSUME EDITPC_B_STATE EQ 18 ; Make sure we test the right FPD bit
0000 207
02DD 31 0000 208 2$: BRW VAX$EDITPC_RESTART ; Restart somewhere else
0003 209
01EE 31 0003 210 5$: BRW EDITPC_ROPRAND_ABORT ; Time to quit if illegal length
0006 211
0006 212 VAX$EDITPC::
F6 54 14 E0 0006 213 BBS #<EDITPC_V_FPD+16>,R4,2$ ; Branch if this is a restart
OFC3 8F BB 000A 214 PUSHR #^M<R0,RT,R6,R7,R8,R9,R10,R11> ; Save lots of registers
1F 50 B1 000E 215 CMPW R0,#31 ; Check for R0 GTRU 31
50 50 FO 1A 0011 216 BGTRU 5$ ; Signal ROPRAND if R0 GTRU 31
52 20 9A 0013 217 MOVZWL R0,R0 ; Clear any junk from high-order word
59 D4 0019 218 MOVZBL #BLANK,R2 ; Set fill to BLANK, stored in R2
001B 219 CLRL R9 ; Start with "zero count" of zero
0020 220 ESTABLISH_HANDLER EDITPC_ACCVIO
5B 0B DC 0020 221 MOVPSL RT1 ; Get current PSL
5B 04 8A 0022 222 BICB #<PSL$M_N!PSL$M_V!PSL$M_C>,R11 ; Clear N-, V-, and C-bits
0025 223 BISB #PSL$M_Z,R11 ; Set Z-bit.
0028 224
0028 225 ; We need to determine the sign in the input decimal string to choose
0028 226 ; the initial setting of the N-bit in the saved PSW.
0028 227
57 50 04 01 EF 0028 228 EXTZV #1,#4,R0,R7 ; Get byte offset to end of string
57 51 C0 002D 229 ADDL R1,R7 ; Get address of byte containing sign
0030 230 MARK_POINT EDITPC_1 , RESTART
57 67 04 00 EF 0030 231 EXTZV #0,#4,(R7),R7 ; Get sign "digit" into R7
0035 232
0035 233 CASE R7,LIMIT=#10,TYPE=B,<- ; Dispatch on sign
0035 234 20$,- ; 10 => +
0035 235 10$,- ; 11 => -
0035 236 20$,- ; 12 => +
0035 237 10$,- ; 13 => -
0035 238 20$,- ; 14 => +
0035 239 20$,- ; 15 => +
0035 240 >
0045 241
0045 242 ; Sign is MINUS
0045 243
5B 0B 88 0045 244 10$: BISB #PSL$M_N,R11 ; Set N-bit in saved PSW
54 2D 9A 0048 245 MOVZBL #MINUS,R4 ; Set sign to MINUS, stored in R4
03 11 004B 246 BRB TOP_OF_LOOP ; Join common code
004D 247
004D 248 ; Sign is PLUS (but initial content of sign register is BLANK)
004D 249
54 20 9A 004D 250 20$: MOVZBL #BLANK,R4 ; Set sign to BLANK, stored in R4
0050 251
0050 252 ; The architectural description of the EDITPC instruction uses an exit flag
0050 253 ; to determine whether to continue reading edit operators from the input
0050 254 ; stream. This implementation does not use an explicit exit flag. Rather, all
0050 255 ; of the end processing is contained in the routine that handles the EOSEND
0050 256 ; operator.
0050 257
0050 258 ; The next several instructions are the main routine in this module. Each
0050 259 ; pattern is used to dispatch to a pattern-specific routine that performs

```



```

0050 260 ; its designated action. These routines (except for EO$END) return control
0050 261 ; to TOP_OF_LOOP to allow the next pattern operator to be processed.
0050 262
FD AF 9F 0050 263 TOP_OF_LOOP:
0050 264 PUSHAB B^TOP_OF_LOOP ; Store 'return PC'
0053 265
0053 266 ; The following instructions pick up the next byte in the pattern stream and
0053 267 ; dispatch to a pattern specific subroutine that performs the designated
0053 268 ; action. Control is passed back to the main EDITPC loop by the RSB
0053 269 ; instructions located in each pattern-specific subroutine.
0053 270
0053 271 ; Note that the seemingly infinite loop actually terminates when the EO$END
0053 272 ; pattern operator is detected. That routine insures that we do not return
0053 273 ; to this loop but rather to the caller of VAXSEITPC.
0053 274
0053 275 MARK_POINT EDITPC_2, RESTART
0053 276 CASE- (R3)+,LIMIT=#0,TYPE=B,<-
0053 277 EO$END_ROUTINE,- ; 00 - EO$END
0053 278 EO$END_FLOAT_ROUTINE,- ; 01 - EO$END_FLOAT
0053 279 EO$CLEAR_SIGNIF_ROUTINE,- ; 02 - EO$CLEAR_SIGNIF
0053 280 EO$SET_SIGNIF_ROUTINE,- ; 03 - EO$SET_SIGNIF
0053 281 EO$STORE_SIGN_ROUTINE,- ; 04 - EO$STORE_SIGN
0053 282 >
0061 283
0061 284 MARK_POINT EDITPC_3
0061 285 CASE- -1(R3),LIMIT=#*X40,TYPE=B,<-
0061 286 EO$LOAD_FILL_ROUTINE,- ; 40 - EO$LOAD_FILL
0061 287 EO$LOAD_SIGN_ROUTINE,- ; 41 - EO$LOAD_SIGN
0061 288 EO$LOAD_PLUS_ROUTINE,- ; 42 - EO$LOAD_PLUS
0061 289 EO$LOAD_MINUS_ROUTINE,- ; 43 - EO$LOAD_MINUS
0061 290 EO$INSERT_ROUTINE,- ; 44 - EO$INSERT
0061 291 EO$BLANK_ZERO_ROUTINE,- ; 45 - EO$BLANK_ZERO
0061 292 EO$REPLACE_SIGN_ROUTINE,- ; 46 - EO$REPLACE_SIGN
0061 293 EO$ADJUST_INPUT_ROUTINE,- ; 47 - EO$ADJUST_INPUT
0061 294 >
0077 295
0077 296 MARK_POINT EDITPC_4
FF A3 OF 93 0077 297 BITB #^B1111,-1(R3) ; Check for 80, 90, or A0
10 13 0078 298 BEQL 30$ ; Reserved operand on repeat of zero
57 FF A3 04 04 EF 007D 299 MARK_POINT EDITPC_5
007D 300 EXTZV #4,#4,-1(R3),R7 ; Ignore repeat count in dispatch
0083 301
0083 302 CASE R7,LIMIT=#8,TYPE=B,<-
0083 303 EO$FILL_ROUTINE,- ; 81 to 8F - EO$FILL
0083 304 EO$MOVE_ROUTINE,- ; 91 to 9F - EO$MOVE
0083 305 EO$FLOAT_ROUTINE,- ; A1 to AF - EO$FLOAT
0083 306 >
008D 307
008D 308 ; If we drop through all three CASE instructions, the pattern operator is
008D 309 ; unimplemented or reserved. R3 is backed up to point to the illegal
008D 310 ; pattern operator and a reserved operand FAULT is signalled.
008D 311
SE 53 D7 008D 312 30$: DECL R3 ; Point R3 to illegal operator
04 C0 008F 313 ADDL #4,SP ; Discard return PC
011E 31 0092 314 BRW EDITPC_ROPRAND_FAULT ; Initiate exception processing
0095 315
0095 316 .DISABLE LOCAL_BLOCK
  
```

```

0095 318 .SUBTITLE Description of Pattern-Specific Routines
0095 319 :+
0095 320 : Functional Description:
0095 321 :
0095 322 : There is a separate action routine for each pattern operator. These
0095 323 : routines are entered with specific register contents and several
0095 324 : scratch registers at their disposal. They perform their designated
0095 325 : action and return to the main VAX$EDITPC routine.
0095 326 :
0095 327 : There are several words used in the architectural description of this
0095 328 : instruction that are carried over into comments in this module. These
0095 329 : words are briefly mentioned here.
0095 330 :
0095 331 : char Character in byte following pattern operator (used by
0095 332 : E0$LOAD_FILL, E0$LOAD_SIGN, E0$LOAD_PLUS, E0$LOAD_MINUS,
0095 333 : and E0$INSERT)
0095 334 :
0095 335 : length Length in byte following pattern operator (used by
0095 336 : E0$BLANK_ZERO, E0$REPLACE_SIGN, and E0$ADJUST_INPUT)
0095 337 :
0095 338 : repeat Repeat count in bits <3:0> of pattern operator (used by
0095 339 : E0$FILL, E0$MOVE, and E0$FLOAT)
0095 340 :
0095 341 : The architecture makes use of two character registers, described
0095 342 : as appearing in different bytes of R2. For simplicity, we use an
0095 343 : additional register.
0095 344 :
0095 345 : fill Stored in R2<7:0>
0095 346 :
0095 347 : sign Stored in R4<7:0>
0095 348 :
0095 349 : Finally, the architecture describes two subroutines, one that obtains
0095 350 : the next digit from the input string and the other that stores a
0095 351 : character in the output string.
0095 352 :
0095 353 : READ Subroutine E0_READ provides this functionality
0095 354 :
0095 355 : STORE A single instruction of the form
0095 356 :
0095 357 : MOVB xxx,(R5)+
0095 358 :
0095 359 : or
0095 360 :
0095 361 : ADDB3 #ZERO,R7,(R5)+
0095 362 :
0095 363 : stores a single character and advances the pointer.
0095 364 :
0095 365 : Input Parameters:
0095 366 :
0095 367 : R0 - Updated length of input decimal string
0095 368 : R1 - Address of next byte of input decimal string
0095 369 : R2 - Fill character
0095 370 : R3 - Address of one byte beyond current pattern operator
0095 371 : R4 - Sign character
0095 372 : R5 - Address of next character to be stored in output character string
0095 373 :
0095 374 : Implicit Input:

```

```
0095 375 :  
0095 376 : Several registers are used to contain intermediate state, passed  
0095 377 : from one action routine to the next.  
0095 378 :  
0095 379 : R7 - Contains latest digit from input stream (output from EO_READ)  
0095 380 : R8 - Used as loop counter  
0095 381 : R9 - Contains the value described in the architecture as R0<31:16>  
0095 382 : R11 - Pseudo-PSW that contains the saved condition codes  
0095 383 :  
0095 384 : Side Effects:  
0095 385 :  
0095 386 : The remaining registers are used as scratch by the action routines.  
0095 387 :  
0095 388 : R6 - Scratch register used only by access violation handler  
0095 389 : R7 - Output parameter of EO_READ routine  
0095 390 : R8 - Scratch register used by pattern-specific routines  
0095 391 :  
0095 392 : Output Parameters:  
0095 393 :  
0095 394 : The actual output depends on the pattern operator that is currently  
0095 395 : executing. The routine headers for each routine will describe the  
0095 396 : specific output parameters.  
0095 397 :-
```

```

0095 399      .SUBTITLE      Utility Subroutine (READ Next Digit)
0095 400      :
0095 401      : Functional Description:
0095 402      :
0095 403      : This routine reads the next digit from the input packed decimal
0095 404      : string and passes it back to the caller.
0095 405      :
0095 406      : Input Parameters:
0095 407      :
0095 408      : R0 - Updated length of input decimal string
0095 409      : R1 - Address of next byte of input decimal string
0095 410      : R9 - Count of extra zeros (see E0$ADJUST_INPUT)
0095 411      :
0095 412      : (SP) - Return address to caller of this routine
0095 413      :
0095 414      : Note that R9<15:0> contains the data described by the architecture as
0095 415      : appearing in R0<31:16>. In the event of an restartable exception
0095 416      : (access violation or reserved operand fault due to an illegal pattern
0095 417      : operator), the contents of R9<15:0> will be stored in R0<31:16>. In
0095 418      : order for the instruction to be restarted, the "zero count" (the
0095 419      : contents of R9) must be preserved. While any available field will do
0095 420      : in the event of an access violation, the use of R0<31:16> is clearly
0095 421      : specified for a reserved operand fault.
0095 422      :
0095 423      : Output Parameters:
0095 424      :
0095 425      : The behavior of this routine depends on the contents of R9
0095 426      :
0095 427      : R9 is zero on input
0095 428      :
0095 429      : R0 - Updated by one
0095 430      : R1 - Updated by one if R0<0> is clear on input
0095 431      : R7 - Next decimal digit in input string
0095 432      : R9 - Unchanged
0095 433      :
0095 434      : PSW<Z> is set if the digit is zero, clear otherwise
0095 435      :
0095 436      : R9 is nonzero (LSS 0) on input
0095 437      :
0095 438      : R0 - Unchanged
0095 439      : R1 - Unchanged
0095 440      : R7 - Zero
0095 441      : R9 - Incremented by one (toward zero)
0095 442      :
0095 443      : PSW<Z> is set
0095 444      :-
0095 445      :
0095 446      EO_READ:
0095 447      TSTL      R9          ; Check for 'R0' LSS 0
0097 448      BNEQ      20$      ; Special code if nonzero
0099 449      DECL      R0          ; Insure that digits still remain
009B 450      BLSS      30$      ; Reserved operand if none
009D 451      BLBC      R0,10$    ; Next code path is flip flop
00A0 452      :
00A0 453      : R0 was even on input (and is now odd), indicating that we want the low
00A0 454      : order nibble in the input stream. The input pointer R1 must be advanced
00A0 455      : to point to the next byte.

```

59 D5  
13 12  
50 D7  
14 19  
06 50 E9

```

57 81 04 00 EF 00A0 456
                00A0 457          MARK POINT      READ 1
05 00A0 458          EXTZV #0,#4,(R1)+,R7          ; Load low order nibble into R7
                00A5 459          RSB              ; Return with information in Z-bit
                00A6 460
                00A6 461 ; R0 was odd on input (and is now even), indicating that we want the high
                00A6 462 ; order nibble in the input stream. The next pass through this routine will
                00A6 463 ; pick up the low order nibble of the same input byte.
                00A6 464
                00A6 465          MARK POINT      READ 2
57 61 04 04 EF 00A6 466 10$:          EXTZV #4,#4,(R1),R7          ; Load high order nibble into R7
05 00AB 467          RSB              ; Return with information in Z-bit
                00AC 468
                00AC 469 ; R9 was nonzero on input, indicating that zeros should replace the original
                00AC 470 ; input digits.
                00AC 471
                59 D6 00AC 472 20$:          INCL R9          ; Advance R9 toward zero
                57 D4 00AE 473          CLRL R7              ; Behave as if we read a zero digit
05 00B0 474          RSB              ; Return with Z-bit set
                00B1 475
                00B1 476 ; The input decimal string ran out of digits before its time. The architecture
                00B1 477 ; dictates that R3 points to the pattern operator that requested the input
                00B1 478 ; digit and R0 contains a -1 when the reserved operand abort is reported.
                00B1 479 ; It is not necessary to load R0 here. R0 already contains -1 because it just
                00B1 480 ; turned negative.
                00B1 481
                53 D7 00B1 482 30$:          DECL R3          ; Back up R3 to current pattern operator
SE 08 C0 00B3 483          ADDL #8,SP          ; Discard two return PCs
013B 31 00B6 484          BRW EDITPC_ROPRAND_ABORT ; Branch aid for reserved operand abort

```

```

00B9 486      .SUBTITLE      E0$INSERT - Insert Character
00B9 487      :+
00B9 488      : Functional Description:
00B9 489      :
00B9 490      :   Insert a fixed character, substituting the fill character if
00B9 491      :   not significant.
00B9 492      :
00B9 493      : Input Parameters:
00B9 494      :
00B9 495      :   R2 - Fill character
00B9 496      :   R3 - Address of character to be inserted if significance is set
00B9 497      :   R5 - Address of next character to be stored in output character string
00B9 498      :   R11<C> - Current setting of significance
00B9 499      :
00B9 500      : Output Parameters:
00B9 501      :
00B9 502      :   Character in pattern stream (or fill character if no significance)
00B9 503      :   is stored in the the output string.
00B9 504      :
00B9 505      :   R3 - Advanced beyond character in pattern stream
00B9 506      :   R5 - Advanced one byte as a result of the STORE operation
00B9 507      : -
00B9 508
00B9 509      E0$INSERT ROUTINE:
04 5B 00  E1 00B9 510      BBC      #PSL$V_C,R11,10$      ; Skip next if no significance
      85 83 90 00BD 511      MARK_POINT  INSERT_1
      05 00C0 512      MOVB      (R3)+,(R5)+      ; STORE 'ch' in output string
      00C1 513      RSB
      00C1 514
      85 52 90 00C1 515      MARK_POINT  INSERT_2
      53  D6 00C1 516 10$:  MOVB      R2,(R5)+      ; STORE fill character
      00C4 517      INCL      R3      ; Skip over unused character
      05 00C6 518      RSB

```

```
00C7 520      .SUBTITLE      EO$STORE_SIGN - Store Sign
00C7 521      :+
00C7 522      : Functional Description:
00C7 523      :
00C7 524      : The contents of the sign register are placed into the output string.
00C7 525      :
00C7 526      : Input Parameters:
00C7 527      :
00C7 528      : R4 - Sign character
00C7 529      : R5 - Address of next character to be stored in output character string
00C7 530      :
00C7 531      : Output Parameters:
00C7 532      :
00C7 533      : Sign character is stored in the the output string.
00C7 534      :
00C7 535      : R5 - Advanced one byte as a result of the STORE operation
00C7 536      :-
00C7 537
00C7 538 EO$STORE_SIGN ROUTINE:
00C7 539      MARK_POINT STORE_SIGN_1
85 54 90 00C7 540      MOVB R4,(R5)+ ; STORE sign character
05 00CA 541      RSB
```

```

00CB 543      .SUBTITLE      EOSFILL - Store Fill
00CB 544      :+
00CB 545      : Functional Description:
00CB 546      :
00CB 547      : The contents of the fill register are placed into the output string
00CB 548      : a total of "repeat" times.
00CB 549      :
00CB 550      : Input Parameters:
00CB 551      :
00CB 552      : R2 - Fill character
00CB 553      : R5 - Address of next character to be stored in output character string
00CB 554      :
00CB 555      : -1(R3)<3:0> - Repeat count is stored in right nibble of pattern operator
00CB 556      :
00CB 557      : Output Parameters:
00CB 558      :
00CB 559      : Fill character is stored in the output string "repeat" times
00CB 560      :
00CB 561      : R5 - Advanced "repeat" bytes as a result of the STORE operations
00CB 562      : -
00CB 563      :
00CB 564      EOSFILL_ROUTINE:
00CB 565      MARK_POINT      FILL_1
58  FF A3 04 00 EF 00CB 566      EXTZV #0,#4,-1(R3),R8 ; Get repeat count from pattern operator
00D1 567      MARK_POINT      FILL_2 , RESTART
      85 52 90 00D1 568 10$: MOVB R2,(R5)+ ; STORE fill character
      FA 58 F5 00D4 569      SOBGTR R8,10$ ; Test for end of loop
00D7 570      RSB

```



```

00D8 572      .SUBTITLE      EOSMOVE - Move Digits
00D8 573      ;+
00D8 574      ; Functional Description:
00D8 575      ;
00D8 576      ; The right nibble of the pattern operator is the repeat count. For
00D8 577      ; repeat times, the following algorithm is executed. The next digit is
00D8 578      ; moved from the source to the destination. If the digit is non-zero,
00D8 579      ; significance is set and zero is cleared. If the digit is not
00D8 580      ; significant (i.e., is a leading zero) it is replaced by the contents
00D8 581      ; of the fill register in the destination.
00D8 582      ; -
00D8 583
00D8 584      EOSMOVE_ROUTINE:
00D8 585      MARK_POINT      MOVE_1
00D8 586      EXTZV      #0,#4,-1(R3),R8      ; Get repeat count
00DE 587
00DE 588      10$:      EO_READ      ; Get next input digit
00E1 589      BEQL      30$      ; Is it zero? Branch if yes
00E3 590      BISB      #PSLSM_C,R11      ; Indicate significance
00E6 591      BICB      #PSLSM_Z,R11      ; Also indicate nonzero
00E9 592
00E9 593      MARK_POINT      MOVE_2 , RESTART
00E9 594      20$:      ADDB3      #ZERO,R7,(R5)+      ; STORE digit in output stream
00ED 595      SOBGTR      R8,10$      ; Test for end of loop
00F0 596      RSB
00F1 597
00F1 598      30$:      BBS      #PSLSV_C,R11,20$      ; If significance, then STORE digit
00F5 599
00F5 600      MARK_POINT      MOVE_3 , RESTART
00F5 601      MOVB      R2,(R5)+      ; Otherwise, STORE fill character
00F8 602      SOBGTR      R8,10$      ; Test for end of loop
00FB 603      RSB

```

```

00FC 605      .SUBTITLE      EOSFLOAT - Float Sign
00FC 606      :+
00FC 607      : Functional Description:
00FC 608      :
00FC 609      : The right nibble of the pattern operator is the repeat count. For
00FC 610      : repeat times, the following algorithm is executed. The next digit
00FC 611      : from the source is examined. If it is non-zero and significance is
00FC 612      : not yet set, then the contents of the sign register is stored in the
00FC 613      : destination, significance is set, and zero is cleared. If the digit
00FC 614      : is significant, it is stored in the destination, otherwise the
00FC 615      : contents of the fill register is stored in the destination.
00FC 616      :-
00FC 617
00FC 618 EOSFLOAT ROUTINE:
00FC 619 MARK_POINT      FLOAT_1
58 FF A3 04 00 EF 00FC 620 EXTZV #0,#4,-1(R3),R8      ; Get repeat count
0102 621
0102 622 10$: EO_READ      ; Get next input digit
0B 5B 00 E0 0105 623 BBS #PSLSV_C,R11,20$      ; Is significance set? Branch if yes.
11 13 0109 624 BEQL 30$      ; Is digit zero? Branch if yes.
010B 625 MARK_POINT      FLOAT_2 , RESTART
85 54 90 010B 626 MOVB R4,(R5)+      ; STORE sign
5B 01 88 010E 627 BISB #PSLSM_C,R11      ; Indicate significance
5B 04 8A 0111 628 BICB #PSLSM_Z,R11      ; Also indicate nonzero
0114 629
0114 630 MARK_POINT      FLOAT_3 , RESTART
85 57 30 81 0114 631 20$: ADDB3 #ZERO,R7,(R5)+      ; STORE digit in output stream
E7 58 F5 0118 632 SOBGTR R8,10$      ; Test for end of loop
05 011B 633 RSB
011C 634
011C 635 30$: MARK_POINT      FLOAT_4 , RESTART
85 52 90 011C 636 MOVB R2,(R5)+      ; Otherwise, STORE fill character
E0 58 F5 011F 637 SOBGTR R8,10$      ; Test for end of loop
05 0122 638 RSB

```

```

0123 640      .SUBTITLE      EOSEND_FLOAT - End Floating Sign
0123 641      :+
0123 642      : Functional Description:
0123 643      :
0123 644      :     If the floating sign has not yet been placed into the destination
0123 645      :     string (that is, if significance is not yet set), then the contents
0123 646      :     of the sign register are stored in the output string and significance
0123 647      :     is set.
0123 648      :
0123 649      : Input Parameters:
0123 650      :
0123 651      :     R4 - Sign character
0123 652      :     R5 - Address of next character to be stored in output character string
0123 653      :     R11<C> - Current setting of significance
0123 654      :
0123 655      : Output Parameters:
0123 656      :
0123 657      :     Sign character is optionally stored in the output string (if
0123 658      :     significance was not yet set).
0123 659      :
0123 660      :     R5 - Optionally advanced one byte as a result of the STORE operation
0123 661      :     R11<C> - (Significance) is unconditionally SET
0123 662      :-
0123 663
0123 664 EOSEND_FLOAT_ROUTINE:
03 5B 00 E2 0123 665      BBSS      #PSL$V_C,R11,10$      ; Test and set significance
0127 666      MARK_POINT      END_FLOAT_1
0127 667      MOVB      R4,(R5)+      ; STORE sign character
05 012A 668 10$:      RSB

```

```

012B 670 .SUBTITLE EOSBLANK_ZERO - Blank Backwards When Zero
012B 671 :+
012B 672 : Functional Description:
012B 673 :
012B 674 : The pattern operator is followed by an unsigned byte integer length.
012B 675 : If the value of the source string is zero, then the contents of the
012B 676 : fill register are stored into the last length bytes of the destination
012B 677 : string.
012B 678 :
012B 679 : Input Parameters:
012B 680 :
012B 681 : R2 - Fill character
012B 682 : R3 - Address of "length", number of characters to blank
012B 683 : R5 - Address of next character to be stored in output character string
012B 684 : R11<Z> - Set if input string is zero
012B 685 :
012B 686 : Output Parameters:
012B 687 :
012B 688 : Contents of fill register are stored in last "length" characters
012B 689 : of output string if input string is zero.
012B 690 :
012B 691 : R3 - Advanced one byte over "length"
012B 692 : R5 - Unchanged
012B 693 :
012B 694 : Side Effects:
012B 695 :
012B 696 : R8 is destroyed
012B 697 :-
012B 698
012B 699 EOSBLANK_ZERO ROUTINE:
012B 700 MARK_POINT BLANK_ZERO_1
09 58 83 9A 012B 701 MOVZBL (R3)+,R8 ; Get length
58 02 E1 012E 702 BBC #PSL$V_Z,R11,20$ ; Skip rest if source string is zero
55 58 C2 0132 703 SUBL R8,R5 ; Back up destination pointer
0135 704 MARK_POINT BLANK_ZERO_2 , RESTART
85 52 90 0135 705 10$: MOVB R2,(R5)+ ; STORE fill character
FA 58 F5 0138 706 SOBGTR R8,10$ ; Check for end of loop
05 013B 707 20$: RSB
  
```

```

013C 709 .SUBTITLE EOS$REPLACE_SIGN - Replace Sign When Zero
013C 710 :+
013C 711 : Functional Description:
013C 712 :
013C 713 : If the value of the source string is zero, then the contents of the
013C 714 : fill register are stored into the byte of the destination string
013C 715 : that is "length" bytes before the current position.
013C 716 :
013C 717 : Input Parameters:
013C 718 :
013C 719 : R2 - Fill character
013C 720 : R3 - Address of "length", number of characters to blank
013C 721 : R5 - Address of next character to be stored in output character string
013C 722 : R11<Z> - Set if input string is zero
013C 723 :
013C 724 : Output Parameters:
013C 725 :
013C 726 : Contents of fill register are stored in byte of output string
013C 727 : "length" bytes before current position if input string is zero.
013C 728 :
013C 729 : R3 - Advanced one byte over "length"
013C 730 : R5 - Unchanged
013C 731 :
013C 732 : Side Effects:
013C 733 :
013C 734 : RB is destroyed
013C 735 :-
013C 736 :
013C 737 EOS$REPLACE_SIGN ROUTINE:
013C 738 MARK_POINT REPLACE_SIGN_1
07 58 83 9A 013C 739 MOVZBL (R3)+,R8 ; Get length
58 55 58 C3 013F 740 BBC #PSL$V Z,R11,10$ ; Skip rest if source string is zero
68 52 90 0143 741 SUBL3 R8,R5,R8 ; Get address of indicated byte
0147 742 MARK_POINT REPLACE_SIGN_2
0147 743 MOVB R2,(R8) ; STORE fill character
014A 744 10$: RSB
  
```

```

014B 746 .SUBTITLE EOSLOAD_xxxxxx - Load Register
014B 747 :+
014B 748 : Functional Description:
014B 749 :
014B 750 : The contents of the fill or sign register are replaced with the
014B 751 : character that follows the pattern operator in the pattern stream.
014B 752 :
014B 753 : EOSLOAD_FILL Load Fill Register
014B 754 :
014B 755 : EOSLOAD_SIGN Load Sign Register
014B 756 :
014B 757 : EOSLOAD_PLUS Load Sign Register If Source String Is Positive (or Zero)
014B 758 :
014B 759 : EOSLOAD_MINUS Load Sign Register If Source String Is Negative
014B 760 :
014B 761 : Input Parameters:
014B 762 :
014B 763 : R3 - Address of character to be loaded
014B 764 : R11<N> - Set if input string is LSS zero (negative)
014B 765 :
014B 766 : Output Parameters:
014B 767 :
014B 768 : If entry is at EOSLOAD_FILL, the fill register contents (R2<7:0>) are
014B 769 : replaced with the next character in the pattern stream.
014B 770 :
014B 771 : If one of the other entry points is used (and the appropriate conditions
014B 772 : obtain), the contents of the sign register are replaced with the next
014B 773 : character in the pattern stream. For simplicity of implementation, the
014B 774 : sign character is stored in R4<7:0> while this routine executes.
014B 775 :
014B 776 : In the event of an exception, the contents of R4<7:0> will be stored
014B 777 : in R2<15:8>, either to conform to the architectural specification of
014B 778 : register contents in the event of a reserved operand fault, or to
014B 779 : allow the instruction to be restarted in the event of an access
014B 780 : violation.
014B 781 :
014B 782 : R3 - Advanced one byte over new fill or sign character
014B 783 : -
014B 784 :
014B 785 EOSLOAD_FILL_ROUTINE:
52 83 90 014B 786 MARK_POINT LOAD_xxxx_1
05 014B 787 MOVB (R3)+,R2 ; Load new fill character
014E 788 RSB
014F 789
014F 790 EOSLOAD_SIGN_ROUTINE:
54 83 90 014F 791 MARK_POINT LOAD_xxxx_2
05 014F 792 MOVB (R3)+,R4 ; Load new sign character into R4
0152 793 RSB
0153 794
0153 795 EOSLOAD_PLUS_ROUTINE:
F8 5B 03 E1 0153 796 BBC #PSL$V_N,R11,EOSLOAD_SIGN_ROUTINE ; Use common code if plus
53 D6 0157 797 INCL R3 ; Otherwise, skip unused character
05 0159 798 RSB
015A 799
015A 800 EOSLOAD_MINUS_ROUTINE:
F1 5B 03 E0 015A 801 BBS #PSL$V_N,R11,EOSLOAD_SIGN_ROUTINE ; Use common code if minus
53 D6 015E 802 INCL R3 ; Otherwise, skip unused character

```

VAXEDITPC  
V04-000

- VAX-11 EDITPC Instruction Emulation<sup>G 9</sup>  
E0\$LOAD\_XXXXXX - Load Register

05 0160 803 RSB

16-SEP-1984 01:35:22  
5-SEP-1984 00:45:19

VAX/VMS Macro V04-00  
[EMULAT.SRC]VAXEDITPC.MAR;1

Page 20  
(14)

VAX  
V04

```
0161 805 .SUBTITLE EO$xxxxxx_SIGNIF - Significance
0161 806 :+
0161 807 : Functional Description:
0161 808 :
0161 809 : The significance indicator (C-bit in auxiliary PSW) is set or
0161 810 : cleared according to the entry point.
0161 811 :
0161 812 : Input Parameters:
0161 813 :
0161 814 : None
0161 815 :
0161 816 : Output Parameters:
0161 817 :
0161 818 : EOS$CLEAR_SIGNIF R11<C> is cleared
0161 819 :
0161 820 : EOS$SET_SIGNIF R11<C> is set
0161 821 :-
0161 822 :
5B 01 8A 0161 823 EOS$CLEAR_SIGNIF_ROUTINE:
05 0164 824 BICB2 #PSL$M_C,R11 ; Clear significance
0165 825 RSB
0165 826
5B 01 88 0165 827 EOS$SET_SIGNIF_ROUTINE:
05 0168 828 BISB2 #PSL$M_C,R11 ; Set significance
0168 829 RSB
```



```

0169 831 .SUBTITLE EO_ADJUST_INPUT - Adjust Input Length
0169 832 :+
0169 833 : Functional Description:
0169 834 :
0169 835 : The pattern operator is followed by an unsigned byte integer length in
0169 836 : the range 1 through 31. If the source string has more digits than
0169 837 : this length, the excess leading digits are read and discarded. If any
0169 838 : discarded digits are non-zero then overflow is set, significance is
0169 839 : set, and zero is cleared. If the source string has fewer digits than
0169 840 : this length, a counter is set of the number of leading zeros to
0169 841 : supply. This counter is stored as a negative number in R0<31:16>.
0169 842 :-
0169 843 :
0169 844 EOS$ADJUST INPUT ROUTINE:
0169 845 MARK POINT ADJUST_INPUT_1
58 58 83 9A 0169 846 MOVZBL (R3)+,R8 ; Get "length" from pattern stream
58 50 58 C3 016C 847 SUBL3 R8,R0,R8 ; Is length larger than input length?
11 1B 0170 848 BLEQU 30$ ; Branch if yes
59 D4 0172 849 CLRL R9 ; Clear count of zeros ('R0<31:16>')
0174 850
0174 851 10$: EO READ ; Get next input digit
5B 06 13 0177 852 BEQL 20$ ; Skip to end of loop if zero
5B 04 8A 0179 853 BICB #PSL$M_Z,R11 ; Otherwise, indicate nonzero
5B 03 88 017C 854 BISB #<PSL$M_C!PSL$M_V>,R11 ; Indicate significance and overflow
F2 58 F5 017F 855 20$: SOBGTR R8,10$ ; Test for end of loop
05 0182 856 RSB
0183 857
59 58 D0 0183 858 30$: MOVL R8,R9 ; Store difference into 'R0<31:16>'
05 0186 859 RSB

```

```
0187 861 .SUBTITLE EO$END - End Edit
0187 862 :+
0187 863 : Functional Description:
0187 864 :
0187 865 : The edit operation is terminated.
0187 866 :
0187 867 : The architectural description of EDITPC divides end processing between
0187 868 : the EO$END routine and code at the end of the main loop. This
0187 869 : implementation performs all of the work in a single place.
0187 870 :
0187 871 : The edit operation is terminated. There are several details that this
0187 872 : routine must take care of.
0187 873 :
0187 874 : 1. The return PC to the main dispatch loop is discarded.
0187 875 :
0187 876 : 2. R3 is backed up to point to the EO$END pattern operator.
0187 877 :
0187 878 : 3. A special check must be made for negative zero to insure that
0187 879 : the N-bit is cleared.
0187 880 :
0187 881 : 4. If any digits still remain in the input string, a reserved
0187 882 : operand abort is taken.
0187 883 :
0187 884 : 5. R2 and R4 are set to zero according to the architecture.
0187 885 :
0187 886 : Input Parameters:
0187 887 :
0187 888 : R0 - Number of digits remaining in input string
0187 889 : R3 - Address of one byte beyond the EO$END operator
0187 890 :
0187 891 : 00(SP) - Return address in dispatch loop in this module (discarded)
0187 892 : 04(SP) - Saved R0
0187 893 : 08(SP) - Saved R1
0187 894 : 12(SP) - Saved R6
0187 895 : 16(SP) - Saved R7
0187 896 : 20(SP) - Saved R8
0187 897 : 24(SP) - Saved R9
0187 898 : 28(SP) - Saved R10
0187 899 : 32(SP) - Saved R11
0187 900 : 36(SP) - Return PC to caller of VAX$EDITPC
0187 901 :
0187 902 : Output Parameters:
0187 903 :
0187 904 : If no overflow has occurred, then this routine exits through the RSB
0187 905 : instruction with the following output parameters:
0187 906 :
0187 907 : These register contents are dictated by the VAX architecture
0187 908 :
0187 909 : R0 - Length in digits of input decimal string
0187 910 : R1 - Address of most significant byte of input decimal string
0187 911 : R2 - Set to zero to conform to architecture
0187 912 : R3 - Backed up one byte to point to EO$END operator
0187 913 : R4 - Set to zero to conform to architecture
0187 914 : R5 - Address of one byte beyond destination character string
0187 915 :
0187 916 : PSL<V> is clear
0187 917 :
```

```

0187 918 : If the V-bit is set, then control is transferred to VAX$EDITPC_OVERFLOW
0187 919 : where a check for decimal overflow exceptions is made.
0187 920 :
0187 921 : The registers are loaded with their correct contents and then saved on
0187 922 : the stack as follows:
0187 923 :
0187 924 :         00(SP) - Saved R0
0187 925 :         04(SP) - Saved R1
0187 926 :         08(SP) - Saved R2
0187 927 :         12(SP) - Saved R3
0187 928 :         16(SP) - Saved R4
0187 929 :         20(SP) - Saved R5
0187 930 :         24(SP) - Saved R6
0187 931 :         28(SP) - Saved R7
0187 932 :         32(SP) - Saved R8
0187 933 :         36(SP) - Saved R9
0187 934 :         40(SP) - Saved R10
0187 935 :         44(SP) - Saved R11
0187 936 :         48(SP) - Return PC to caller of VAX$EDITPC
0187 937 :
0187 938 : PSL<V> is set
0187 939 : -
0187 940 :
0187 941 EO$END_ROUTINE:
0187 942 ADDL #4,SP ; Discard return PC to main loop
03 5B 04 C0 018A 943 DECL R3 ; Back up pattern pointer one byte
03 5B 02 E1 018C 944 BBC #PSL$V_Z,R11,10$ ; Check for negative zero
03 5B 08 8A 0190 945 BICB #PSL$M_N,R11 ; Turn off N-bit if zero
03 5B 50 D5 0193 946 10$: TSTL R0 ; Any digits remaining?
03 5B 5D 12 0195 947 BNEQ EDITPC_ROPRAND_ABORT ; Error if yes
03 5B 59 D5 0197 948 TSTL R9 ; Any zeros (R0<31:16>) remaining?
03 5B 59 12 0199 949 BNEQ EDITPC_ROPRAND_ABORT ; Error if yes
03 5B 52 D4 019B 950 CLRL R2 ; Architecture specifies that R2
03 5B 54 D4 019D 951 CLRL R4 ; and R4 are zero on exit
03 5B 0F B9 019F 952 BICPSW #<PSL$M_N!PSL$M_Z!PSL$M_V!PSL$M_C> ; Clear condition codes
03 5B 5B B8 01A1 953 BISPSW R11 ; Set codes according to saved PSW
03 5B 01 E0 01A3 954 BBS #PSL$V_V,R11,20$ ; Get out of line if overflow
03 5B 0F C3 8F BA 01A7 955 POPR #^M<R0,R1,R6,R7,R8,R9,R10,R11> ; Restore saved registers
03 5B 05 01AB 956 RSB ; Return to caller's caller
03 5B 01AC 957
03 5B 01AC 958 ; At this point, we must determine whether the DV bit is set. The tests that
03 5B 01AC 959 ; must be performed are identical to the tests performed by the overflow
03 5B 01AC 960 ; checking code for the packed decimal routines. In order to make use of
03 5B 01AC 961 ; that code, we need to set up the saved registers on the stack to match
03 5B 01AC 962 ; the input to that routine. Note also that the decimal routines specify
03 5B 01AC 963 ; that R0 is zero on completion while EDITPC dictates that R0 contains the
03 5B 01AC 964 ; initial value of "srclen". For this reason, we cannot simply branch to
03 5B 01AC 965 ; VAX$DECIMAL_EXIT but must use a special entry point.
03 5B 01AC 966
03 5B 03 BA 01AC 967 20$: POPR #^M<R0,R1> ; Restore R0 and R1
03 5B 3F BB 01AE 968 PUSHR #^M<R0,R1,R2,R3,R4,R5> ; ... only to save them again
03 5B 01B0 969
03 5B 01B0 970 ; The condition codes were not changed by the previous two instructions.
03 5B 01B0 971
03 5B FE4D' 31 01B0 972 BRW VAX$EDITPC_OVERFLOW ; Join exit code

```

01B3 974 .SUBTITLE EDITPC\_ROPRAND\_FAULT - Handle Illegal Pattern Operator

01B3 975 :+  
 01B3 976 : Functional Description:  
 01B3 977 :

01B3 978 : This routine stores the intermediate state of an EDITPC instruction  
 01B3 979 : that has been prematurely terminated by an illegal pattern operator.  
 01B3 980 : These exceptions and access violations are the only exceptions from  
 01B3 981 : which execution can continue after the exceptional condition has been  
 01B3 982 : cleared up. After the state is stored in the registers R0 through R5,  
 01B3 983 : control is transferred through VAX\$ROPRAND to VAX\$REFLECT\_FAULT, where  
 01B3 984 : the appropriate backup method is determined, based on the return PC  
 01B3 985 : from the VAX\$EDITPC routine.  
 01B3 986 :

01B3 987 : Input Parameters:  
 01B3 988 :

- 01B3 989 R0 - Current digit count in input string
- 01B3 990 R1 - Address of next digit in input string
- 01B3 991 R2 - Fill character
- 01B3 992 R3 - Address of illegal pattern operator
- 01B3 993 R4 - Sign character (stored in R2<15:8>)
- 01B3 994 R5 - Address of next character to be stored in output character string
- 01B3 995 R9 - Zero count (stored in R0<31:16>)
- 01B3 996 R11 - Condition codes

- 01B3 997
- 01B3 998 00(SP) - Saved R0
- 01B3 999 04(SP) - Saved R1
- 01B3 1000 08(SP) - Saved R6
- 01B3 1001 12(SP) - Saved R7
- 01B3 1002 16(SP) - Saved R8
- 01B3 1003 20(SP) - Saved R9
- 01B3 1004 24(SP) - Saved R10
- 01B3 1005 28(SP) - Saved R11
- 01B3 1006 32(SP) - Return PC from VAX\$EDITPC routine
- 01B3 1007

01B3 1008 : Output Parameters:  
 01B3 1009 :

- 01B3 1010 00(SP) - Offset in packed register array to delta PC byte
- 01B3 1011 04(SP) - Return PC from VAX\$EDITPC routine
- 01B3 1012
- 01B3 1013 Some of the register contents are dictated by the VAX architecture.
- 01B3 1014 Other register contents are architecturally described as "implementation
- 01B3 1015 dependent" and are used to store the instruction state that enables it
- 01B3 1016 to be restarted successfully and complete according to specifications.
- 01B3 1017

01B3 1018 : The following register contents are architecturally specified

- 01B3 1019
- 01B3 1020 R0<15:00> - Current digit count in input string
- 01B3 1021 R0<31:16> - Current zero count (from R9)
- 01B3 1022 R1 - Address of next digit in input string
- 01B3 1023 R2<07:00> - Fill character
- 01B3 1024 R2<15:08> - Sign character (from R4)
- 01B3 1025 R3 - Address of next pattern operator
- 01B3 1026 R5 - Address of next character in output character string
- 01B3 1027

01B3 1028 : The following register contents are peculiar to this implementation

- 01B3 1029
- 01B3 1030 R2<23:16> - Delta-PC (if initiated by exception)

```

01B3 1031 : R2<31:24> - Delta srcaddr (current srcaddr minus initial srcaddr)
01B3 1032 : R4<07:00> - Initial digit count (from saved R0)
01B3 1033 : R4<15:08> - Saved condition codes (for easy retrieval)
01B3 1034 : R4<23:16> - State flags
01B3 1035 : State = EDITPC_2_RESTART
01B3 1036 : FPD bit is set
01B3 1037 : ACCVIO bit is clear
01B3 1038 : R4<31:24> - Unused for this exception (see access violations)
01B3 1039 :
01B3 1040 : EDITPC_2_RESTART is the restart code that causes the instruction
01B3 1041 : to be restarted at the top of the main loop. It is the simplest
01B3 1042 : point at which to resume execution after an illegal pattern
01B3 1043 : operator fault.
01B3 1044 :
01B3 1045 : The condition codes reported in the exception PSL are also defined
01B3 1046 : by the VAX architecture.
01B3 1047 :
01B3 1048 : PSL<N> - Source string has a minus sign
01B3 1049 : PSL<Z> - All digits are zero so far
01B3 1050 : PSL<V> - Nonzero digits have been lost
01B3 1051 : PSL<C> - Significance
01B3 1052 :
01B3 1053 :
01B3 1054 :
01B3 1055 :
01B3 1056 :
01B3 1057 :
01B3 1058 :
01B3 1059 :
01B3 1060 :
01B3 1061 :
01B3 1062 :
01B3 1063 :
01B3 1064 :
01B3 1065 :
01B3 1066 :
01B3 1067 :
01B3 1068 :
01B3 1069 :
01B3 1070 :
01B3 1071 :
01B3 1072 :
01B3 1073 :
01B3 1074 :
01B3 1075 :
01B3 1076 :
01B3 1077 :
01B3 1078 :
01B3 1079 :
01B3 1080 :
01B3 1081 :
01B3 1082 :
01B3 1083 :
01B3 1084 :
01B3 1085 :
01B3 1086 :
01B3 1087 :

```

ASSUME EDITPC\_L\_SAVED\_R1 EQ <EDITPC\_L\_SAVED\_R0 + 4>

EDITPC\_ROPRAND\_FAULT:

```

50 10 OF BB 01B3 1057 PUSHR #*M<R0,R1,R2,R3> ; Save current R0..R3
10 AE 54 7D 01B5 1058 MOVQ EDITPC_L_SAVED_R0(SP),R0 ; Retrieve original R0 and R1
02 AE 59 80 01BD 1060 MOVQ R4,16(SP) ; Save R4 and R5 in right place on s
09 AE 54 90 01BD 1061 ; Now start stuffing the various registers
10 AE 50 90 01BD 1062
51 04 AE 51 C3 01BD 1063 MOVW R9,EDITPC_W_ZERO_COUNT(SP) ; Save R9 in R0<31:16>
08 AE 51 90 01C1 1064 MOVW R4,EDITPC_B_SIGN(SP) ; Save R4 in R2<15:8>
11 AE 5B 90 01C5 1065 MOVW R0,EDITPC_B_INISRCLEN(SP) ; Save initial value of R0
12 AE 12 90 01C9 1066 SUBL3 R1,EDITPC_A_SRCADDR(SP),R1 ; Calculate srcaddr difference
OFFF 8F BA 01CE 1067 MOVW R1,EDITPC_B_DELTA_SRCADDR(SP) ; Store it in R4<15:8>
0000010A 8F DD 01D2 1068 MOVW R11,EDITPC_B_SAVED_PSW(SP) ; Save condition codes
01D6 1069 MOVW #<EDITPC_M_FPD!EDITPC_2_RESTART>,- ; Set the FPD bit
01D8 1070 EDITPC_B_STATE(SP)
01DA 1071 POPR #*M<R0,R1,R2,R3,R4,R5,R6,R7,R8,R9,R10,R11> ; Load registers
01DE 1072 PUSHL #<EDITPC_B_DELTA_PC!- ; Store delta-PC offset
01E4 1073 PACK_M_FPDS ; Indicate that FPD should be set
01E4 1074
01E4 1075
01E4 1076 ; The following is admittedly gross. This is the only code path into
01E4 1077 ; VAX$ROPRAND where the condition codes are significant. All other paths can
01E4 1078 ; store the delta-PC offset without concern for its affect on condition
01E4 1079 ; codes. Fortunately, the POPR instruction does not affect condition codes.
01E4 1080
01E4 1081 ASSUME EDITPC_B_SAVED_PSW EQ 17 ; Make sure we get them from right place
01E4 1082
50 54 04 50 DD 01E4 1083 PUSHL R0 ; Get a scratch register
08 EF 01E6 1084 EXTZV #8,#4,R4,R0 ; Get codes from R4<11:8>
OF B9 01EB 1085 BICPSW #<PSL$M_N!PSL$M_Z!PSL$M_V!PSL$M_C> ; Clear the codes
50 B8 01ED 1086 BISPSW R0 ; Set relevant condition codes
01 01 BA 01EF 1087 POPR #*M<R0> ; Restore R0, preserving PSW

```

VAXEDITPC  
V04-000

N 9  
- VAX-11 EDITPC Instruction Emulation 16-SEP-1984 01:35:22 VAX/VMS Macro V04-00  
EDITPC\_ROPRAND\_FAULT - Handle Illegal Pa 5-SEP-1984 00:45:19 [EMULAT.SRC]VAXEDITPC.MAC;1 Page 27  
FEOC' 31 01F1 1088 BRW VAX\$ROPRAND ; Continue exception handling (18)

VAX  
V04

```

01F4 1090      .SUBTITLE      EDITPC_ROPRAND_ABORT - Abnormally Terminate Instruction
01F4 1091      :-
01F4 1092      Functional Description:
01F4 1093      This routine reports a reserved operand abort back to the caller.
01F4 1094      Reserved operand aborts are trivial to handle because they cannot be
01F4 1095      continued. There is no need to pack intermediate state into the
01F4 1096      general registers. Those registers that should not be modified by the
01F4 1097      EDITPC instruction have their contents restored. Control is then
01F4 1098      passed to VAX$ROPRAND, which takes the necessary steps to eventually
01F4 1099      reflect the exception back to the caller.
01F4 1100      The following conditions cause a reserved operand abort
01F4 1101      1. Input digit count GTRU 31
01F4 1102      (This condition is detected by the EDITPC initialization code.)
01F4 1103      2. Not enough digits in source string to satisfy pattern operators
01F4 1104      (This condition is detected by the EO_READ routine.)
01F4 1105      3. Too many digits in source string (digits left over)
01F4 1106      (This condition is detected by the EO$END routine.)
01F4 1107      4. An EO$END operator was encountered while zero count was nonzero
01F4 1108      (This condition is also detected by the EO$END routine.)
01F4 1109      Input Parameters:
01F4 1110      00(SP) - Saved R0
01F4 1111      04(SP) - Saved R1
01F4 1112      08(SP) - Saved R6
01F4 1113      12(SP) - Saved R7
01F4 1114      16(SP) - Saved R8
01F4 1115      20(SP) - Saved R9
01F4 1116      24(SP) - Saved R10
01F4 1117      28(SP) - Saved P11
01F4 1118      32(SP) - Return PC from VAX$EDITPC routine
01F4 1119      Output Parameters:
01F4 1120      The contents of R0 through R5 are not important because the
01F4 1121      architecture states that they are UNPREDICTABLE if a reserved
01F4 1122      operand abort occurs. No effort is made to put these registers
01F4 1123      into a consistent state.
01F4 1124      R6 through R11 are restored to their values when the EDITPC
01F4 1125      instruction began executing.
01F4 1126      00(SP) - Offset in packed register array to delta PC byte
01F4 1127      04(SP) - Return PC from VAX$EDITPC routine
01F4 1128      Implicit Output:
01F4 1129      This routine passes control to VAX$ROPRAND where further
01F4 1130      exception processing takes place.
01F4 1131      :-
01F4 1132
01F4 1133
01F4 1134
01F4 1135
01F4 1136
01F4 1137
01F4 1138
01F4 1139
01F4 1140
01F4 1141
01F4 1142
01F4 1143
01F4 1144
01F4 1145
01F4 1146      :-
  
```

		01F4	1147						
		01F4	1148	EDITPC_ROPRAND_ABORT:					
0FC3	8F	BA	01F4	1149	POPR	#^M<R0,R1,R6,R7,R8,R9,R10,R11>	:	Restore saved registers	
	OA	DD	01F8	1150	PUSHL	#EDITPC_B DELTA_PC	:	Store delta-PC offset	
FE03'		31	01FA	1151	BRW	VAX\$ROPRAND	:	Continue exception handling	



```

01FD 1153 .SUBTITLE EDITPC_ACCVIO - Reflect an Access Violation
01FD 1154 :
01FD 1155 :+ Functional Description:
01FD 1156 :
01FD 1157 : This routine receives control when an access violation occurs while
01FD 1158 : executing within the EDITPC emulator. This routine determines whether
01FD 1159 : the exception occurred while accessing the source decimal string, the
01FD 1160 : pattern stream, or the output character string. (This check is made
01FD 1161 : based on the PC of the exception.)
01FD 1162 :
01FD 1163 : If the PC is one that is recognized by this routine, then the state of
01FD 1164 : the instruction (character counts, string addresses, and the like) are
01FD 1165 : restored to a state where the instruction/routine can be restarted
01FD 1166 : after (if) the cause for the exception is eliminated. Control is then
01FD 1167 : passed to a common routine that sets up the stack and the exception
01FD 1168 : parameters in such a way that the instruction or routine can restart
01FD 1169 : transparently.
01FD 1170 :
01FD 1171 : If the exception occurs at some unrecognized PC, then the exception is
01FD 1172 : reflected to the user as an exception that occurred within the
01FD 1173 : emulator.
01FD 1174 :
01FD 1175 : There are two exceptions that can occur that are not backed up to
01FD 1176 : appear as if they occurred at the site of the original emulated
01FD 1177 : instruction. These exceptions will appear to the user as if they
01FD 1178 : occurred inside the emulator itself.
01FD 1179 :
01FD 1180 : 1. If stack overflow occurs due to use of the stack by one of
01FD 1181 : the routines, it is unlikely that this routine will even
01FD 1182 : execute because the code that transfers control here must
01FD 1183 : first copy the parameters to the exception stack and that
01FD 1184 : operation would fail. (The failure causes control to be
01FD 1185 : transferred to VMS, where the stack expansion logic is
01FD 1186 : invoked and the routine resumed transparently.)
01FD 1187 :
01FD 1188 : 2. If assumptions about the address space change out from under
01FD 1189 : these routines (because an AST deleted a portion of the
01FD 1190 : address space or a similar silly thing), the handling of the
01FD 1191 : exception is UNPREDICTABLE.
01FD 1192 :
01FD 1193 : Input Parameters:
01FD 1194 :
01FD 1195 : R0 - Value of SP when exception occurred
01FD 1196 : R1 - PC at which exception occurred
01FD 1197 : R2 - scratch
01FD 1198 : R3 - scratch
01FD 1199 : R10 - Address of this routine (no longer needed)
01FD 1200 :
01FD 1201 : 00(SP) - Value of R0 when exception occurred
01FD 1202 : 04(SP) - Value of R1 when exception occurred
01FD 1203 : 08(SP) - Value of R2 when exception occurred
01FD 1204 : 12(SP) - Value of R3 when exception occurred
01FD 1205 : 16(SP) - Return PC in exception dispatcher in operating system
01FD 1206 :
01FD 1207 : 20(SP) - First longword of system-specific exception data
01FD 1208 :
01FD 1209 :
  
```

```

01FD 1210 : xx(SP) - Last longword of system-specific exception data
01FD 1211 :
01FD 1212 : The address of the next longword is the position of the stack when
01FD 1213 : the exception occurred. R0 locates this address.
01FD 1214 :
01FD 1215 : R0 -> xx+4(SP) - Instruction-specific data
01FD 1216 : . - Optional instruction-specific data
01FD 1217 : . - Optional instruction-specific data
01FD 1218 : xx+<4*M>(SP) - Return PC from VAX$EDITPC routine (M is the number
01FD 1219 : of instruction-specific longwords)
01FD 1220 :
01FD 1221 : Implicit Input:
01FD 1222 :
01FD 1223 : It is assumed that the contents of all registers coming into this
01FD 1224 : routine are unchanged from their contents when the exception occurred.
01FD 1225 : (For R0 through R3, this assumption applies to the saved register
01FD 1226 : contents on the top of the stack. Any modification to these four
01FD 1227 : registers must be made to their saved copies and not to the registers
01FD 1228 : themselves.)
01FD 1229 :
01FD 1230 : It is further assumed that the exception PC is within the bounds of
01FD 1231 : this module. (Violation of this assumption is simply an inefficiency.)
01FD 1232 :
01FD 1233 : Finally, the macro BEGIN_MARK_POINT should have been invoked at the
01FD 1234 : beginning of this module to define the symbols
01FD 1235 :
01FD 1236 : MODULE_BASE
01FD 1237 : PC_TABLE_BASE
01FD 1238 : HANDLER_TABLE_BASE
01FD 1239 : TABLE_SIZE
01FD 1240 :
01FD 1241 : Output Parameters:
01FD 1242 :
01FD 1243 : If the exception is recognized (that is, if the exception PC is
01FD 1244 : associated with one of the mark points), control is passed to the
01FD 1245 : context-specific routine that restores the instruction state to a
01FD 1246 : uniform point from which the EDITPC instruction can be restarted.
01FD 1247 :
01FD 1248 : R0 - Value of SP when exception occurred
01FD 1249 : R1 - scratch
01FD 1250 : R2 - scratch
01FD 1251 : R3 - scratch
01FD 1252 : R10 - scratch
01FD 1253 :
01FD 1254 : VAX$EDITPC is different from the other emulated instructions in that
01FD 1255 : it requires intermediate state to be stored in R4 and R5 as well as R0
01FD 1256 : through R3. This requires that R4 and R5 also be saved on the stack so
01FD 1257 : that they can be manipulated in a consistent fashion.
01FD 1258 :
01FD 1259 : 00(SP) - Value of R0 when exception occurred
01FD 1260 : 04(SP) - Value of R1 when exception occurred
01FD 1261 : 08(SP) - Value of R2 when exception occurred
01FD 1262 : 12(SP) - Value of R3 when exception occurred
01FD 1263 : 16(SP) - Value of R4 when exception occurred
01FD 1264 : 20(SP) - Value of R5 when exception occurred
01FD 1265 : 24(SP) - Value of R0 when exception occurred
01FD 1266 : 28(SP) - Value of R1 when exception occurred
  
```



```

0231 1320      .SUBTITLE      Access Violation While Reading Input Digit
0231 1321      :+
0231 1322      : EO_READ Packing Routine
0231 1323      :
0231 1324      : Functional Description:
0231 1325      :
0231 1326      :     This routine executes if an access violation occurred in the EO_READ
0231 1327      :     subroutine while accessing the input packed decimal string.
0231 1328      :
0231 1329      : Input Parameters:
0231 1330      :
0231 1331      :     R0 - Address of top of stack when access violation occurred
0231 1332      :
0231 1333      :     00(R0) - Return PC to caller of EO_READ
0231 1334      :     04(R0) - Return PC to main VAX$EDITPC control loop
0231 1335      :     08(R0) - Saved R0
0231 1336      :     12(R0) - Saved R1
0231 1337      :     etc.
0231 1338      :
0231 1339      : Output Parameters:
0231 1340      :
0231 1341      :     If the caller of this routine a recognized restart point, the restart
0231 1342      :     code is stored in EDITPC_B_STATE in the saved register array, the
0231 1343      :     psuedo stack pointer R0 is advanced by one, and control is passed to
0231 1344      :     the general EDITPC_PACK routine for final exception processing.
0231 1345      :
0231 1346      :     R0 is advanced by one longword
0231 1347      :
0231 1348      :     00(R0) - Return PC to main VAX$EDITPC control loop
0231 1349      :     04(R0) - Saved R0
0231 1350      :     08(R0) - Saved R1
0231 1351      :     etc.
0231 1352      :
0231 1353      :     EDITPC_B_STATE(SP) - Code that uniquely determines the caller
0231 1354      :     of EO_READ when the access violation was detected.
0231 1355      :
0231 1356      :     If the caller's PC is not recognized, the exception is dismissed from
0231 1357      :     further modification.
0231 1358      :
0231 1359      :-
0231 1360      READ_1:
0231 1361      READ_2:
0231 1362      CLRL   R2                ; Set table index to zero
0231 1363      PUSHAB MODULE_BASE      ; Prepare for PIC arithmetic
0231 1364      SUBL3  (SP)+,(R0)+,R1    ; R1 contains relative PC
0231 1365      SUBL2  #3,R1          ; Back up over BSBW instruction
0231 1366      :
0231 1367      40$:  CMPW   R1,RESTART_PC_TABLE_BASE[R2] ; Check next PC offset
0231 1368      BEQL   50$              ; Exit loop if match
0231 1369      AOBLS  #RESTART_TABLE_SIZE,R2,40$ ; Check for end of loop
0231 1370      :
0231 1371      : If we drop through this loop, we got into the EO_READ subroutine from
0231 1372      : other than one of the three known call sites. We pass control back to
0231 1373      : the general exception dispatcher.
0231 1374      :
0231 1375      BRB   20$                ; Join common code to dismiss exception
0231 1376

```

```

          52   D4
          FDC9 CF 9F
51      80   8E  C3
          51   03  C2
0000'CF42 51  B1
          06   13
          F4 52 0C  F2
          D1   11
          024A 1370
          024A 1371
          024A 1372
          024A 1373
          024A 1374
          D1   11 024A 1375
          024C 1376

```

VA  
Ps  
  
PS  
--  
SA  
V  
PC  
HA  
RE  
  
Ph  
--  
In  
Col  
Pa  
Syl  
Pa  
Syl  
Ps  
Cri  
As  
  
Th  
34  
Th  
18  
20  
  
Ma  
--  
-\$  
-\$  
TO  
  
25  
Th  
MA

```
024C 1377 ; Store the restart code appropriate to the return PC and join common code to
024C 1378 ; store the rest of the instruction state into the saved register array.
024C 1379
024C 1380 ASSUME EDITPC_V_STATE EQ 0
024C 1381
12 AE 52 01 81 024C 1382 50$: ADDB3 #1,R2,EDITPC_B_STATE(SP) ; Restart code base is 1, not 0
6E B6 0251 1383 INCW EDITPC_W_SRCLEN(SP) ; Digit never got read
2E 11 0253 1384 BRB 70$ ; Make sure that R8 is saved
```

```

0255 1386      .SUBTITLE      Access Violation While Executing Loop
0255 1387      :+
0255 1388      : Packing Routine for Storage Loops
0255 1389      :
0255 1390      : Functional Description:
0255 1391      :
0255 1392      : All of the following labels are associated with exceptions that occur
0255 1393      : inside a loop that is reading digits from the input stream and
0255 1394      : optionally storing these or other characters in the output string.
0255 1395      : While it is a trivial matter to back up the output pointer and restart
0255 1396      : the loop from the beginning, it is somewhat more difficult to handle
0255 1397      : all of the cases that can occur with the input packed decimal string
0255 1398      : (because a byte can contain two digits). To avoid this complication,
0255 1399      : we add the ability to restart the various loops where they left off.
0255 1400      : In order to accomplish this, we need to store the loop count and,
0255 1401      : optionally, the latest input digit in the intermediate state array.
0255 1402      :
0255 1403      : The two entry points where the contents of R7 (the last digit read
0255 1404      : from the input stream) are significant are MOVE_2 and FLOAT_3. All
0255 1405      : other entry points ignore the contents of R7. (Note that these two
0255 1406      : entry points exit through label 60$ to store R7 in the saved register
0255 1407      : array.)
0255 1408      :
0255 1409      : Input Parameters:
0255 1410      :
0255 1411      : R0 - Address of top of stack when access violation occurred
0255 1412      : R7 - Latest digit read from input stream (MOVE_2 and FLOAT_3 only)
0255 1413      : R8 - Remaining loop count
0255 1414      :
0255 1415      : 00(R0) - Return PC to main VAX$EDITPC control loop
0255 1416      : 04(R0) - Saved R0
0255 1417      : 08(R0) - Saved R1
0255 1418      : etc.
0255 1419      :
0255 1420      : Output Parameters:
0255 1421      :
0255 1422      : A restart code that is unique for each entry is stored in the saved
0255 1423      : register array. The loop count (and the latest input digit, if
0255 1424      : appropriate) is also stored before passing control to EDITPC_PACK.
0255 1425      :
0255 1426      : EDITPC_B_STATE(SP) - Code that uniquely determines the code that
0255 1427      : was executing when the access violation was detected.
0255 1428      :
0255 1429      : EDITPC_B_EO_READ_CHAR(SP) - Latest digit read from the input string
0255 1430      :
0255 1431      : EDITPC_B_LOOP_COUNT(SP) - Remaining loop count
0255 1432      :
0255 1433      : Side Effects:
0255 1434      :
0255 1435      : R0 is unchanged by this code path
0255 1436      : -
0255 1437      :
0255 1438      : ASSUME EDITPC_V_STATE EQ 0
0255 1439      :
0255 1440      : FILL_2:
12 AE 03 90 0255 1441      MOVB    #FILL_2_RESTART,EDITPC_B_STATE(SP)
28 11 0259 1442      BRB     70$

```

			025B	1443				
			025B	1444	MOVE_2:			
12	AE	05	90	025B	1445	MOV	#MOVE_2_RESTART,EDITPC_B_STATE(SP)	
		1E	11	025F	1446	BRB	60\$	
				0261	1447			
				0261	1448	MOVE_3:		
12	AE	06	90	0261	1449	MOV	#MOVE_3_RESTART,EDITPC_B_STATE(SP)	
		1C	11	0265	1450	BRB	70\$	
				0267	1451			
				0267	1452	FLOAT_2:		
12	AE	08	90	0267	1453	MOV	#FLOAT_2_RESTART,EDITPC_B_STATE(SP)	
		12	11	0268	1454	BRB	60\$	
				026D	1455			
				026D	1456	FLOAT_3:		
12	AE	09	90	026D	1457	MOV	#FLOAT_3_RESTART,EDITPC_B_STATE(SP)	
		0C	11	0271	1458	BRB	60\$	
				0273	1459			
				0273	1460	FLOAT_4:		
12	AE	0A	90	0273	1461	MOV	#FLOAT_4_RESTART,EDITPC_B_STATE(SP)	
		0A	11	0277	1462	BRB	70\$	
				0279	1463			
				0279	1464	BLANK_ZERO_2:		
12	AE	0B	90	0279	1465	MOV	#BLANK_ZERO_2_RESTART,EDITPC_B_STATE(SP)	
		04	11	027D	1466	BRB	70\$	
				027F	1467			
01	AE	57	90	027F	1468	60\$:	MOV	R7,EDITPC_B_EO_READ_CHAR(SP) ; Save result of latest read
13	AE	58	90	0283	1469	70\$:	MOV	R8,EDITPC_B_LOOP_COUNT(SP) ; Save loop counter
		16	11	0287	1470	BRB	80\$	

```
0289 1472            .SUBTITLE            Access Violation in Initialization Code
0289 1473            :+
0289 1474            : Functional Description:
0289 1475            :
0289 1476            :            An access violation at EDITPC_1 indicates that the byte containing the
0289 1477            :            sign of the input packed decimal string could not be read. There is
0289 1478            :            little state to preserve. The key step here is to store a restart code
0289 1479            :            that differentiates this exception from the large number that can be
0289 1480            :            restarted at the top of the command loop.
0289 1481            :
0289 1482            : Input Parameters:
0289 1483            :
0289 1484            :            00(R0) - Saved R0
0289 1485            :            04(R0) - Saved R1
0289 1486            :            etc.
0289 1487            :
0289 1488            : Output Parameter:
0289 1489            :
0289 1490            :            EDITPC_B_STATE(SP) - Code that indicates that instruction should
0289 1491            :            be restarted at point where sign "digit" is fetched.
0289 1492            :-
0289 1493            :            ASSUME EDITPC_V_STATE EQ 0
0289 1494            :
12 AE    01    90    0289 1495 EDITPC_1:
          13    11    0289 1496            MOVB    #EDITPC_1_RESTART,EDITPC_B_STATE(SP)
                          028D 1497            BRB     EDITPC_PACK
```



```

028F 1499 .SUBTITLE Simple Access Violation
028F 1500 :+
028F 1501 : Functional Description:
028F 1502 :
028F 1503 : This routine handles all of the simple access violations, those that
028F 1504 : can be backed up to the same intermediate state. In general, an access
028F 1505 : violation occurred in one of the simpler routines or at some other
028F 1506 : point where it is not difficult to back up the EDITPC operation to the
028F 1507 : top of the main dispatch loop.
028F 1508 :
028F 1509 : Input Parameters:
028F 1510 :
028F 1511 : R3 - Points one byte beyond current pattern operator (except for
028F 1512 : REPLACE_SIGN_2 where it is one byte further along)
028F 1513 :
028F 1514 : 00(R0) - TOP_OF_LOOP (Return PC to main VAX$EDITPC control loop)
028F 1515 : 04(R0) - Saved R0
028F 1516 : 08(R0) - Saved R1
028F 1517 : etc.
028F 1518 :
028F 1519 : Output Parameters:
028F 1520 :
028F 1521 : R3 must be decremented to point to the pattern operator that was being
028F 1522 : processed when the exception occurred. The return PC must be
028F 1523 : "discarded" to allow the registers to be restored and the return PC
028F 1524 : from VAX$EDITPC to be located.
028F 1525 :
028F 1526 : R3 - Points to current pattern operator
028F 1527 :
028F 1528 : 00(R0) - Saved R0
028F 1529 : 04(R0) - Saved R1
028F 1530 : etc.
028F 1531 :
028F 1532 : Output Parameter:
028F 1533 :
028F 1534 : EDITPC_B_STATE(SP) - The restart point called EDITPC_2 is the place
028F 1535 : from which all "simple" access violations are restarted.
028F 1536 : This is essentially the location TOP_OF_LOOP.
028F 1537 :-
028F 1538 :
028F 1539 END_FLOAT 1:
05 5B 00 E4 028F 1540 BBSC #PSL$V_C,R11,75$ ; Clear saved C-bit before restarting
03 11 0293 1541 BRB 75$ ; We should never get here but ...
0295 1542
0295 1543 REPLACE_SIGN_2:
0C AE D7 0295 1544 -DECL EDITPC_A_PATTERN(SP) ; Back up to "length" byte
0298 1545
0298 1546 EDITPC_3:
0298 1547 EDITPC_4:
0298 1548 EDITPC_5:
0298 1549
0298 1550 INSERT_1:
0298 1551 INSERT_2:
0298 1552
0298 1553 STORE_SIGN_1:
0298 1554
0298 1555 FILL_1:

```

```

0298 1556
0298 1557 MOVE_1:
0298 1558
0298 1559 FLOAT_1:
0298 1560
0298 1561 BLANK_ZERO_1:
0298 1562
0298 1563 REPLACE_SIGN_1:
0298 1564
0298 1565 LOAD_xxxx_1:
0298 1566 LOAD_xxxx_2:
0298 1567
0298 1568 ADJUST_INPUT_1:
0298 1569
0C AE D7 0298 1570 75$: DECL EDITPC_A_PATTERN(SP) ; Back up to current pattern operator
0298 1571
0298 1572 EDITPC_2:
0298 1573 MOV B #EDITPC_2_RESTART,- ; Store special restart code
12 AE 90 0298 1574 EDITPC_B_STATE(SP)
50 04 C0 029F 1575 80$: ADDL #4,RO ; Discard return PC
02A2 1576 ; ... and drop through to EDITPC_PACK
02A2 1577
02A2 1578 .DISABLE LOCAL_BLOCK

```

```

02A2 1580      .SUBTITLE      EDITPC_PACK - Store EDITPC Intermediate State
02A2 1581      :+
02A2 1582      : Functional Description:
02A2 1583      :
02A2 1584      : This routine stores the intermediate state of an EDITPC instruction
02A2 1585      : that has been prematurely terminated by an access violation. These
02A2 1586      : exceptions and illegal pattern operators are the only exceptions from
02A2 1587      : which execution can continue after the exceptional condition has been
02A2 1588      : cleared up. After the state is stored in the registers R0 through R5,
02A2 1589      : control is transferred to VAX$REFLECT_FAULT, where the appropriate
02A2 1590      : backup method is determined, based on the return PC from the
02A2 1591      : VAX$EDITPC routine.
02A2 1592      :
02A2 1593      : Input Parameters:
02A2 1594      :
02A2 1595      : R0 - Current digit count in input string
02A2 1596      : R1 - Address of next digit in input string
02A2 1597      : R2 - Fill character
02A2 1598      : R3 - Address of current pattern operator
02A2 1599      : R4 - Sign character (stored in R2<15:8>)
02A2 1600      : R5 - Address of next character to be stored in output character string
02A2 1601      : R9 - Zero count (stored in R0<31:16>)
02A2 1602      : R11 - Condition codes
02A2 1603      :
02A2 1604      : 00(R0) - Saved R0
02A2 1605      : 04(R0) - Saved R1
02A2 1606      : 08(R0) - Saved R6
02A2 1607      : 12(R0) - Saved R7
02A2 1608      : 16(R0) - Saved R8
02A2 1609      : 20(R0) - Saved R9
02A2 1610      : 24(R0) - Saved R10
02A2 1611      : 28(R0) - Saved R11
02A2 1612      : 32(R0) - Return PC from VAX$EDITPC routine
02A2 1613      :
02A2 1614      : Output Parameters:
02A2 1615      :
02A2 1616      : R0 - Address of return PC from VAX$EDITPC routine
02A2 1617      :
02A2 1618      : 00(R0) - Return PC from VAX$EDITPC routine
02A2 1619      :
02A2 1620      : Some of the register contents are dictated by the VAX architecture.
02A2 1621      : Other register contents are architecturally described as "implementation
02A2 1622      : dependent" and are used to store the instruction state that enables it
02A2 1623      : to be restarted successfully and complete according to specifications.
02A2 1624      :
02A2 1625      : The following register contents are architecturally specified
02A2 1626      :
02A2 1627      : R0<15:00> - Current digit count in input string
02A2 1628      : R0<31:16> - Current zero count (from R9)
02A2 1629      : R1 - Address of next digit in input string
02A2 1630      : R2<07:00> - Fill character
02A2 1631      : R2<15:08> - Sign character (from R4)
02A2 1632      : R3 - Address of current pattern operator
02A2 1633      : R5 - Address of next character in output character string
02A2 1634      :
02A2 1635      : The following register contents are peculiar to this implementation
02A2 1636      :

```

```

02A2 1637 : R2<23:16> - Delta-PC (if initiated by exception)
02A2 1638 : R2<31:24> - Delta src ddr (current srcaddr minus initial srcaddr)
02A2 1639 : R4<07:00> - Initial digit count (from saved R0)
02A2 1640 : R4<15:08> - Saved condition codes (for easy retrieval)
02A2 1641 : R4<23:16> - State flags
02A2 1642 : State field determines the restart point
02A2 1643 : FPD bit is set
02A2 1644 : ACCVIO bit is set
02A2 1645 : R4<31:24> - Unused for this exception (see access violations)
02A2 1646 :
02A2 1647 : The condition codes are not architecturally specified by the VAX
02A2 1648 : architecture for an access violation. The following list applies to
02A2 1649 : some but not all of the points where an access violation can occur.
02A2 1650 :
02A2 1651 : PSL<N> - Source string has a minus sign
02A2 1652 : PSL<Z> - All digits are zero so far
02A2 1653 : PSL<V> - Nonzero digits have been lost
02A2 1654 : PSL<C> - Significance
02A2 1655 :-
02A2 1656 :
02A2 1657 : ASSUME EDITPC_L_SAVED_R1 EQ <EDITPC_L_SAVED_R0 + 4>
02A2 1658 :
02A2 1659 EDITPC_PACK:
02A2 1660 :
02A2 1661 ; Now start stuffing the various registers
02A2 1662 :
53 02 AE 59 80 02A2 1663 MOVW R9,EDITPC_W_ZERO_COUNT(SP) ; Save R9 in R0<31:16>
09 AE 54 90 02A6 1664 MOVB R4,EDITPC_B_SIGNT(SP) ; Save R4 in R2<15:8>
52 80 7D 02AA 1665 MOVQ (R0)+,R2 ; Get initial R0/R1 to R2/R3
10 AE 52 90 02AD 1666 MOVB R2,EDITPC_B_INISRCLEN(SP) ; Save initial value of R0
04 AE 53 C3 02B1 1667 SUBL3 R3,EDITPC_A_SRCADDR(SP),R3 ; Calculate srcaddr difference
08 AE 53 90 02B6 1668 MOVB R3,EDITPC_B_DELTA_SRCADDR(SP) ; Store it in R4<15:8>
11 AE 58 90 02BA 1669 MOVB R11,EDITPC_B_SAVED_PSW(SP) ; Save condition codes
12 AE 10 88 02BE 1670 BISB #EDITPC_M_FPD,EDITPC_B_STATE(SP) ; Set the FPD bit
02C2 1671 :
02C2 1672 ; Restore the remaining registers
02C2 1673 :
56 80 7D 02C2 1674 MOVQ (R0)+,R6 ; Restore R6 and R7
58 80 7D 02C5 1675 MOVQ (R0)+,R8 ; ... and R8 and R9
5A 80 7D 02C8 1676 MOVQ (R0)+,R10 ; ... and R10 and R11
02CB 1677 :
02CB 1678 ; Get rid of the extra copy of saved registers on the stack
02CB 1679 :
10 AE 8E 7D 02CB 1680 MOVQ (SP)+,16(SP) ; Copy the saved R0/R1 pair
10 AE 8E 7D 02CF 1681 MOVQ (SP)+,16(SP) ; ... and the saved R2/R3 pair
54 8E 7D 02D3 1682 MOVQ (SP)+,R4 ; R4 and R5 can be themselves
02D6 1683 :
02D6 1684 ; R1 contains delta-PC offset and indicates that FPD gets set
02D6 1685 :
51 000030A 8F D0 02D6 1686 MOVL #<EDITPC_B_DELTA_PC!- ; Locate delta-PC offset
02DD 1687 PACK_M_FPD!- ; Set FPD bit in exception PSL
02DD 1688 PACK_M-ACCVIO>,R1 ; Indicate an access violation
FD20' 31 02DD 1689 BRW VAX$REFLECT_FAULT ; Reflect fault to caller


```

02E0 1691                    .SUBTITLE                    EDITPC\_RESTART - Unpack and Restart EDITPC Instruction

02E0 1692                    :+  
 02E0 1693                    : Functional Description:

02E0 1694                    :  
 02E0 1695                    :        This routine receives control when an EDITPC instruction is restarted.  
 02E0 1696                    :        The instruction state (stack and general registers) is restored to the  
 02E0 1697                    :        point where it was when the instruction (routine) was interrupted and  
 02E0 1698                    :        control is passed back to the top of the control loop or to another  
 02E0 1699                    :        restart point.

02E0 1700                    :  
 02E0 1701                    : Input Parameters:



02E0 1718                    : Depending on where the exception occurred, some of these parameters  
 02E0 1719                    : may not be relevant. They are nevertheless stored as if they were  
 02E0 1720                    : valid to make this restart code as simple as possible.

02E0 1722                    : These register fields are more or less architecturally defined. They  
 02E0 1723                    : are strictly specified for a reserved operand fault (illegal pattern  
 02E0 1724                    : operator) and it makes sense to use the same register fields for  
 02E0 1725                    : access violations as well.

- 02E0 1727                    :        R0<07:00> - Current digit count in input string
- 02E0 1728                    :                    (see EO\_READ\_CHAR below)
- 02E0 1729                    :        R0<31:16> - Current zero count (loaded into R9)
- 02E0 1730                    :        R1        - Address of next digit in input string
- 02E0 1731                    :        R2<07:00> - Fill character
- 02E0 1732                    :        R2<15:08> - Sign character (loaded into R4)
- 02E0 1733                    :        R3        - Address of next pattern operator
- 02E0 1734                    :        R5        - Address of next character in output character string

02E0 1735                    :  
 02E0 1736                    :        These register fields are specific to this implementation.

- 02E0 1738                    :        R0<15:08> - Latest digit from input string (loaded into R7)
- 02E0 1739                    :        R2<23:16> - Size of instruction (Unused by this routine)
- 02E0 1740                    :        R2<31:24> - Delta srcaddr (used to compute saved R1)
- 02E0 1741                    :        R4<07:00> - Initial digit count (stored in saved R0)
- 02E0 1742                    :        R4<15:08> - Saved condition codes (stored in R11)
- 02E0 1743                    :                    PSL<N> - Source string has a minus sign
- 02E0 1744                    :                    PSL<Z> - All digits are zero so far
- 02E0 1745                    :                    PSL<V> - Nonzero digits have been lost
- 02E0 1746                    :                    PSL<C> - Significance
- 02E0 1747                    :        R4<23:16> - State flags

```

02E0 1748 : State field determines the restart point
02E0 1749 : R4<31:24> - Loop count (loaded into R8)
02E0 1750 :
02E0 1751 : 00(SP) - Return PC from VAX$EDITPC routine
02E0 1752 :
02E0 1753 : Implicit Input:
02E0 1754 :
02E0 1755 : Note that the initial 'srclen' is checked for legality before any
02E0 1756 : restartable exception can occur. This means that R0 LEQU 31, which
02E0 1757 : leaves bits <15:5> free for storing intermediate state. In the case of
02E0 1758 : an access violation, R0<15:8> is used to store the latest digit read
02E0 1759 : from the input stream. In the case of an illegal pattern operator,
02E0 1760 : R0<15:5> are not used so that the architectural requirement that
02E0 1761 : R0<15:0> contain the current byte count is adhered to.
02E0 1762 :
02E0 1763 : Output Parameters:
02E0 1764 :
02E0 1765 : All of the registers are loaded, even if some of their contents are
02E0 1766 : not relevant to the particular point at which the instruction will be
02E0 1767 : restarted. This makes the output of this routine conditional on a
02E0 1768 : single thing, namely on whether the restart point is in one of the
02E0 1769 : pattern-specific routines or in the outer VAX$EDITPC routine. This
02E0 1770 : comment applies especially to R7 and R8.
02E0 1771 :
02E0 1772 : R0 - Current digit count in input string
02E0 1773 : R1 - Address of next digit in input string
02E0 1774 : R2 - Fill character
02E0 1775 : R3 - Address of next pattern operator
02E0 1776 : R4 - Sign character (stored in R2<15:8>)
02E0 1777 : R5 - Address of next character to be stored in output character string
02E0 1778 : R6 - Scratch
02E0 1779 : R7 - Latest digit read from input packed decimal string
02E0 1780 : R8 - Loop count
02E0 1781 : R9 - Zero count (stored in R0<31:16>)
02E0 1782 : R10 - Address of EDITPC_ACCVIO, this module's 'condition handler'
02E0 1783 : R11 - Condition codes
02E0 1784 :
02E0 1785 : 00(SP) - Saved R0
02E0 1786 : 04(SP) - Saved R1
02E0 1787 : 08(SP) - Saved R6
02E0 1788 : 12(SP) - Saved R7
02E0 1789 : 16(SP) - Saved R8
02E0 1790 : 20(SP) - Saved R9
02E0 1791 : 24(SP) - Saved R10
02E0 1792 : 28(SP) - Saved R11
02E0 1793 : 32(SP) - Return PC from VAX$EDITPC routine
02E0 1794 :
02E0 1795 : Side Effects:
02E0 1796 :
02E0 1797 : R6 is assumed unimportant and is used as a scratch register by this
02E0 1798 : routine as soon as it is saved.
02E0 1799 : -
02E0 1800 :
02E0 1801 : VAX$EDITPC_RESTART:
OFFF 8F BB 02E0 1802 : PUSHR #*M<R0,R1,R2,R3,R4,R5,R6,R7,R8,R9,R10,R11> ; Save them all
02E4 1803 : ESTABLISH HANDLER EDITPC_ACCVIO ; Reload R10 with handler address
50 50 9A 02E9 1804 : MOVZBL R0,R0 ; Clear out R0<31:8>

```

```

54 09 AE 9A 02EC 1805      MOVZBL EDITPC_B_SIGN(SP),R4      ; Put 'sign' back into R4
      00 EF 02F0 1806      EXTZV  #EDITPC_V_STATE,-
      04      02F2 1807      #EDITPC_S_STATE,-
56 12 AE      02F3 1808      EDITPC_B_STATE(SP),R6      ; Put restart code into R6
           02F6 1809
      02F6 1810      ; The following two values are not used on all restart paths but R7 and R8
      02F6 1811      ; are loaded unconditionally to make this routine simpler. The most extreme
      02F6 1812      ; example is that R7 gets recalculated below for the EDITPC_1 restart point.
      02F6 1813
57 01 AE 9A 02F6 1814      MOVZBL EDITPC_B_EO_READ_CHAR(SP),R7  ; Get latest input digit
58 13 AE 9A 02FA 1815      MOVZBL EDITPC_B_LOOP_COUNT(SP),R8   ; Restore loop count
59 02 AE 32 02FE 1816      CVTWL  EDITPC_W_ZERO_COUNT(SP),R9  ; Reset zero count (R9 LSS 0)
5B 11 AE 9A 0302 1817      MOVZBL EDITPC_B_SAVED_PSW(SP),R11   ; Restore saved condition codes
           0306 1818
      0306 1819      ; The next four instructions reconstruct the initial values of 'srclen' and
      0306 1820      ; 'srcaddr' and store them on the stack just above the saved R6. These values
      0306 1821      ; will be loaded into R0 and R1 when the instruction completes execution.
      0306 1822      ; Note that these two instructions destroy information in the saved copy of
      0306 1823      ; R4 so all of that information must be removed before these instructions
      0306 1824      ; execute.
      0306 1825
14 AE 0B AE 9A 0306 1826      MOVZBL EDITPC_B_DELTA_SRCADDR(SP),EDITPC_L_SAVED_R1(SP)
      14 AE C3 030B 1827      SUBL3  EDITPC_L_SAVED_R1(SP),-
      04 AE      030E 1828      EDITPC_A_SRCADDR(SP),-
      14 AE      0310 1829      EDITPC_L_SAVED_R1(SP)
10 AE 10 AE 9A 0312 1830      MOVZBL EDITPC_B_INISRCLEN(SP),EDITPC_L_SAVED_R0(SP)
           0317 1831
      0317 1832      ; The top four longwords are discarded and control is passed to the restart
      0317 1833      ; point obtained from the restart PC table. Note that there is an assumption
      0317 1834      ; here that the first two restart points are different from the others in that
      0317 1835      ; they do not have an additional return PC (TOP_OF_LOOP) on the stack.
      0317 1836
      SE 10 C0 0317 1837      ADDL  #EDITPC_L_SAVED_R0,SP      ; Make saved registers R0, R1, R6, ...
      01 56 D1 031A 1838      CMLP  R6,#EDITPC_1_RESTART      ; Check for restart in main routine
      06 1B 031D 1839      BLEQU 10$      ; Branch if no return PC
      FD2D CF 9F 031F 1840      PUSHAB TOP_OF_LOOP      ; Restart in some subroutine
      08 11 0323 1841      BRB 20$      ; Use common code to resume execution
      0325 1842
      0325 1843      ; EDITPC_1 is a restart point where R7 must contain the address of the byte
      0325 1844      ; that contains the sign 'digit'. This address must be recalculated. Note that
      0325 1845      ; this calculation overwrites the previous R7 restoration.
      0325 1846
57 50 04 01 EF 0325 1847 10$: EXTZV #1,#4,R0,R7      ; Get byte offset to end of string
      57 51 C0 032A 1848      ADDL  R1,R7      ; Get address of byte containing sign
      032D 1849
56 FFFE'CF46 3C 032D 1850 20$: MOVZWL RESTART_PC_TABLE_BASE-2[R6],R6 ; Convert code to PC offset
      FCC8 CF46 17 0333 1851      JMP  MODULE_BASE[R6]      ; Get back to work
      0338 1852
      0338 1853      END_MARK_POINT      EDITPC_M_STATE
      0338 1854
      0338 1855      .END
  
```

```

...PC = 00000169
...RESTART PC... = 00000174
ADJUST_INPUT_1 = 00000298 R 02
BLANK = 00000020
BLANK_ZERO_1 = 00000298 R 02
BLANK_ZERO_2 = 00000279 R 02
BLANK_ZERO_2_RESTART = 00000008
EDITPC_1 = 00000289 R 02
EDITPC_1_RESTART = 00000001
EDITPC_2 = 00000298 R 02
EDITPC_2_RESTART = 00000002
EDITPC_3 = 00000298 R 02
EDITPC_4 = 00000298 R 02
EDITPC_5 = 00000298 R 02
EDITPC_ACCVIO = 000001FD R 02
EDITPC_A_PATTERN = 0000000C
EDITPC_A_SRCADDR = 00000004
EDITPC_B_DELTA_PC = 0000000A
EDITPC_B_DELTA_SRCADDR = 0000000B
EDITPC_B_EO_READ_CHAR = 00000001
EDITPC_B_INISRLEN = 00000010
EDITPC_B_LOOP_COUNT = 00000013
EDITPC_B_SAVED_PSW = 00000011
EDITPC_B_SIGN = 00000009
EDITPC_B_STATE = 00000012
EDITPC_L_SAVED_R0 = 00000010
EDITPC_L_SAVED_R1 = 00000014
EDITPC_M_FPD = 00000010
EDITPC_M_STATE = 0000000F
EDITPC_PACK = 000002A2 R 02
EDITPC_ROPRAND_ABORT = 000001F4 R 02
EDITPC_ROPRAND_FAULT = 000001B3 R 02
EDITPC_S_STATE = 00000004
EDITPC_V_FPD = 00000004
EDITPC_V_STATE = 00000000
EDITPC_W_SRLEN = 00000000
EDITPC_W_ZERO_COUNT = 00000002
END_FLOAT_1 = 0000028F R 02
EOSADJUST_INPUT_ROUTINE = 00000169 R 02
EOSBLANK_ZERO_ROUTINE = 0000012B R 02
EOSCLEAR_SIGNIF_ROUTINE = 00000161 R 02
EOSEND_FLOAT_ROUTINE = 00000123 R 02
EOSEND_ROUTINE = 00000187 R 02
EOSFILE_ROUTINE = 000000CB R 02
EOSFLOAT_ROUTINE = 000000FC R 02
EOSINSERT_ROUTINE = 000000B9 R 02
EOSLOAD_FILL_ROUTINE = 0000014B R 02
EOSLOAD_MINUS_ROUTINE = 0000015A R 02
EOSLOAD_PLUS_ROUTINE = 00000153 R 02
EOSLOAD_SIGN_ROUTINE = 0000014F R 02
EOSMOVE_ROUTINE = 000000D8 R 02
EOSREPLACE_SIGN_ROUTINE = 0000013C R 02
EOSSET_SIGNIF_ROUTINE = 00000165 R 02
EOSSTORE_SIGN_ROUTINE = 000000C7 R 02
EO_READ = 00000095 R 02
FILL_1 = 00000298 R 02
FILL_2 = 00000255 R 02

```

```

FILL_2_RESTART = 00000003
FLOAT_1 = 00000298 R 02
FLOAT_2 = 00000267 R 02
FLOAT_2_RESTART = 00000008
FLOAT_3 = 0000026D R 02
FLOAT_3_RESTART = 00000009
FLOAT_4 = 00000273 R 02
FLOAT_4_RESTART = 0000000A
HANDLER_TABLE_BASE = 00000000 R 04
INSERT_1 = 00000298 R 02
INSERT_2 = 00000298 R 02
LOAD_XXXX_1 = 00000298 R 02
LOAD_XXXX_2 = 00000298 R 02
MINUS = 0000002D
MODULE_BASE = 00000000 R 02
MODULE_END = 00000338 R 02
MOVE_1 = 00000298 R 02
MOVE_2 = 0000025B R 02
MOVE_2_RESTART = 00000005
MOVE_3 = 00000261 R 02
MOVE_3_RESTART = 00000006
PACK_M_ACCVIO = 00000200
PACK_M_FPD = 00000100
PC_TABLE_BASE = 00000000 R 03
PSL$M_C = 00000001
PSL$M_N = 00000008
PSL$M_V = 00000002
PSL$M_Z = 00000004
PSL$V_C = 00000000
PSL$V_N = 00000003
PSL$V_V = 00000001
PSL$V_Z = 00000002
READ_1 = 00000231 R 02
READ_2 = 00000231 R 02
REPLACE_SIGN_1 = 00000298 R 02
REPLACE_SIGN_2 = 00000295 R 02
RESTART_PC_TABLE_BASE = 00000000 R 05
RESTART_TABLE_SIZE = 0000000C
STORE_SIGN_1 = 00000298 R 02
TABLE_SIZE = 0000001B
TOP_OF_LOOP = 00000050 R 02
VAX$EDITPC = 00000006 RG 02
VAX$EDITPC_OVERFLOW = ***** X 00
VAX$EDITPC_RESTART = 000002E0 RG 02
VAX$REFLECT_FAULT = ***** X 00
VAX$ROPRAND = ***** X 00
ZERO = 00000030

```



-----  
! Psect synopsis !  
-----

PSECT name	Allocation	PSECT No.	Attributes
. ABS .	00000000 ( 0.)	00 ( 0.)	NOPIC USR CON ABS LCL NOSHR NOEXE NORD NOWRT NOVEC BYTE
\$AB\$\$	00000000 ( 0.)	01 ( 1.)	NOPIC USR CON ABS LCL NOSHR EXE RD WRT NOVEC BYTE
VAX\$CODE	00000338 ( 824.)	02 ( 2.)	PIC USR CON REL LCL SHR EXE RD NOWRT NOVEC LONG
PC TABLE	00000036 ( 54.)	03 ( 3.)	PIC USR CON REL LCL SHR NOEXE RD NOWRT NOVEC BYTE
HANDLER_TABLE	00000036 ( 54.)	04 ( 4.)	PIC USR CON REL LCL SHR NOEXE RD NOWRT NOVEC BYTE
RESTART_PC_TABLE	00000018 ( 24.)	05 ( 5.)	PIC USR CON REL LCL SHR NOEXE RD NOWRT NOVEC BYTE

-----  
! Performance indicators !  
-----

Phase	Page faults	CPU Time	Elapsed Time
Initialization	10	00:00:00.02	00:00:02.33
Command processing	71	00:00:00.51	00:00:03.36
Pass 1	160	00:00:05.76	00:00:17.88
Symbol table sort	0	00:00:00.22	00:00:00.68
Pass 2	320	00:00:03.65	00:00:10.65
Symbol table output	12	00:00:00.10	00:00:00.26
Psect synopsis output	2	00:00:00.03	00:00:00.17
Cross-reference output	0	00:00:00.00	00:00:00.00
Assembler run totals	575	00:00:10.30	00:00:35.34

The working set limit was 1500 pages.  
34222 bytes (67 pages) of virtual memory were used to buffer the intermediate code.  
There were 20 pages of symbol table space allocated to hold 158 non-local and 44 local symbols.  
1855 source lines were read in Pass 1, producing 23 object records in Pass 2.  
20 pages of virtual memory were used to define 17 macros.

-----  
! Macro library statistics !  
-----

Macro library name	Macros defined
_\$255\$DUA28:[EMULAT.OBJ]VAXMACROS.MLB;1	8
_\$255\$DUA28:[SYSLIB]STARLET.MLB;2	5
TOTALS (all libraries)	13

256 GETS were required to define 13 macros.

There were no errors, warnings or information messages.

MACRO/LIS=LIS\$:VAXEDITPC/OBJ=OBJ\$:VAXEDITPC MSRC\$:VAXEDITPC/UPDATE=(ENH\$:VAXEDITPC)+LIB\$:VAXMACROS/LIB

