


```

NN      NN  EEEEEEEEE  TTTTTTTTT  DDDDDDD  LL      EEEEEEEEE
NN      NN  EEEEEEEEE  TTTTTTTTT  DDDDDDD  LL      EEEEEEEEE
NN      NN  EE          TT          DD      DD  LL      EE
NN      NN  EE          TT          DD      DD  LL      EE
NNNN    NN  EE          TT          DD      DD  LL      EE
NNNN    NN  EE          TT          DD      DD  LL      EE
NN  NN  NN  EEEEEEE    TT          DD      DD  LL      EEEEEEE
NN  NN  NN  EEEEEEE    TT          DD      DD  LL      EEEEEEE
NN      NNNN EE          TT          DD      DD  LL      EE
NN      NNNN EE          TT          DD      DD  LL      EE
NN      NN  EE          TT          DD      DD  LL      EE
NN      NN  EE          TT          DD      DD  LL      EE
NN      NN  EEEEEEEEE  TT          DDDDDDD  LLLLLLLLL  EEEEEEEEE
NN      NN  EEEEEEEEE  TT          DDDDDDD  LLLLLLLLL  EEEEEEEEE

```

```

LL      IIIIII  SSSSSSS
LL      IIIIII  SSSSSSS
LL      II     SS
LL      II     SS
LL      II     SS
LL      II     SS
LL      II     SSSSSS
LL      II     SSSSSS
LL      II     SS
LL      II     SS
LL      II     SS
LL      II     SS
LLLLLLLL IIIIII  SSSSSSS
LLLLLLLL IIIIII  SSSSSSS

```

(2)	72	Declarations
(3)	257	DLE\$DISPATCH - Dispatch newly recieved DLE IRP
(4)	322	DLE\$ACCESS - Handle IO\$ ACCESS function
(5)	434	DLE\$LPD STATUS - Check completion of MOP transition
(6)	525	BC ACCESS - Handle DLE access to broadcast circuit
(7)	583	DLE\$SETMODE - Process IO\$ SETMODE request
(8)	672	DLE\$DEACCESS - Process IO\$ DEACCESS request
(9)	735	LEAVE MOP STATE - Leave MOP state
(10)	777	DLE\$CANCEL - Process DLE cancel request
(11)	799	DLE\$BC_UP - Initialize DLE on broadcast circuit
(12)	884	DLE\$BC_DOWN - Cleanup DLE on broadcast circuit
(13)	951	INIT UNSOL_CHAN - Initialize channel for unsolicited msgs
(14)	1014	ISSUE NI_READ - Issue read request to NI driver
(15)	1104	RCV DCE_MSG - Receive unsolicited DLE message
(16)	1216	DLE\$MOP_REQUEST - Partner has requested MOP mode
(17)	1296	STARTUP_MOM - Start MOM process
(18)	1364	ATTACH UNSOL_MSG - Attach unsolicited message
(19)	1441	DLE\$PRC_EXIT - Handle MOM process termination

```

0000 1 .TITLE NETDLE - NETACP DLE processing
0000 2 .IDENT 'V04-000'
0000 3
0000 4 :*****
0000 5 :*
0000 6 :* COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
0000 7 :* DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
0000 8 :* ALL RIGHTS RESERVED.
0000 9 :*
0000 10 :* THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
0000 11 :* ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
0000 12 :* INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
0000 13 :* COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
0000 14 :* OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
0000 15 :* TRANSFERRED.
0000 16 :*
0000 17 :* THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
0000 18 :* AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
0000 19 :* CORPORATION.
0000 20 :*
0000 21 :* DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
0000 22 :* SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
0000 23 :*
0000 24 :*
0000 25 :*****
0000 26
0000 27 :++
0000 28 : FACILITY: DECnet-VAX
0000 29
0000 30 : ABSTRACT:
0000 31
0000 32 : This module contains most of the DLE process-level code in
0000 33 : NETACP. It works with the DLE driver (NDDRIVER) to implement
0000 34 : DLE to allow programs direct access to DECnet circuits. This
0000 35 : is primarily used to implement MOP support.
0000 36
0000 37 : ENVIRONMENT:
0000 38
0000 39 : MODE = KERNEL
0000 40
0000 41 : AUTHOR:
0000 42
0000 43 : Tim Halvorsen, January 1983
0000 44
0000 45 : MODIFIED BY:
0000 46
0000 47 : V003 TMH0003 Tim Halvorsen 24-Aug-1984
0000 48 : Prevent duplicate MOM processes from being started due
0000 49 : to unsolicited messages received AFTER MOM has issued
0000 50 : its ACCESS but before it has established a connection
0000 51 : with the node (via SETMODE). This is done by simply
0000 52 : leaving the unsolicited message which started MOM in the
0000 53 : unsolicited queue for the life of the MOM process, causing
0000 54 : any new unsolicited messages which "squeak through" to be
0000 55 : dropped rather than starting a new MOM process.
0000 56
0000 57 : V002 TMH0002 Tim Halvorsen 28-Apr-1983

```

0000 58 :
0000 59 :
0000 60 :
0000 61 :
0000 62 :
0000 63 :
0000 64 :
0000 65 :
0000 66 :
0000 67 :
0000 68 :
0000 69 :
0000 70 :--

V001

Change loopback assistant multicast address to
the one listed in the Ethernet V2 spec.

TMH0001 Tim Halvorsen 29-Mar-1983
Compute a unique MOM process name, so that multiple
service operations can occur on the same circuit.
Fix deallocation of BC blocks to wait for all outstanding
I/O to rundown before deallocating the block.
Add protective code to prevent multiple MOMs from starting
up if the remote station sends requests too often - if we
receive another message while a MOM process is still starting,
it is ignored.

```
0000 72      .SBTTL  Declarations
0000 73      :
0000 74      : VMS definitions
0000 75      :
0000 76      :
0000 77      $ABDDEF      ; ACP buffer descriptor
0000 78      $CCBDEF      ; Channel control block
0000 79      $CXBDEF      ; Complex buffer
0000 80      $DDBDEF      ; Device data block
0000 81      $DDTDEF      ; Driver dispatch table
0000 82      $DYNDEF      ; Structure types
0000 83      $IRPDEF      ; I/O request packet
0000 84      $IODEF      ; I/O function codes
0000 85      $JIBDEF      ; Job information block
0000 86      $PCBDEF      ; Process control block
0000 87      $UCBDEF      ; Device unit control block
0000 88      :
0000 89      :
0000 90      : Network definitions
0000 91      :
0000 92      :
0000 93      $DWBDEF      ; DLE window control block
0000 94      $EVCDEF      ; Event logging parameter codes
0000 95      $LPDDEF      ; Logical path descriptor (circuit)
0000 96      $NETSYMDEF   ; Get NET$C_IPL symbol
0000 97      $NFBDEF      ; Network parameter codes
0000 98      $NMADEF      ; NICE parameter codes
0000 99      $WQEDEF      ; Work queue entries
0000 100     :
0000 101     :
0000 102     : Define symbols for timer qualifiers
0000 103     :
0000 104     :
00000001 0000 105 TID_C_READSUP = 1      ; NI receive 'wait' timer
0000 106     :
00000004 0000 107 WQESC_QUAL_DLE = 4    ; && temp &&
0000 108     :
0000 109     :
0000 110     : Define format of broadcast circuit 'default protocol user' context block.
0000 111     : This block holds all context related to enabling this process to receive
0000 112     : all unsolicited messages ('default user') for the MOP protocol types on
0000 113     : a broadcast circuit, specifically 'load/dump' and 'loopback' protocol types.
0000 114     :
0000 115     :
0000 116     $DEFINI BC GLOBAL      ; (GLOBAL is only for debugging)
0000 117     :
0000 118 $DEF  BC_L_FLINK      .BLKL  2      ; Forward/backward queue links
0008 119 $DEF  BC_W_SIZE      .BLKW  1      ; Size of structure
000A 120 $DEF  BC_B_TYPE      .BLKB  1      ; Type of structure
000B 121 $DEF  BC_B_FLAGS     .BLKB  1      ; Flags
000C 122  _VIELD BC,O,<-      ;
000C 123  <DELETE,,M>,-      ; Block is marked for deallocation
000C 124  >
0000000E 000C 125 $DEF  BC_B_REFCNT .BLKB  1      ; # of IOWQEs still outstanding
000D 126     .BLKB  1      ; (spare for alignment)
000E 127 $DEF  BC_W_LPD      .BLKW  1      ; LPD ID of broadcast circuit
0010 128 $DEF  BC_W_LD_CHAN    .BLKW  1      ; Channel for 'load/dump' protocol
```

```

0012 129 $DEF BC_W_LP_CHAN .BLKW 1 ; Channel for "loopback" protocol
0014 130 $DEF BC_Q_PND_RCV .BLKL 2 ; Listhead of pending receive IOWQEs
001C 131 $DEF BC_Q_CUR_RCV .BLKL 2 ; Listhead of current receive IOWQEs
0024 132 $DEF BC_Q_UNSQL_MSGS .BLKL 2 ; Listhead for received unsolicited msgs
002C 133 $DEF BC_C_LENGTH ; Length of structure
002C 134
002C 135 $DEFEND BC
0000 136
0000 137 ;
0000 138 ; Define format of an unsolicited message context block
0000 139 ;
0000 140
0000000E 0000 141 NIHDRSIZ = 14 ; Size of NI datalink header
0000 142
0000 143 $DEFINI IOWQE GLOBAL ; (GLOBAL is only for debugging)
0000 144
00000C24 0000 145 . = WQESC_LENGTH ; Start just after standard WQE
0024 146
00000026 0024 147 $DEF IOWQE_Q_IOSB .BLKL 2 ; I/O status block
002C 148 IOWQE_W_MSGLEN = IOWQE_Q_IOSB+2 ; Message length
002C 149 $DEF IOWQE_W_CHAN .BLKW 1 ; Channel to datalink
00000030 002E 150 .BLKW 1 ; (spare for alignment)
0030 151 $DEF IOWQE_L_PID .BLKL 1 ; IPID of MOM process for this msg
0034 152 $DEF IOWQE_L_BC .BLKL 1 ; Address of corresponding BC block
0038 153 $DEF IOWQE_G_NIHDR .BLKB NIHDRSIZ ; NI datalink header
0046 154 $DEF IOWQE_G_MSG .BLKB 1500 ; Actual message (allow for largest)
0622 155 $DEF IOWQE_C_LENGTH
0622 156
0622 157 $DEFEND IOWQE
0000 158
0000 159 ;
0000 160 ; Read/write storage
0000 161 ;
0000 162
00000000 163 .PSECT NET_IMPURE,WRT,NOEXE,LONG
0000 164
00000000' 0000 165 DLE_ACC:
00000000' 0004 166 .ADDRESS DLE_ACC ; Queue of DLE IOS_ACCESS IRPs
00000000' 0008 167 .ADDRESS DLE_ACC ; waiting for circuit to go into MOP
0008 168
00000008' 0008 169 BC_QUEUE:
00000008' 000C 170 .ADDRESS BC_QUEUE ; Queue of BC blocks for all broadcast
00000008' 0010 171 .ADDRESS BC_QUEUE ; circuits in the "run" state
0010 172
00000018 0010 173 IOSB: .BLKL 2 ; General purpose I/O status block
0018 174
00000000 175 .PSECT NET_PURE,NOWRT,NOEXE,LONG
0000 176
0000 177 ;
0000 178 ; Define storage needed to startup MOM
0000 179 ;
0000 180
0000000A 0000 181 MAX_MOM_PROC = 10 ; Maximum number of simultaneous
0000 182 ; MOM processes for a single circuit
0000 183 MOM_OBJ_NAM:
4D 4F 4D 24 00' 0000 184 .ASCIC '$MOM' ; Name of MOM object
04 0000

```

```

4C 55 21 5F 44 41 21 5F 4D 4F 4D 00' 0005 185 MOM_PRCNAM:
OB 0005 186 .ASCIC 'MOM;!AD;!UL' ; MOM process name
0011 187
0011 188 :
0011 189 : UNA "setmode" parameters for load/dump protocol
0011 190 :
0011 191 :
0011 192 LD_PARAMS:
OBOE 0011 193 .WORD NMASC_PCLI_PTY ; Protocol type = 60-01
00000160 0013 194 .LONG ^X0160
OB1E 0017 195 .WORD NMASC_PCLI_ACC ; Protocol access mode = SHARED
00000001 0019 196 .LONG NMASC_ACC_SHR
OAF1 001D 197 .WORD NMASC_PCLI_BUS ; Buffer size = 1498 (2 bytes for PAD)
000005DA 001F 198 .LONG 1498
O451 0023 199 .WORD NMASC_PCLI_BFN ; Number of buffers = 2
00000002 0025 200 .LONG 2
OBOF 0029 201 .WORD NMASC_PCLI_MCA ; Reception of multicast messages:
0008 002B 202 .WORD 8 ; (8 byte string follows)
0001 002D 203 .WORD NMASC_LINMC_SET ; Enable reception of multicast
010000AB 002F 204 .LONG ^X010000AB ; "dump/load assistance"
0000 0033 205 .WORD 0
OB1A 0035 206 .WORD NMASC_PCLI_PAD ; Padding length word = ON
00000000 0037 207 .LONG NMASC_STATE_ON
OB18 003B 208 .WORD NMASC_PCLI_PRM ; Promiscuous mode = OFF
00000001 003D 209 .LONG NMASC_STATE_OFF
OB19 0041 210 .WORD NMASC_PCLI_MLT ; Multicast address state = OFF
00000001 0043 211 .LONG NMASC_STATE_OFF
OB1B 0047 212 .WORD NMASC_PCLI_DCH ; Data chaining = OFF
00000001 0049 213 .LONG NMASC_STATE_OFF ; (DLE driver can't handle multiple CXBs)
OB1C 004D 214 .WORD NMASC_PCLI_CRC ; CRC generation = ON
00000000 004F 215 .LONG NMASC_STATE_ON
0053 216
00000042 0053 217 LD_SETMODE:
00000011' 0053 218 .LONG .-LD_PARAMS ; Descriptor of above buffer
0057 219 .ADDRESS LD_PARAMS
005B 220
005B 221 :
005B 222 : UNA "setmode" parameters for loopback protocol
005B 223 :
005B 224 :
005B 225 LP_PARAMS:
OBOE 005B 226 .WORD NMASC_PCLI_PTY ; Protocol type = 90-00
00000090 005D 227 .LONG ^X0090
OB1E 0061 228 .WORD NMASC_PCLI_ACC ; Protocol access mode = SHARED
00000001 0063 229 .LONG NMASC_ACC_SHR
OAF1 0067 230 .WORD NMASC_PCLI_BUS ; Buffer size = 1500
000005DC 0069 231 .LONG 1500
O451 006D 232 .WORD NMASC_PCLI_BFN ; Number of buffers = 2
00000002 006F 233 .LONG 2
OBOF 0073 234 .WORD NMASC_PCLI_MCA ; Reception of multicast messages:
0008 0075 235 .WORD 8 ; (8 byte string follows)
0001 0077 236 .WORD NMASC_LINMC_SET ; Enable reception of multicast
000000CF 0079 237 .LONG ^X000000CF ; "loopback assistance"
0000 007D 238 .WORD 0
OB1A 007F 239 .WORD NMASC_PCLI_PAD ; Padding length word = OFF
00000001 0081 240 .LONG NMASC_STATE_OFF

```

```
00000001 0085 241 .WORD NMASC_PCLI_PRM ; Promiscuous mode = OFF
00000001 0087 242 .LONG NMASC_STATE_OFF
00000001 008B 243 .WORD NMASC_PCLI_MLT ; Multicast address state = OFF
00000001 008D 244 .LONG NMASC_STATE_OFF
00000001 0091 245 .WORD NMASC_PCLI_DCH ; Data chaining = OFF
00000001 0093 246 .LONG NMASC_STATE_OFF ; (DLE driver can't handle multiple CXBs)
00000000 0097 247 .WORD NMASC_PCLI_CRC ; CRC generation = ON
00000000 0099 248 .LONG NMASC_STATE_ON
00000000 009D 249
00000042 009D 250 LP_SETMODE:
0000005B' 00A1 251 .LONG .-LP_PARAMS ; Descriptor of above buffer
0000005B' 00A5 252 .ADDRESS LP_PARAMS
00000000 00A5 253
00000000 00A5 254
00000000 255 .PSECT NET_CODE,NOWRT,EXE
```

```

0000 257      .SBTTL DLE$DISPATCH - Dispatch newly recieved DLE IRP
0000 258      :+
0000 259      : DLE$DISPATCH - Dispatch newly received DLE IRP
0000 260      :
0000 261      : This routine is called from AQB dispatching when an IRP is dequeued
0000 262      : which has the PHYSIO flag set in the IRP flags. This flag is used
0000 263      : by convention between NETDRIVER and NDDRIVER to distinguish between
0000 264      : various flavors of IRPs.
0000 265      :
0000 266      : Inputs:
0000 267      :
0000 268      :     R3 = IRP address
0000 269      :
0000 270      : Outputs:
0000 271      :
0000 272      :     None - the IRP is always returned to the driver.
0000 273      :-
0000 274      DLE$DISPATCH::
0000 275      EXTZV  #IRP$V_FCODE,-           ; Get function code
0002 276      #IRP$S_FCODE,-
57  20 A3 0003 277      IRP$W_FUNC(R3),R7
0006 278      $DISPATCH R7,<-
0006 279      <IOS_ACCESS, 30$>,-
0006 280      <IOS_ACPCONTROL, 40$>,-
0006 281      <IOS_DEACCESS, 50$>,-
0006 282      <IOS_SETMODE, 60$>>
0000'8F 3C 0036 283 10$: MOVZWL #SS$_ILLIOFUNC,-           ; Say "illegal I/O function"
38 A3 003A 284      IRP$L_IOST1(R3)
0000 285      BRB 90$           ; Exit
0000 286      :
0000 287      :     ACCESS function - dispatch to connect processor
0000 288      :
0000 289      30$: BSBW DLE$ACCESS           ; Process IOS_ACCESS function
0034 23 11 0041 290      BRB 90$           ; Exit
0000 291      :
0000 292      :     ACP Control
0000 293      :
0000 294      40$: BBS #IRP$V_COMPLX,-           ; If normal IOS_ACPCONTROL, then
EE 2A A3 0045 295      IRP$W_STS(R3),10$           ; inform user we don't support them
18 A3 01 8A 0048 296      BICB #1,IRP$L_WIND(R3)           ; Clear interlock bit in case an
0000 297      :     IOS_ACCESS or IOS_DEACCESS is pending
02E2 30 11 004C 298      BSBW DLE$CANCEL           ; Do cancel-related work
0000 299      BRB 90$           ; Continue
0000 300      :
0000 301      :     DEACCESS function
0000 302      :
56  18 A3 01 CB 0051 303 50$: BICL3 #1,IRP$L_WIND(R3),R6           ; Get DWB without interlock bit
0000 304      BGEQ 90$           ; If GEQ then no DWB
0000 305      BSBW DLE$DEACCESS           ; Process IOS_DEACCESS function
0000 306      BRB 90$           ; Continue
0000 307      :
0000 308      :     SETMODE function
0000 309      :
56  18 A3 D0 005D 310 60$: MOVL IRP$L_WIND(R3),R6           ; Get DWB address
0000 311      BGEQ 90$           ; If GEQ then no DWB
0000 312      BSBW DLE$SETMODE           ; Process IOS_SETMODE function
0000 313      :

```

```
0066 314 ; Give the IRP back to the DLE driver with the I/O status setup
0066 315 ;
53 DS 0066 316 90$: fSTL R3 ; Did IRP get tucked away somewhere
OA 13 0068 317 BEQL 100$ ; If so, exit
55 1C A3 D0 006A 318 MOVL IRP$U,UCB(R3),R5 ; Get UCB address
00000000 GF 16 006E 319 JSB G^EXE$INSIOQ ; Queue packet to driver
05 0074 320 100$: RSB ; Done
```

```

0075 322 .SBTTL DLE$ACCESS - Handle IOS_ACCESS function
0075 323 :+
0075 324 : DLE$ACCESS - Process IOS_ACCESS function for a DLE channel
0075 325 :
0075 326 : This routine is entered after the initial IOS_ACCESS processing
0075 327 : done in the DLE driver. It's main function is to perform all
0075 328 : those things which must be done in process context in order to
0075 329 : setup the connection between DLE user and the datalink.
0075 330 :
0075 331 : Inputs:
0075 332 :
0075 333 : R3 = IRP address
0075 334 :
0075 335 : P1 = Circuit name for DLE I/O
0075 336 :
0075 337 : Outputs:
0075 338 :
0075 339 : R3 = IRP address, 0 if not to be returned to driver yet.
0075 340 : IRP$IOST1 = I/O status
0075 341 :
0075 342 DLE$ACCESS:
54 A3 D4 0075 343 CLRL IRP$I_EXTEND(R3) ; Assume no rcvd msg to be returned
0078 344 :
0078 345 : Construct a descriptor of the circuit name
0078 346 :
57 2C B3 C1 0078 347 ADDL3 @IRP$I_SVAPTE(R3),- ; Get address of P1 ABD
54 08 0078 348 #ABD$I_FIB*ABD$I_LENGTH,R4
57 02 A4 3C 007D 349 MOVZWL ABD$I_COUNT(R4),R7 ; Get length of circuit name
51 64 3C 0081 350 MOVZWL ABD$I_TEXT(R4),R1 ; Get offset to circuit name
58 01 A441 9E 0084 351 MOVAB 1+ABD$I_TEXT(R4)[R1],R8 ; Get address of text (skip acmode)
0089 352 :
0089 353 : Locate the CRI and LPD for the circuit, and make sure it is
0089 354 : in a state to handle MOP mode.
0089 355 :
5B 0000000'EF D0 0089 356 MOVL NET$I_GL_CNR_CRI,R11 ; Point to CRI root block
5A D4 0090 357 CLRL R10 ; Start at beginning of CRI list
50 0000'8F 3C 0092 358 MOVZWL #SS$I_NOSUCHDEV,R0 ; Setup default error code
48 50 E9 00A6 359 $SEARCH egl,cri,s,nam ; Lookup CRI by circuit name
00A9 360 BLBC R0,91$ ; If error detected, then report it
50 0000'8F 3C 00A9 361 $GETFLD cri,l,sta ; Get circuit state
01 58 D1 00B6 362 MOVZWL #SS$I_DEVINACT,R0 ; Assume circuit not on
31 13 00BE 363 CMPL R8,#MASC_STATE_OFF ; Circuit off?
FF3D' 30 00C0 364 BEQL 91$ ; If so, report an error
2B 50 E9 00C3 365 BSBW NET$I_LOCATE_LPD ; Get LPD address
50 4C A3 D0 00C6 366 BLBC R0,91$ ; Exit if error detected
20 A6 B0 00CA 367 MOVL IRP$I_DIAGBUF(R3),R0 ; Get DWB address
3E A0 00CD 368 MOVW LPD$I_PTH(R6),- ; Store LPD ID of circuit
00CF 369 DWB$I_PATH(R0) ; into DLE window block
50 0000'8F 3C 00DC 370 $GETFLD cri,v,ser ; Service functions enabled?
0D 58 E8 00E1 371 MOVZWL #SS$I_IVMODE,R0 ; Assume service disabled
07 E0 00E4 372 BLBS R8,91$ ; If disabled, then report error
08 22 A6 00E6 373 BBS #LPD$I_X25,- ; No service is allowed
00E9 374 LPD$I_STS(R6),91$ ; on X.25 DLM circuits
00E9 375 :
00E9 376 : If this is a multiaccess circuit, such as Ethernet,
00E9 377 : then skip the circuit transition, since there is no
00E9 378 : circuit "mode".

```

```

06 22 0A E1 00E9 379 ;
06 22 A6 00E9 380 ; BBC #LPDSV BC,- ; Skip if not broadcast
00CF 30 00EB 381 ; LPDSW_STS(R6),10$
005E 31 00EE 382 ; BSBW BC_ACCESS ; Handle broadcast DLE access
00F1 383 91$: BRW 90$ ; Return status to DLE driver
00F4 384 10$:
00F4 385 ;
00F4 386 ; Mark the DLE process as the owner of the circuit. If the
00F4 387 ; circuit is already owned, return an error.
00F4 388 ;
50 0D 50 E9 0101 389 ; $GETFLD cri,l,owpid ; Get PID of DLE owner
OC A3 58 D1 0104 390 ; BLBC R0,20$ ; Branch if not currently owned
07 13 0108 391 ; CMPL R8,IRP$L_PID(R3) ; Is it already owned by process?
50 0000 8F 3C 010A 392 15$: ; BEQL 20$ ; If so, ok to access
41 11 010F 393 ; MOVZWL #SS$_DEVALLOC,R0 ; Report circuit already owned
03 E2 0111 394 20$: ; BRB 90$
F4 22 A6 0113 395 ; BBSS #LPDSV_ACCESS,- ; Mark circuit accessed for DLE
58 OC A3 DO 0116 396 ; LPDSW_STS(R6),15$ ; If already accessed, report error
FEE3 30 011A 397 ; MOVL IRP$L_PID(R3),R8 ; Get caller's PID
02 E2 011D 398 ; BSBW CNF$POT_FIELD ; Make process owner of the circuit
1D 22 A6 011F 399 ; BBSS #LPDSV_DLE,- ; Mark in DLE mode
0122 400 ; LPDSW_STS(R6),30$ ; If already in DLE, skip logging event
0122 401 ;
0122 402 ; Log an event indicating the circuit has been accessed
0122 403 ; locally by a process.
55 00000000 EF 9E 0122 404 ; MOVAB NET$AB_EVT_WQE,R5 ; Get address of common WQE
20 A6 B0 0129 405 ; MOVW LPDSW_PTH(R6),- ; Set LPD ID into WQE
12 A5 012C 406 ; WQESW-REQIDT(R5)
0140 8F B0 012E 407 ; MOVW #EVC$C_DLL_LSC,- ; "locally initiated state change"
1C A5 0132 408 ; WQESW_EVL_CODE(R5)
03 90 0134 409 ; MOVB #EVC$C_DLC_POLD_RUNG,- ; Old state = RUNNING
1E A5 0136 410 ; WQESB_EVL_DT1(R5)
04 90 0138 411 ; MOVB #EVC$C_DLC_POLD_MAIN,- ; New state = MAINTAINANCE
1F A5 013A 412 ; WQESB_EVL_DT2(R5)
FEC1 30 013C 413 ; BSBW NET$EVT_INTRAW ; Log the event record
013F 414 ;
013F 415 ; Bring the circuit up in 'MOP' state.
50 0000 8F 3C 013F 416 30$: ; MOVZWL #LEV$C_DLE_ACC,R0 ; Setup DLLTRN event code
FEB9 30 0144 418 ; BSBW SET_DLC_EVT ; Queue the request
0147 419 ;
0147 420 ; Wait for the circuit to become ready. When it does, the
0147 421 ; routine DLE$LPD_STATUS will be called.
0147 422 ;
00000004 FF 63 OE 0147 423 ; INSQUE (R3),@DLE_ACC+4 ; Insert IRP onto waiting queue
53 D4 014E 424 ; CLRL R3 ; Indicate IRP not to be returned
04 11 0150 425 ; BRB 100$
0152 426 ;
0152 427 ;
0152 428 ; An error has been detected. Return the IRP back to the driver.
0152 429 ;
0152 430 ;
38 A3 50 3C 0152 431 90$: ; MOVZWL R0,IRP$L_IOST1(R3) ; Pass status back in IRP
05 0156 432 100$: ; RSB

```

```

0157 434 .SBTTL DLE$LPD_STATUS - Check completion of MOP transition
0157 435 :+
0157 436 : DLE$LPD_STATUS - Check completion of MOP transition
0157 437 :
0157 438 : This routine is called when an LPD has made the transition into MOP
0157 439 : state or if an error has occurred. It is always called by DLLTRN
0157 440 : on circuit transitions if the ACCESS flag is set in the LPD.
0157 441 :
0157 442 : If there is a process waiting to access the circuit, then if the
0157 443 : transition was successful, then that process is allowed to proceed
0157 444 : with the access.
0157 445 :
0157 446 : Inputs:
0157 447 :
0157 448 : R6 = LPD address
0157 449 : R0 = Status of attempted MOP transition of circuit
0157 450 :
0157 451 : Outputs:
0157 452 :
0157 453 : None
0157 454 :
0157 455 : R0-R3,R8-R9 are destroyed.
0157 456 :
0157 457 DLE$LPD_STATUS::
30 BB 0157 458 PUSHHR #^M<R4,R5> ; Save registers
0159 459 :
0159 460 : Locate the DWB corresponding to the process attempting
0159 461 : the circuit ACCESS.
0159 462 :
51 00000000*EF 9E 0159 463 MOVAB DLE_ACC,R1 ; Get address of DLE ACCESS IRP listhead
53 51 DO 0160 464 MOVL R1,R3 ; Setup for loop
53 63 DO 0163 465 10$: MOVL (R3),R3 ; Skip to next IRP in list
51 53 D1 0166 466 : MOVL R3,R1 ; End of list?
39 13 0169 467 BEQL 60$ ; If so, then ignore the status
54 4C A3 DO 016B 468 MOVL IRP$L_DIAGBUF(R3),R4 ; Get DWB address for ACCESS request
20 A6 B1 016F 469 CMPW LPD$W_PTH(R6),- ; Is it for this circuit?
3E A4 0172 470 DWB$W_PATH(R4)
ED 12 0174 471 BNEQ 10$ ; If not, keep looking
53 63 OF 0176 472 REMQUE (R3),R3 ; Remove from pending ACCESS list
10 50 E9 0179 473 BLBC R0,20$ ; Branch if circuit is down
017C 474 :
017C 475 : Setup the datalink channel and UCB address in DWB
017C 476 :
14 A6 B0 017C 477 MOVW LPD$W_CHAN(R6),- ; Save channel to datalink
4C A4 017F 478 DWB$W_DLL_CHAN(R4)
10 A6 DO 0181 479 MOVL LPD$L_UCB(R6),- ; Save UCB of datalink
48 A4 0184 480 DWB$L_DLL_UCB(R4)
0186 481 :
0186 482 : Set the circuit substate to "auto-service"
0186 483 :
27 06 90 0186 484 MOVB #NMASC_LINSS_ASE,- ; Set circuit substate
A6 0188 485 LPD$B_SUB_STA(R6)
08 11 018A 486 BRB 50$ ; Pass success back to driver
018C 487 :
018C 488 : Failure to make transition - reset LPD to original state
018C 489 :
50 DD 018C 490 20$: PUSHL R0 ; Save final status

```

```

0167 30 018E 491      BSBW  LEAVE_MOP_STATE      ; Leave MOP state
50 8ED0 0191 492      POPL  R0                    ; Restore final status
                                ;
                                ; Report the status back to DLE driver
                                ;
38 A3 50 B0 0194 496 50$: MOVW  R0,IRP$L_IOST1(R3)      ; Store status in IRP
55 1C A3 D0 0198 497    MOVL  IRP$L_UCB(R3),R5      ; Point to the DLE UCB
00000000'GF 16 019C 498    JSB   G^EXE$INSIOQ        ; Queue packet to DLE driver
19 11 01A2 499    BRB   90$
                                ;
                                ;
                                ; 60$:
                                ;
                                ; There is no ACCESS request pending for this circuit. If
                                ; the LPD status is "success", then we can ignore it, since
                                ; its not relevant except to restart a pending ACCESS.
                                ;
16 50 EB 01A4 506    BLBS  R0,90$                ; Exit if LPD is ok
                                ;
                                ; There may be an active DLE session currently in progress
                                ; over this circuit. Tell the DLE driver to locate all DWBs
                                ; associated with this circuit, and if any, to abort them.
                                ;
58 20 A6 3C 01A7 512    MOVZWL LPD$W_PTH(R6),R8      ; Pass path ID to driver
55 00000000'EF D0 01AB 513    MOVL  NET$G^DLE_UCB,R5      ; Get DLE UCB address
51 0088 C5 D0 01B2 514    MOVL  UCB$L_DDT(R5),R1      ; Get DDT address
04 B1 16 01B7 515    JSB   @DDT$C_UNSOINT(R1)  ; Call "LPD down" entry point
                                ; with R0 = status code
                                ; and R8 = path ID
                                ;
                                ;
                                ; Leave MOP state
                                ;
013B 30 01BA 521      BSBW  LEAVE_MOP_STATE      ; Leave MOP state
30 BA 01BD 522 90$: POPR  #^M<R4,R5>      ; Restore registers
05 01BF 523    RSB

```

```

01C0 525      .SBTTL BC_ACCESS - Handle DLE access to broadcast circuit
01C0 526      :+
01C0 527      BC_ACCESS - Handle DLE access to multiaccess circuit
01C0 528      :
01C0 529      This routine is called when an access is being attempted to an
01C0 530      Ethernet. Since there is no "MOP mode" for multiaccess circuits,
01C0 531      we simply assign a new channel to the device, issue a SETMODE to
01C0 532      enable access to a given destination, and complete the access.
01C0 533      :
01C0 534      Inputs:
01C0 535      :
01C0 536      R3 = IRP address for ACCESS request
01C0 537      R6 = LPD address
01C0 538      R10/R11 = CNF/CNR addresses for CRI
01C0 539      :
01C0 540      Outputs:
01C0 541      :
01C0 542      R0 = Status code
01C0 543      :
01C0 544      BC_ACCESS:
01C0 545      :
01C0 546      Make sure the circuit is in the "run" state
01C0 547      :
50 04 E0 01C0 548      BBS      #LPDSV RUN,-          ; If circuit not ready,
08 22 A6 01C2 549      LPDSW STS(R6),10$
50 0000'8F 3C 01C5 550      MOVZWL #SS$_DEVINACT,R0          ; Return "circuit not on"
0051 31 01CA 551      BRW      90$              ; Report the error
01CD 552      10$:
01CD 553      Set a flag in the DWB indicating that this is an NI.
01CD 554      :
54 4C A3 D0 01CD 555      MOVL     IRP$L_DIAGBUF(R3),R4      ; Get DWB address
01D1 556      SETBIT  #DWBSV_BC,DWBSW_FLAGS(R4) ; Indicate circuit is an NI
01D6 557      :
01D6 558      Assign a new channel for this DLE session. Each DLE
01D6 559      session uses a new NETACP channel so that the demultiplexing
01D6 560      done by the datalink for received messages (based on the
01D6 561      source node) can be used by the DLE driver to distinguish
01D6 562      incoming messages between the various DLE users.
01D6 563      :
50 0000'8F 3C 01D6 564      MOVZWL #SS$_NOSUCHDEV,R0          ; Setup default error code
01DB 565      $GETFLD cri,s,vmsnam          ; Get datalink device name
01E8 566      BLBC     R0,90$              ; Exit if error detected
01EB 567      MOVQ     R7,-(SP)            ; Push descriptor on stack
01EE 568      MOVL     SP,R0              ; Get address of descriptor
01F1 569      $ASSIGN _S DEVNAM=(R0),-      ; Assign a new channel for DLE
01F1 570      CHAN=DWBSW_DLL_CHAN(R4)
01FF 571      ADDL     #8,SP              ; Pop descriptor off stack
0202 572      BLBC     R0,90$              ; Exit if error detected
0205 573      PUSHL   R3                  ; Save IRP address
0207 574      MOVZWL DWBSW_DLL_CHAN(R4),R0 ; Get channel number
020B 575      JSB     G^IOCSVERIFYCHAN    ; Get the CCB address; ignore errors
0211 576      POPL    R3                  ; Restore IRP address
0214 577      MOVL     CCB$L_UCB(R1),-      ; Save the datalink UCB address
0216 578      DWBSL_DLL_UCB(R4)
0218 579      BSBW     ATTACH_UNSOL_MSG      ; Pass unsolicited message to user
50 00 05 021B 580      MOVL     S^#SS$_NORMAL,R0      ; Success
021E 581      RSB                        ; Exit with status

```

```

021F 583 .SBTTL DLE$SETMODE - Process IOS_SETMODE request
021F 584 :+
021F 585 : DLE$SETMODE - Process IOS_SETMODE request at process level
021F 586 :
021F 587 : This routine is called to perform all work needed for the DLE SETMODE
021F 588 : QIO at IPL 0. This includes issuing a SETMODE function to the datalink
021F 589 : driver on the DLE user's behalf. Most of the work done for the SETMODE
021F 590 : has already been accomplished by the DLE driver.
021F 591 :
021F 592 : Inputs:
021F 593 :
021F 594 : R6 = DWB address
021F 595 : R3 = IRP address
021F 596 :
021F 597 : P2 = UNA P2 buffer (used only for DLE access to UNA)
021F 598 : P3 = Ethernet remote address (used only for DLE access to UNA)
021F 599 : P4 = Substate
021F 600 :
021F 601 : Outputs:
021F 602 :
021F 603 : R3 = IRP address, 0 if not to be returned to driver yet.
021F 604 : IRP$L_IOST1 = I/O status
021F 605 :
021F 606 DLE$SETMODE:
021F 607 :
021F 608 : For point-to-point circuits, propagate the (possibly) updated
021F 609 : circuit substate to the LPD (it has already been set in the
021F 610 : DWB by the driver) so that we can see it with existing network
021F 611 : management.
021F 612 :
021F 613 BBS #DWBSV BC,- ; If point-to-point circuit.
17 OE A3 E0 0221 614 DWBSW_FLAGS(R6),10$
58 3E A6 3C 0224 615 MOVZWL DWBSW_PATH(R6),R8 ; Get LPD ID
56 DD 0228 616 PUSHL R6 ; Save DWB address
FDD3' 30 022A 617 BSBW NET$FIND_LPD ; Locate LPD
52 56 DO 022D 618 MOVL R6,R2 ; Set LPD address in R2
56 BED0 0230 619 POPL R6 ; Restore DWB address
05 50 E9 0233 620 BLBC R0,10$ ; If cannot be found, skip it
46 A6 90 0236 621 MOVVB DWBSB_SUBSTA(R6),- ; Copy substate value to LPD
27 A2 0239 622 LPDSB_SUB_STA(R2)
023B 623 10$:
023B 624 : Construct a descriptor of the P2 buffer (UNA P2 buffer).
023B 625 : If none specified, then skip the SETMODE.
023B 626 :
023B 627 ADDL3 @IRP$L_SVAPTE(R3),- ; Get address of P2 ABD
54 10 023E 628 #ABD$C_NAME*ABD$C_LENGTH,R4
57 02 A4 3C 0240 629 MOVZWL ABD$W_COUNT(R4),R7 ; Get length of P2
59 13 0244 630 BEQL 40$ ; Skip if none
51 64 3C 0246 631 MOVZWL ABD$W_TEXT(R4),R1 ; Get offset to P2 data
58 01 A441 9E 0249 632 MOVAB 1+ABD$W_TEXT(R4)[R1],R8 ; Get address of P2 data (skip acmode)
024E 633 :
024E 634 : Issue a SETMODE to the datalink driver to establish
024E 635 : "shared" access to the remote node. This allows
024E 636 : more than one DLE user to use the protocol type at the
024E 637 : same time - demultiplexing is done for received messages
024E 638 : based on the remote node address.
024E 639 :

```

```

      7E 57 7D 024E 640      MOVQ  R7,-(SP)           ; Push descriptor of UNA P2 buffer
      50 5E 7D 0251 641      MOVL  SP,R0             ; Get address of descriptor
52 00000010'EF 9E 0254 642      MOVAB IOSB,R2          ; Get address of I/O status block
      025B 643      $QIOW_S  FUNC=#IOS SETMODE!IOSM CTRL!IOSM_STARTUP,- ; Issue request
      025B 644      CHAN=DWBSW_DLL_CHAN(R6),-
      025B 645      EFN=#NET$C_EFN_WAIT,-
      025B 646      IOSB=(R2),-
      025B 647      P2=R0
      5E 08 7D 0279 648      ADDL  #8,SP            ; Pop descriptor off stack
      23 50 7D 027C 649      BLBC  R0,90$          ; Exit if error detected
      50 62 7D 027F 650      MOVZWL (R2),R0         ; Get final I/O status
      07 50 7D 0282 651      BLBS  R0,30$         ; Exit if ok
3C A3 04 A2 7D 0285 652      MOVL  4(R2),IRP$L_IOST2(R3) ; Return UNA longword to user
      16 11 7D 028A 653      BRB   90$            ; Store primary status and exit
      028C 654 30$:
      028C 655
      028C 656
      028C 657
      028C 658
      028C 659
      028C 660
      028C 661
      50 53 7D 028C 662      PUSHL R3              ; Save IRP address
      4C A6 7D 028E 663      MOVZWL DWBSW_DLL_CHAN(R6),R0 ; Get channel number
00000000'GF 16 7D 0292 664      JSB   G^IOC$VERIFYCHAN ; Get the CCB address; ignore errors
      53 8E 7D 0298 665      PCPL  R3              ; Restore IRP address
      61 7D 029B 666      MOVL  CCB$L_UCB(R1),- ; Save the datalink UCB address
      48 A6 7D 029D 667      DWBSL_DLL_UCB(R6)
      50 00' 7D 029F 668 40$: MOVL  S^#SS$ NORMAL,R0 ; Successful
38 A3 50 7D 02A2 669 90$: MOVW  R0,IRP$L_IOST1(R3) ; Store status in IRP
      05 02A6 670      RSB                    ; Exit with status

```

```

:
: As a result of a SETMODE to the UNA driver for LIMITED protocol
: access, the UNA driver may have evaporated the UCB we initially
: got after the $ASSIGN, and "integrated" us into an existing UCB
: for the first user of the protocol type. As a result, we must
: re-lookup the datalink UCB address immediately after the SETMODE,
: and reset our saved value, whether it changed or not.
:
:

```

```

02A7 672      .SBTTL DLE$DEACCESS - Process IO$_DEACCESS request
02A7 673      :+
02A7 674      : DLE$DEACCESS - Process IO$_DEACCESS request
02A7 675      :
02A7 676      : This routine is called to perform all work needed for the DLE DEACCESS
02A7 677      : QIO at IPL 0.  If this is a point-to-point circuit, then we must cause
02A7 678      : the circuit to revert back into its original state.
02A7 679      :
02A7 680      : Inputs:
02A7 681      :
02A7 682      :     R6 = DWB address
02A7 683      :     R3 = IRP address
02A7 684      :
02A7 685      : Outputs:
02A7 686      :
02A7 687      :     R3 = IRP address, 0 if not to be returned to driver yet.
02A7 688      :     IRP$L_IOST1 = I/O status
02A7 689      :-
02A7 690      DLE$DEACCESS:
02A7 691      :
02A7 692      :     Locate the circuit data structures based on the LPD ID
02A7 693      :     stored in the DWB at access time.
02A7 694      :
02A7 695      :     MOVL    R6,R4                ; Save DWB address for later
58 54 56 D0 02AA 696      :     MOVZWL   DWBSW_PATH(R6),R8      ; Get LPD ID
   3E A6 3C 02AE 697      :     BEQL    70$                ; If none, report error
   41 13 02B0 698      :     BSBW   NET$GET_LPD_CRI      ; Get LPD, CRI addresses
   FD4D' 30 02B3 699      :     BLBC   R0,90$            ; Exit if error detected
   36 50 E9 02B6 700      :
02B6 701      :     If this is a multiaccess circuit, such as Ethernet,
02B6 702      :     then skip the circuit transition, since there is no
02B6 703      :     circuit "mode".
02B6 704      :
02B6 705      :     BBC    #LPDSV BC,-          ; Skip if not broadcast
OD 22 OA E1 02B8 706      :     LPDSW STS(R6),20$
   A6 02BB 707      :     $DASSGN_S CHAN=DWBSW_DLL_CHAN(R4) ; Deassign channel to datalink
   24 11 02C6 708      :     BRB   90$                ; Exit with status
OC 19 50 E9 02C8 709      :     20$:
   A3 58 D1 02C8 710      :     ; Make sure this user is actually the current "owner"
   13 12 02C8 711      :     ; of the circuit.
   02C8 712      :
   02C8 713      :     $GETFLD cri,l,owpid        ; Get the owner PID
   02D5 714      :     BLBC   R0,70$            ; If none at all, report an error
   02D8 715      :     CMPL   R8,IRP$L_PID(R3)    ; Check if this user is owner
   02DC 716      :     BNEQ   70$                ; If not, return an error
   02DE 717      :
   02DE 718      :     Leave MOP state
   02DE 719      :
   0017 30 02DE 720      :     BSBW   LEAVE_MOP_STATE     ; Leave MOP state
   02E1 721      :
   02E1 722      :     Bring the circuit down, which will cause it to attempt
   02E1 723      :     to re-initialize, this time in normal mode (because the
   02E1 724      :     DLE flag is off).
   02E1 725      :
50 0000'8F 3C 02E1 726      :     MOVZWL #LEVSC_LIN_DOWN,R0    ; Setup DLLTRN event code
   FD17' 30 02E6 727      :     BSBW   SET_DLE_EVT        ; Queue the request
   50 00' D0 02E9 728      :     MOVL   S^#SS$_NORMAL,R0   ; Success

```

```
38 A3 50 B0 02EC 729 90$: MOVW R0,IRP$L_IOST1(R3) ; Store status in IRP
          05 02F0 730 RSB ; Exit with status
          02F1 731
50 0000'8F 3C 02F1 732 70$: MOVZWL #SS$_FILNOTACC,R0 ; Circuit not accessed
          F4 11 02F6 733 BRB 90$
```

```

02F8 735      .SBTTL LEAVE_MOP_STATE - Leave MOP state
02F8 736      :+
02F8 737      : LEAVE_MOP_STATE - Leave MOP state for an LPD
02F8 738      :
02F8 739      : This routine is called to reset LPD fields when leaving MOP state.
02F8 740      :
02F8 741      : Inputs:
02F8 742      :
02F8 743      :     R10/R11 = CRI pointers
02F8 744      :     R6 = LPD address
02F8 745      :
02F8 746      : Outputs:
02F8 747      :
02F8 748      :     None
02F8 749      :-
02F8 750      LEAVE_MOP_STATE:
02F8 751      :
02F8 752      :     Mark the circuit no longer accessed
02F8 753      :
02F8 754      CLRBIT #LPDSV_ACCESS,-           ; Mark no longer accessed
02F8 755      LPDSW_STS(R6)
02FD 756      $CLRFLD cri,l,owpid           ; Clear the owner PID
030A 757      :
030A 758      :     If we are just leaving MOP mode, then reset circuit
030A 759      :     substate and log an event record.
030A 760      :
02F8 761      BBCC #LPDSV_DLE,-           ; Clear DLE flag
030C 762      LPDSW_STS(R6),30$           ; If already cleared, skip following
030F 763      MOVB #NMASC_LINSS_SYN,-     ; Enter "synchronizing" substate
0311 764      LPDSB_SUB_STA(R6)
0313 765      MOVAB NET$AB_EVT_WQE,R5     ; Get address of common WQE
031A 766      MOVW LPDSW_PTH(R6),-       ; Set LPD ID into WQE
031D 767      WQESW_REQIDT(R5)
031F 768      MOVW #EVCSC_DLL_LSC,-     ; "locally initiated state change"
0323 769      WQESW_EVL_CODE(R5)
0325 770      MOVB #EVCSC_DLC_POLD_MAIN,- ; Old state = MAINTAINANCE
0327 771      WQESB_EVL_DT1(R5)
0329 772      MOVB #EVCSC_DLC_POLD_RUNG,- ; New state = RUNNING
032B 773      WQESB_EVL_DT2(R5)
032D 774      BSBW NET$EVT_INTRAW         ; Log the event record
0330 775      RSB

```

```
0331 777 .SBTTL DLE$CANCEL - Process DLE cancel request
0331 778 :+
0331 779 : DLE$CANCEL - Process DLE cancel request
0331 780 :
0331 781 : This routine is called to perform all work needed for a cancel of a
0331 782 : DLE "accessed" channel at IPL 0. Presently, nothing needs to be done
0331 783 : except the datalink cancel I/O already done by the driver.
0331 784 :
0331 785 : Inputs:
0331 786 :
0331 787 : R3 = IRP address
0331 788 :
0331 789 : Outputs:
0331 790 :
0331 791 : R3 = IRP address, 0 if not to be returned to driver yet.
0331 792 : IRP$L_IOST1 = I/O status
0331 793 :-
0331 794 DLE$CANCEL:
38 50 00' D0 0331 795 MOVL S^#SS$ NORMAL,R0 ; Successful
A3 50 B0 0334 796 MOVW R0,IRP$L_IOST1(R3) ; Store status in IRP
05 0338 797 RSB
```

```

0339 799      .SBTTL DLE$BC_UP - Initialize DLE on broadcast circuit
0339 800      :+
0339 801      : DLE$BC_UP - Initialize DLE on a broadcast circuit which has just come up
0339 802      :
0339 803      : This routine is called when a broadcast circuit has just come up and
0339 804      : entered the "run" state. It sets up NETACP as the "shared" protocol user
0339 805      : of the "load/dump" and "loopback" NI protocols, so that DECnet can
0339 806      : receive requests from other nodes on the NI.
0339 807      :
0339 808      : Inputs:
0339 809      :
0339 810      :     R11 = CRI CNR address
0339 811      :     R10 = CRI CNF address
0339 812      :     R7  = ADJ address
0339 813      :     R6  = LPD address
0339 814      :     R4  = RCB address
0339 815      :
0339 816      : Outputs:
0339 817      :
0339 818      :     R0 = Status code
0339 819      :
0339 820      :     R1 is destroyed.
0339 821      :
0339 822      DLE$BC_UP::
0339 823      PUSH  #M<R2,R3,R4,R5,R6,R7,R8,R9> ; Save registers
0339 824      :
0339 825      :     If service functions are disabled for this circuit, then do
0339 826      :     not enable "load/dump" or "loopback" protocol types.
0339 827      :
0339 828      $GETFLD cri,l,ser ; Get SERVICE flag
0339 829      BLBS  R8,90$ ; Branch if disabled
0339 830      :
0339 831      :     Allocate and initialize a new BC context block
0339 832      :
0339 833      MOVZWL #BC_C_LENGTH,R1 ; Size of structure
0339 834      JSB  NET$ALLOCATE ; Allocate the block
0339 835      BLBC R0,100$ ; Exit if error detected
0339 836      PUSH  R2 ; Save address of block
0339 837      MOV  #0,(SP),#0,#BC_C_LENGTH-12,12(R2) ; Zero the block
0339 838      POPL  R5 ; Set R5 to block address
0339 839      MOVAB BC_Q_UNSOLED_MSGS(R5),R0 ; Get address of listhead
0339 840      MOVL  R0,(R0) ; Init listhead
0339 841      MOVAL (R0)+,(R0)
0339 842      MOVAB BC_Q_PND_RCV(R5),R0 ; Get address of listhead
0339 843      MOVL  R0,(R0) ; Init listhead
0339 844      MOVAL (R0)+,(R0)
0339 845      MOVAB BC_Q_CUR_RCV(R5),R0 ; Get address of listhead
0339 846      MOVL  R0,(R0) ; Init listhead
0339 847      MOVAL (R0)+,(R0)
0339 848      MOVW  LPD$W_PTH(R6),BC_W_LPD(R5) ; Save LPD of associated circuit
0339 849      INSQUE (R5),BC_QUEUE+4 ; Insert block into queue
0339 850      :
0339 851      :     Initialize ourselves as the "default user" of the "load/dump"
0339 852      :     protocol type.
0339 853      :
0339 854      MOVAB BC_W_LD_CHAN(R5),R3 ; Point to word to receive channel #
0339 855      MOVAB LD_SETMODE,R4 ; Point to descriptor of SETMODE buffer

```

```

00A5 30 039A 856      BSBW  INIT_UN SOL_CHAN      ; Initialize channel
16 50 F9 039D 857      BLBC  RO,100$              ; Exit if error detected
      03A0 858      ;
      03A0 859      ; Initialize ourselves as the "default user" of the "loopback"
      03A0 860      ; protocol type.
      03A0 861      ;
54 53 12 A5 3E 03A0 862      MOVAW  BC_W_LP_CHAN(R5),R3      ; Point to word to receive channel #
0000009D'EF 9E 03A4 863      MOVAB  LP_SETMODE,R4          ; Point to descriptor of SETMODE buffer
      0094 30 03AB 864      BSBW  INIT_UN SOL_CHAN      ; Initialize channel
      05 50 E9 03AE 865      BLBC  RO,100$              ; Branch if error detected
      03FC 8F BA 03B1 866 90$: POPR  #^M<R2,R3,R4,R5,R6,R7,R8,R9> ; Restore registers
      05 03B5 867      RSB      ; Exit with status
      03B6 868      ;
      03B6 869      ;
      03B6 870      ; An error occurred trying to setup the circuit for service functions.
      03B6 871      ; Log an error, and bring down the circuit.
      03B6 872      ;
      03B6 873      ;
55 00000000'EF 9E 03B6 874 100$: MOVAB  NET$AB_EVT_WQE,R5      ; Get address of common WQE
      07 80 03BD 875      MOVW   #EVC$C_NMA_ABS,-      ; "aborted service request"
      1C A5 03BF 876      ;
      04 90 03C1 877      MOVB   #EVC$C_NMA_PRSN_LOE,-      ; Reason = "line open error"
      1E A5 03C3 878      ;
      FC38' 30 03C5 879      BSBW  NET$EVT_INTRAW      ; Log the event record
50 0000'8F 3C 03C8 880      MOVZWL #LEV$C_CIN_DOWN,RO      ; Setup "circuit down" event
      FC30' 30 03CD 881      BSBW  SET_DLC_EVT          ; Queue event to DLLTRN
      DF 11 03D0 882      BRB    90$              ; Exit

```

```

03D2 884 .SBTTL DLE$BC_DOWN - Cleanup DLE on broadcast circuit
03D2 885 :+
03D2 886 :- DLE$BC_DOWN - Cleanup DLE on broadcast circuit
03D2 887 :
03D2 888 : This routine is called when a broadcast circuit leaves the "run" state.
03D2 889 : We must deallocate any BC context blocks if they were associated with this
03D2 890 : circuit.
03D2 891 :
03D2 892 : Inputs:
03D2 893 :
03D2 894 : R6 = LPD address
03D2 895 :
03D2 896 : Outputs:
03D2 897 :
03D2 898 : None
03D2 899 :-
03D2 900 DLE$BC_DOWN::
3C BB 03D2 901 PUSHR #^M<R2,R3,R4,R5> ; Save registers
03D4 902 :
03D4 903 : Locate the BC block associated with this circuit.
03D4 904 :
51 00000008'EF 9E 03D4 905 MOVAB BC_QUEUE,R1 ; Get address of BC queue
55 51 D0 03DB 906 MOVL R1,R5 ; Setup for loop
55 65 D0 03DE 907 10$: MOVL (R5),R5 ; Skip to next block in queue
51 55 D1 03E1 908 CMPL R5,R1 ; End of list?
OE 59 13 03E4 909 BEQL 90$ ; If not found, skip it
20 A5 B1 03E6 910 CMPW BC_W_LPD(R5),- ; Does the LPD ID match?
20 A6 03E9 911 LPD$Q_PTH(R6)
55 65 OF 03EB 912 BNEQ 10$ ; If not, keep looking
03ED 913 REMQUE (R5),R5 ; Remove BC from list
03F0 914 :
03F0 915 : For any non-zero channels, deassign them
03F0 916 :
50 10 A5 3C 03F0 917 MOVZWL BC_W_LD_CHAN(R5),R0 ; Get "load/dump" channel
OA 13 03F4 918 BEQL 20$ ; If nonzero,
03F6 919 $DASSGN_S CHAN=R0 ; Deassign it
50 12 A5 3C 0400 920 20$: MOVZWL BC_W_LP_CHAN(R5),R0 ; Get "loopback" channel
OA 13 0404 921 BEQL 30$ ; If nonzero,
0406 922 $DASSGN_S CHAN=R0 ; Deassign it
0410 923 30$:
0410 924 : Deallocate all unsolicited messages still waiting for
0410 925 : the process to deal with them.
0410 926 :
50 24 B5 OF 0410 927 40$: REMQUE @BC_Q_UN SOL_MSGS(R5),R0 ; Get next unsolicited message
00000000'EF 08 1D 0414 928 BVS 45$ ; Branch if none left in queue
F2 11 0416 929 JSB NET$DEALLOCATE ; Deallocate the block
041C 930 BRB 40$ ; Empty the entire queue
041E 931 45$:
041E 932 : Deallocate all receive IOWQEs waiting to be issued to
041E 933 : the NI driver.
041E 934 :
50 14 B5 OF 041E 935 60$: REMQUE @BC_Q_PND_RCV(R5),R0 ; Get next waiting receive IOWQE
00000000'EF 08 1D 0422 936 BVS 65$ ; Branch if none left in queue
F2 11 0424 937 JSB NET$DEALLOCATE ; Deallocate the block
042A 938 BRB 60$ ; Empty the entire queue
042C 939 65$:
042C 940 : Deallocate the BC context block

```

```

          042C 941
          042C 942
OC A5 95 0431 943
   09 12 0434 944
          0436 945
50 55 D0 0436 946
00000000'EF 16 0439 947
          3C BA 043F 948 90$:
          05 0441 949
          ;
          SETBIT #BC_V_DELETE,BC_B_FLAGS(R5) ; Mark block for deletion
          TSTB BC_B_REFCNT(R5) ; Are there still receives outstanding?
          BNEQ 90$ ; If so, wait for them to complete
          ; before deallocating B block
          MOVL R5,R0 ; Set the block address
          JSB NET$DEALLOCATE ; Deallocate it
          POPR #^M<R2,R3,R4,R5> ; Restore registers
          RSB
```

```

0442 951      .SBTTL INIT_UNSQL_CHAN - Initialize channel for unsolicited msgs
0442 952      :+
0442 953      : INIT_UNSQL_CHAN - Initialize channel for unsolicited messages for a protocol
0442 954      :
0442 955      : This routine is called to assign a new datalink channel, setup the channel
0442 956      : to be the "default user" of the protocol, so that messages not directly
0442 957      : intended for any other "limited users" of the protocol come to us, and then
0442 958      : issue an asynchronous receive on the channel.
0442 959      :
0442 960      : Inputs:
0442 961      :
0442 962      :     R10/R11 = CRI pointers
0442 963      :     R3 = Address of word to store channel number
0442 964      :     R4 = Address of SETMODE P2 buffer
0442 965      :     R5 = Address of BC context block
0442 966      :
0442 967      : Outputs:
0442 968      :
0442 969      :     R0 = Status code
0442 970      :
0442 971      : -
0442 971      INIT_UNSQL_CHAN:
50 0000'8F 3C 0442 972      MOVZWL #SS$ NOSUCHDEV,R0      ; Setup default error status
0442 973      $GETFLD cri,s,vmsnam      ; Get datalink device name
0442 974      BLBC R0,90$      ; Branch if error detected
0442 975      MOVQ R7,-(SP)      ; Push descriptor on stack
0442 976      MOVL SP,R0      ; Get address of descriptor
0442 977      $ASSIGN,S DEVNAM=(R0),-      ; Assign channel to NI driver
0442 978      CHAN=(R3)
0442 979      ADDL #8,SP      ; Pop descriptor off stack
0442 980      BLBC R0,90$      ; Branch if error detected
0442 981      :
0442 982      : Issue a SETMODE request to the NI driver to establish the
0442 983      : channels as accessing the protocol type as "default user".
0442 984      :
0442 985      $QIOW,S FUNC=#IOS$ SETMODE!IOSM_CTRL!IOSM_STARTUP,-
0442 986      CHAN=(R3),-
0442 987      EFN=#NETSC$ EFN_WAIT,-
0442 988      IOSB=IOSB,-
0442 989      P2=R4
0442 990      BLBC R0,90$      ; Branch if error detected
0442 991      MOVZWL IOSB,R0      ; Get final I/O status
0442 992      BLBC R0,90$      ; Branch if error detected
0442 993      :
0442 994      : Allocate and initialize an IOWQE to to be used to receive
0442 995      : unsolicited messages for this protocol.
0442 996      :
0442 997      MOVZWL #IOWQE_C LENGTH-WQESC_LENGTH,R1 ; Get additional storage size
0442 998      MOVL #WQESC_SUB_AST,R0      ; Indicate WQE sub-type
0442 999      BSBW WQE$ALLOCATE      ; Allocate a WQE - always succeeds
0442 1000      MOVW (R3),IOWQE_W_CHAN(R2) ; Store channel to datalink
0442 1001      MOVL R5,IOWQE_L_BC(R2) ; Store backpointer to BC block
0442 1002      MOVW BC_W_LPD(R5),-      ; Use LPD ID as REQIDT
0442 1003      WQE$REQIDT(R2)
0442 1004      INSQUE (R2),BC_Q_PND_RCV+4(R5); Insert on pending receive queue
0442 1005      :
0442 1006      : Issue asynchronous read on the channel, so that we are
0442 1007      : notified when someone sends us an unsolicited message.
  
```



```

0517 1071      IOSB=IOWQE_Q_IOSB(R2),-
0517 1072      ASTADR=B^RCV_DLE_MSG_AST,-
0517 1073      ASTPRM=R2,-
0517 1074      P1=IOWQE_G_MSG(R2),-      ; Address of receive buffer
0517 1075      P2=#1500,-                  ; Length of receive buffer
0517 1076      P5=R0                        ; Address of buffer to receive NI header
24 A2 C5 50 E8 053E 1077      BLBS      R0,10$                ; Branch if ok
50      50 3C 0541 1078      MOVZWL   R0,IOWQE_Q_IOSB(R2)      ; Store QIO status in IOSB
52      52 DD 0545 1079      PUSHL    R2                    ; IOWQE address
4E'AF 01 FB 0547 1080      CALLS   #1,B^RCV_DLE_MSG_AST ; Call AST routine
B9      11 054B 1081      BRB     10$                    ; Keep scanning
05      05 054D 1082      90$:     RSB
054E 1083      ;
054E 1084      ; Receive AST
054E 1085      ;
054E 1086      ;
054E 1087      ;
054E 1088      RCV_DLE_MSG AST:
0000 054E 1089      .WORD   0
50 04 AC D0 0550 1090      MOVL    4(AP),R0                ; Get WQE address
0554 1092      ;
0554 1093      ; Remove from outstanding receive queue
50 60 OF 0554 1095      REMQUE  (R0),R0                ; Remove from queue
0557 1096      ;
0557 1097      ; Queue a work queue entry to process the I/O completion
0557 1098      ;
60'AF 9E 0557 1099      MOVAB  B^RCV_DLE_MSG,-        ; Set address of work routine
OC A0 055A 1100      WQESL ACTION(R0)
FAA1' 30 055C 1101      BSBW   WQESINSQUE            ; Insert onto work queue
04 055F 1102      RET

```

NE
PS

PS
--
:SA
NE
NE
NE

Ph
--
In
Co
Pa
Sy
Pa
Sy
Ps
Cr
As

Th
17
Th
15
58

Ma
--
-s
-s
-s
-s
-s
TO
35
Th
MA

```

0560 1104      .SBTTL RCV_DLE_MSG - Receive unsolicited DLE message
0560 1105      :+
0560 1106      : RCV_DLE_MSG - Receive unsolicited DLE message
0560 1107      :
0560 1108      : This routine is called when a receive completes on one of the DLE "shared"
0560 1109      : channels. This means that an unsolicited message has come in which could
0560 1110      : not be associated with any existing protocol user. Our action is to start
0560 1111      : up a MOM process to handle the DLE session.
0560 1112      :
0560 1113      : Inputs:
0560 1114      :
0560 1115      :     R5 = IOWQE address
0560 1116      :
0560 1117      : Outputs:
0560 1118      :
0560 1119      :     None
0560 1120      :-
0560 1121      RCV_DLE_MSG:
54  34 A5  D0 0560 1122      MOVL   IOWQE_L BC(R5),R4      ; Get BC address
   OC A4  97 0564 1123      DECB   BC_B_REFCNT(R4)      ; Decrement outstanding I/O count
0567 1124      :
0567 1125      :     Locate the CRI associated with this circuit
0567 1126      :
58  0E A4  3C 0567 1127      MOVZWL BC W LPD(R4),R8      ; Get LPD ID
   FA92'  30 0568 1128      BSBW   NET$GET_LPD_CRI      ; Get LPD, CRI addresses
   2C 50  E9 056E 1129      BLBC   R0,5$              ; Exit if error detected
0571 1130      :
0571 1131      :     If the BC is marked for rundown, then this I/O completion
0571 1132      :     should be ignored, and the BC deallocated if possible.
0571 1133      :
10 0B A4  00 E1 0571 1134      BBC    #BC V DELETE,BC_B_FLAGS(R4),4$ ; If BC marked for rundown,
   OC A4  95 0576 1135      TSTB   BC_B_REFCNT(R4)      ; Any more receives still outstanding?
   22 12 0579 1136      BNEQ   5$                ; If so, don't deallocate BC yet
   50 54  D0 057B 1137      MOVL   R4,R0              ; Set address of BC
00000000'EF 16 057E 1138      JSB    NET$DEALLOCATE      ; Deallocate BC
   17 11 0584 1139      BRB    5$                ; and deallocate IOWQE as well
0586 1140      4$:
0586 1141      :
0586 1142      :     If I/O status was not successful, then stop doing any I/O
0586 1143      :     on this channel (assume it is in the process of running down).
1D 24 A5  E8 0586 1144      BLBS   IOWQE_Q IOSB(R5),10$ ; If I/O failure,
   07 B0 058A 1145      MOVW   #EVC$C NMA_ABS,-    ; "Aborted service request"
   1C A5  058C 1146      :
   01 90 058E 1147      MOVW   #EVC$C NMA PRSN ERR,- ; "Receive error"
   1E A5  0590 1148      :
   FA6B' 30 0592 1149      BSBW   NET$EVT INTRAW      ; Log the event record
50  0000'8F 3C 0595 1150      MOVZWL #LEV$C [IN DOWN,R0 ; Setup "circuit down" event
   FA63' 30 059A 1151      BSBW   SET_DLC_EVT         ; Queue event to DLLTRN
   50 55  D0 059D 1152      5$: MOVL   R5,R0              ; Get IOWQE address
00000000'EF 16 05A0 1153      JSB    NET$DEALLOCATE      ; Deallocate it
   05 05A6 1154      RSB
05A7 1155      10$:
05A7 1156      :
05A7 1157      :     If there is already an unsolicited message received from
05A7 1158      :     the remote node waiting for the MOM process to startup,
05A7 1159      :     then drop the message on the floor - don't startup a
05A7 1159      :     redundant MOM process for the same node.
05A7 1160      :

```

```

RCV_DLE_MSG - Receive unsolicited DLE me
51 24 A4 9E 05A7 1161      MOVAB  BC_Q_UN SOL_MSGS(R4),R1 ; Get address of unsolicited msg queue
52 51 D0 05AB 1162      MOVL   R1,R2                  ; Setup for loop
52 62 D0 05AE 1163 15$: MOVL   (R2),R2                ; Skip to next msg in list
51 52 D1 05B1 1164      CML    R2,R1                  ; End of list?
OE 13 05B4 1165      BEQL   20$                    ; If so, then skip it
06 BB 05B6 1166      PUSHR #^M<R1,R2>              ; Save registers
OE 29 05B8 1167      CMPC  #NIHDR$IZ,-             ; Does the NI header match?
38 A2 05BA 1168      IOWQE_G_NIHDR(R2),-
38 A5 05BC 1169      IOWQE_G_NIHDR(R5),-
06 BA 05BE 1170      POPR  #^M<RT,R2>              ; Restore registers
EC 12 05C0 1171      BNEQ  15$                    ; If it doesn't match, keep looking
06 11 05C2 1172      BRB   30$                    ; If match found, drop msg on floor
05C4 1173 20$:
05C4 1174      ; Startup a process to deal with the message
05C4 1175      ;
OOAE 30 05C4 1176      BSBW  STARTUP_MOM             ; Start MOM process
05C7 1177      ;
05C7 1178      ; If the process could not be created, re-issue the read
05C7 1179      ; request using the same buffer.
05C7 1180      ;
18 B4 50 E8 05C7 1181 30$: BLBS  R0,40$                  ; Branch if successful
51 65 OE A4 3C 05CA 1182      INSQUE (R5),@ABC_Q_PND_RCV+4(R4); Insert on pending receive queue
51 FE 30 05CE 1183      MOVZWL BC_W_LPD(R4),RT        ; Get LPD ID
FE 30 05D2 1184      BSBW  ISSUE_NI_READ           ; Re-issue read request
05 05D5 1185      RSB
05D6 1186      ;
05D6 1187      ; Save PID of MOM process just started in unsolicited message
05D6 1188      ; context block. From now on, this message is "tagged" for
05D6 1189      ; that process: If the process comes in with an ACCESS function,
05D6 1190      ; we give it the message; if the process dies, we deallocate the
05D6 1191      ; message.
30 A5 51 D0 05D6 1193 40$: MOVL   R1,IOWQE_L_PID(R5)          ; Save PID of associated MOM process
05DA 1194      ;
05DA 1195      ; Insert the message on the queue waiting for the process to
05DA 1196      ; get started.
28 B4 65 OE 05DA 1198      INSQUE (R5),@ABC_Q_UN SOL_MSGS+4(R4) ; Insert at end of queue
05DE 1199      ;
05DE 1200      ; Re-issue another receive request for this protocol type
05DE 1201      ;
51 05FE 8F 3C 05DE 1202      MOVZWL #IOWQE_C_LENGTH-WQESC_LENGTH,R1 ; Get additional storage size
50 03 D0 05E3 1203      MOVL   #WQESC_SUB_AST,R0      ; Indicate WQE sub-type
FA17 30 05E6 1204      BSBW  WQES$ALLOCATE           ; Allocate a WQE - always succeeds
2C A5 B0 05E9 1205      MOVW  IOWQE_W_CHAN(R5),-      ; Copy channel to datalink
2C A2 B0 05EC 1206      MOVW  IOWQE_W_CHAN(R2),-
34 A5 D0 05EE 1207      MOVL  IOWQE_L_BC(R5),-        ; Copy backpointer to BC block
34 A2 D0 05F1 1208      MOVL  IOWQE_L_BC(R2),-
12 A5 B0 05F3 1209      MOVW  WQESW_REQIDT(R5),-      ; Use the same REQIDT
12 A2 B0 05F6 1210      MOVW  WQESW_REQIDT(R2),-
18 B4 62 OE 05F8 1211      INSQUE (R2),@ABC_Q_PND_RCV+4(R4); Insert on pending receive queue
51 0E A4 3C 05FC 1212      MOVZWL BC_W_LPD(R4),RT        ; Get LPD ID
FE C1 30 0600 1213      BSBW  ISSUE_NI_READ           ; Issue another read request
05 0603 1214 90$:      RSB

```

```

0604 1216      .SBTTL DLE$MOP_REQUEST - Partner has requested MOP mode
0604 1217      :+
0604 1218      : DLE$MOP_REQUEST - The circuit partner has requested MOP mode
0604 1219      :
0604 1220      : This routine is called when the datalink has received a MOP message
0604 1221      : from the partner node on a point-to-point datalink.
0604 1222      :
0604 1223      : Inputs:
0604 1224      :
0604 1225      :     R10/R11 = CRI pointers
0604 1226      :     R6 = LPD address
0604 1227      :
0604 1228      : Outputs:
0604 1229      :
0604 1230      :     None
0604 1231      :
0604 1232      :     R0-R3,R8-R9 are destroyed.
0604 1233      :
0604 1234      : DLE$MOP_REQUEST::
00F0 8F  BB 0604 1235      PUSH  #^M<R4,R5,R6,R7>      ; Save registers
          02  E2 0608 1236      BBS    #LPDSV_DLE,-      ; Mark circuit in MOP mode
1D 22 A6  060A 1237      LPDSW_STS(R6),10$      ; If already marked, skip logging event
          060D 1238      :
          060D 1239      :     Log an event indicating the circuit has gone into MOP mode
          060D 1240      :
55 00000000'EF 9E 060D 1241      MOVAB NET$AB_EVT,WQE,R5      ; Get address of common WQE
          20 A6  B0 0614 1242      MOVW  LPDSW_PTH(R6),-      ; Set LPD ID into WQE
          12 A5  0617 1243      MOVW  WQESW_REQIDT(R5)
          0141 8F B0 0619 1244      MOVW  #EVCSC_DLL_RSC,-      ; 'remotely initiated state change'
          1C A5  061D 1245      MOVW  WQESW_EVL_CODE(R5)
          03 90 061F 1246      MOVW  #EVCSC_DLC_POLD_RUNG,- ; Old state = RUNNING
          1E A5  0621 1247      MOVW  WQESB_EVL_DT1(R5)
          04 90 0623 1248      MOVW  #EVCSC_DLC_POLD_MAIN,- ; New state = MAINTAINANCE
          1F A5  0625 1249      MOVW  WQESB_EVL_DT2(R5)
          F9D6' 30 0627 1250      BSBW  NET$EVT_INTRAW      ; Log the event record
          062A 1251      :
          062A 1252      :     If circuit is already accessed, then ignore MOP notification
          062A 1253      :
          2A 22 03  E0 062A 1254 10$: BBS    #LPDSV_ACCESS,-      ; Branch if circuit accessed
          A6  062C 1255      LPDSW_STS(R6),40$
          062F 1256      :
          062F 1257      :     If service functions are disabled for this circuit, then
          062F 1258      :     ignore MOP request, and recycle circuit.
          062F 1259      :
          24 58  E8 062F 1260      $GETFLD cri,l,ser      ; Get SERVICE flag
          063C 1261      BLBS  R8,50$      ; Branch if disabled
          063F 1262      :
          063F 1263      :     Set the circuit substate to "auto-service"
          063F 1264      :
          27 06 90 063F 1265      MOVW  #NMASC_LINSS_ASE,-      ; Set circuit substate
          A6  0641 1266      LPDSB_SUB_STA(R6)
          0643 1267      :
          0643 1268      :     Startup a process to deal with the message
          0643 1269      :
          002F 30 0643 1270      BSBW  STARTUP_MOM      ; Start MOM process
          1A 50  E9 0646 1271      BLBC  R0,50$      ; Branch if unsuccessful
          0649 1272      :

```

```
0649 1273 ; Save PID of MOM process just started in CRI block
0649 1274 ;
58 51 D0 0649 1275 MOVL R1,R8 ; Setup PID of created process
064C 1276 $PUTFLD cri,l,owpid ; Set DLE owner of circuit
0659 1277 ;
0659 1278 ; We can respond to the MOP request. Recycle the circuit
0659 1279 ; and force it to come up in "MOP" state (because of the
0659 1280 ; DLE flag).
0659 1281 ;
50 0000'8F 3C 0659 1282 40$: MOVZWL #LEV$C_LIN_DOWN,R0 ; Setup "line down" event
F99F' 30 065E 1283 BSBW SET_DLE_EVT ; Queue the event
OD 11 0661 1284 BRB 90$
0663 1285 ;
0663 1286 ;
0663 1287 ; We cannot respond to the MOP request. Recycle the circuit
0663 1288 ; and force it to come back in regular mode.
0663 1289 ;
50 0000'8F 3C 0663 1290 50$: CLRBIT #LPD$V_DLE,LPD$W_STS(R6) ; Mark circuit in "normal" mode
F990' 30 0668 1291 MOVZWL #LEV$C_LIN_DOWN,R0 ; Setup "line down" event
00F0 8F BA 066D 1292 BSBW SET_DLE_EVT ; Queue the event
05 0670 1293 90$: POPR #^MZR4,R5,R6,R7> ; Restore registers
0674 1294 RSB
```

```

0675 1296 .SBTTL STARTUP_MOM - Start MOM process
0675 1297 :+
0675 1298 : STARTUP_MOM - Start MOM process for auto-service
0675 1299 :
0675 1300 : This routine is called to start the MOM process.
0675 1301 :
0675 1302 : Inputs:
0675 1303 :
0675 1304 : R10/R11 = CRI pointers
0675 1305 :
0675 1306 : Outputs:
0675 1307 :
0675 1308 : R0 = Status code
0675 1309 : R1 = IPID of process, if successful
0675 1310 :
0675 1311 : R2-R3,R7-R9 are destroyed.
0675 1312 :
0675 1313 : -
0675 1314 : STARTUP_MOM:
30 BB 0675 1314 : PUSHR #M<R4,R5> ; Save registers
0677 1315 : $GETFLD cri,s,nam ; Get circuit name
0684 1316 :
0684 1317 : : Repeatedly try to startup MOM, and if it fails due to "duplicate
0684 1318 : : process name", then try again with another process name until
0684 1319 : : it succeeds.
0684 1320 :
59 01 DO 0684 1321 : MOVL #1,R9 ; Start with postfix #1
5E 0C C2 0687 1322 10$: : SUBL #12,SP ; Allocate prcnam buffer on stack
5E 5E DD 068A 1323 : PUSHL SP ; Construct descriptor of buffer
51 00000005'EF 9E 068E 1325 : MOVAB MOM_PRCNAM,R1 ; Get address of FAO string
50 81 9A 0695 1326 : MOVZBL (R1)+,R0 ; Construct descriptor of FAO string
7E 50 7D 0698 1327 : MOVQ R0,-(SP) ; Push FAO descriptor onto stack
50 5E DO 069B 1328 : MOVL SP,R0 ; Get stack address
069E 1329 : $FAO_S CTRSTR=(R0),- ; Construct process name
069E 1330 : OUTBUF=8(R0),-
069E 1331 : OUTLEN=8(R0),-
069E 1332 : P1=R7,- ; Length of circuit name
069E 1333 : P2=R8,- ; Address of circuit name
069E 1334 : P3=R9 ; Process number
5E 08 C0 06B3 1335 : ADDL #8,SP ; Pop FAO string descriptor
54 8E 7D 06B6 1336 : MOVQ (SP)+,R4 ; R4/R5 = descriptor of process name
52 57 7D 06B9 1337 : MOVQ R7,R2 ; Pass circuit name as SYS$NET
0180 8F BB 06BC 1338 : PUSHR #M<R7,R8> ; Save circuit name
58 00000000'EF 9E 06C0 1339 : MOVAB MOM_OBJ_NAM,R8 ; Point to ASCII MOM object name
57 88 9A 06C7 1340 : MOVZBL (R8)+,R7 ; Construct descriptor of name
F933' 30 06CA 1341 : BSBW NET$STARTUP_OBJ_NAM ; Startup the object
0180 8F BA 06CD 1342 : POPR #M<R7,R8> ; Restore circuit name
5E 0C C0 06D1 1343 : ADDL #12,SP ; Pop process name buffer
0000'8F 50 B1 06D4 1344 : CMPW R0,#SS$_DUPLNAM ; Process name already exist?
08 12 06D9 1345 : BNEQ 20$ ; If so,
FFA6 59 01 0A F1 06DB 1346 : ACBL #MAX_MOM_PROC,#1,R9,10$ ; Increment number and try again
1A 11 06E1 1347 : BRB 90$ ; Exit with error, but don't log
06E3 1348 : ; any error - too many MOMs already
06E3 1349 20$: :
06E3 1350 : : If the process could not be created, log an event record.
06E3 1351 :
17 50 E8 06E3 1352 : BLBS R0,90$ ; Branch if successful

```

```
55 00000000 50 DD 06E6 1353      PUSHL  R0          ; Save status
      EF 9E 06E8 1354      MOVAB  NET$AB_EVT_WQE,R5 ; Get address of common WQE
      07 B0 06EF 1355      MOVW   #EVCSC-NMA-ABS,- ; "aborted service request"
      1C A5 06F1 1356      WQESW EVL CODE(R5)
      04 90 06F3 1357      MOVB   #EVCSC-NMA-PRSN-LOE,- ; Reason = "line open error"
      1E A5 06F5 1358      WQESB EVL DT1(R5)
      F906' 30 06F7 1359      BSBW  NET$EVT_INTRAW    ; Log the event record
      50 8ED0 06FA 1360     POPL  R0          ; Restore status
      30 BA 06FD 1361 90$: POPR  #^M<R4,R5> ; Restore registers
      05 06FF 1362      RSB
```

```

0700 1364 .SBTTL ATTACH_UNSQL_MSG - Attach unsolicited message
0700 1365 :+
0700 1366 : ATTACH_UNSQL_MSG - Attach unsolicited message to newly accessed DWB
0700 1367 :
0700 1368 : This routine is called to search the unsolicited message queue, and
0700 1369 : if one is found for this DLE user, to insert the message onto it's
0700 1370 : private receive queue.
0700 1371 :
0700 1372 : Inputs:
0700 1373 :
0700 1374 : R3 = IOS_ACCESS IRP address
0700 1375 : R4 = DWB address
0700 1376 :
0700 1377 : Outputs:
0700 1378 :
0700 1379 : IRP$L_EXTEND(R3) = Address of CXB containing unsolicited message
0700 1380 : (or zero if no message found)
0700 1381 :
0700 1382 : CXB$W_LENGTH = Message length in bytes (not incl. NI header)
0700 1383 : CXB$C_HEADER = 14-byte NI datalink header
0700 1384 : CXB$C_HEADER+14 = Message
0700 1385 :
0700 1386 : R0-R1 are destroyed.
0700 1387 :-
0700 1388 ATTACH_UNSQL_MSG:
54 55 DD 0700 1389 PUSH R5 ; Save registers
54 A3 D4 0702 1390 CLRL IRP$L_EXTEND(R3) ; Preset no CXB address
0705 1391 :
0705 1392 : Locate the BC block associated with this circuit.
0705 1393 :
51 00000008'EF 9E 0705 1394 MOVAB BC_QUEUE,R1 ; Get address of BC queue
55 51 D0 070C 1395 MOVL R1,R5 ; Setup for loop
55 65 D0 070F 1396 5$: MOVL (R5),R5 ; Skip to next block in queue
51 55 D1 0712 1397 CMPL R5,R1 ; End of list?
OE A5 B1 0715 1398 BEQL 90$ ; If not found, skip it
3E A4 0717 1399 CMPW BC W LPD(R5),- ; Does the LPD ID match?
F1 12 071A 1400 DWB$Q_PATH(R4)
071C 1401 BNEQ 5$ ; If not, keep looking
071E 1402 :
071E 1403 : Search for unsolicited message which was "tagged" for
071E 1404 : this process.
071E 1405 :
51 24 A5 9E 071E 1406 MOVAB BC_Q_UNSQL_MSGS(R5),R1 ; Get address of unsolicited msg queue
55 51 D0 0722 1407 MOVL R1,R5 ; Setup for loop
55 65 D0 0725 1408 10$: MOVL (R5),R5 ; Skip to next msg in list
51 55 D1 0728 1409 CMPL R5,R1 ; End of list?
30 A5 D1 072B 1410 BEQL 90$ ; If so, then skip it
OC A3 072D 1411 CMPL IOWQE_L_PID(R5),- ; Does the IPID match?
F1 12 0730 1412 IRP$L_PID(R3)
0732 1413 BNEQ 10$ ; If not, keep looking
0734 1414 :
0734 1415 : Allocate a CXB from non-paged pool, store the message into
0734 1416 : the block, and insert it into the DWB receive queue.
0734 1417 :
51 51 26 A5 3C 0734 1418 MOVZWL IOWQE_W_MSGLEN(R5),R1 ; Get size of message
0000005A 8F C0 0738 1419 ADDL #CXB$C_OVERHEAD+NIHDRSIZ,R1 ; Compute size of CXB
00000000'EF 16 073F 1420 JSB NET$ALONPAGED ; Allocate from non-paged pool

```

```
08 A2 29 50 E9 0745 1421 BLBC R0,90$ ; If insufficient memory, skip it
OA A2 51 B0 0748 1422 MOVW R1,CXBSW SIZE(R2) ; Set size of structure
62 A2 1B 90 074C 1423 MOVB #DYN$C_CXB,CXBSB_TYPE(R2) ; Set type of structure
62 56 A2 9E 0750 1424 MOVAB CXB$C_HEADER+ ; Set data area address in CXB
0754 1425
26 A5 B0 0754 1426 MOVW IOWQE_W_MSGL$N(R5),- ; Save message size in CXB
OC A2 0757 1427 CXBSW_LENGTH(R2)
54 A3 52 D0 0759 1428 MOVL R2,IRPSL_EXTEND(R3) ; Save address of CXB
3C BB 075D 1429 PUSHR #^M<R2,R3,R4,R5> ; Save registers
OE 28 075F 1430 MOVC #NIHDR$IZ,- ; Copy NI datalink header
38 A5 0761 1431 IOWQE_G_NIHDR(R5),-
48 A2 0763 1432 CXB$C_HEADER(R2)
55 OC AE D0 0765 1433 MOVL 3*4(SP),R5 ; Recover IOWQE address
26 A5 28 0769 1434 MOVC IOWQE_W_MSGL$N(R5),- ; Copy message
46 A5 076C 1435 IOWQE_G_MSG(R5),-
63 076E 1436 (R3)
3C BA 076F 1437 POPR #^M<R2,R3,R4,R5> ; Restore registers
55 8ED0 0771 1438 90$: POPL R5 ; Restore registers
05 0774 1439 RSB
```

```

0775 1441      .SBTTL DLE$PRC_EXIT - Handle MOM process termination
0775 1442      :+
0775 1443      : DLE$PRC_EXIT - Handle MOM process termination
0775 1444      :
0775 1445      : This routine is called whenever any process "owned" by NETACP terminates.
0775 1446      : We must check if we have any unsolicited MOP messages intended for the
0775 1447      : terminated process, and if so, clean them up.
0775 1448      :
0775 1449      : Inputs:
0775 1450      :
0775 1451      :     R8 = IPID of terminated process
0775 1452      :
0775 1453      : Outputs:
0775 1454      :
0775 1455      :     None
0775 1456      :-
0775 1457      DLE$PRC_EXIT::
0775 1458      :
0775 1459      :     Scan all broadcast circuits
0775 1460      :
51 00000008'EF 9E 0775 1461      MOVAB BC_QUEUE,R1      ; Get address of BC queue
      55 51 DO 077C 1462      MOVL R1,R5      ; Setup for loop
      55 65 DO 077F 1463 5$: MOVL (R5),R5      ; Skip to next block in queue
      51 55 D1 0782 1464      CMPL R5,R1      ; End of list?
      25 13 0785 1465      BEQL 20$      ; If not found, skip it
0787 1466      :
0787 1467      :     Deallocate any messages which are intended for this process
0787 1468      :
52 24 A5 9E 0787 1469      MOVAB BC_Q_UN SOL_MSGS(R5),R2 ; Get address of unsolicited msg queue
      53 52 DO 078B 1470      MOVL R2,R3      ; Setup for loop
      53 63 DO 078E 1471 10$: MOVL (R3),R3      ; Skip to next msg in list
      52 53 D1 0791 1472 15$: CMPL R3,R2      ; End of list?
      E9 13 0794 1473      BEQL 5$      ; If so, then continue to next circuit
58 30 A3 D1 0796 1474      CMPL IOWQE_L_PID(R3),R8 ; Does the IPID match?
      F2 12 079A 1475      BNEQ 10$      ; If not, keep looking
      63 DD 079C 1476      PUSHL (R3)      ; Save pointer to next block in list
      50 63 OF 079E 1477      REMQUE (R3),R0 ; Remove it from the queue
00000000'EF 16 07A1 1478      JSB NET$DEALLOCATE ; Deallocate the block
      53 8ED0 07A7 1479      POPL R3      ; Set R3 to next block in list
      E5 11 07AA 1480      BRB 15$      ; Keep looking for more
07AC 1481 20$:
07AC 1482      :
07AC 1483      :     If any circuits are in MOP state waiting for the MOM
07AC 1484      :     process to issue its initial ACCESS, then reset them
07AC 1485      :     back into normal state. We recognize this condition
07AC 1486      :     if the OWPID field is still set to the PID, meaning
07AC 1487      :     that the process must never have accessed the DLE
07AC 1488      :     channel (or else we would have cleared it on DEACCESS).
5B 00000000'EF DO 07AC 1489      MOVL NET$GL_CNR_CRI,R11 ; Point to CRI database
      5A D4 07B3 1490      CLRL R10      ; Start at beginning
      13 50 E9 07B5 1491 25$: $SEARCH egl_cri,l,owpid ; Search for circuits
      F836' 30 07C4 1492      BLBC R0,30$ ; Branch if none found
      E8 50 E9 07C7 1493      BSBW NET$LOCATE_LPD ; Locate associated LPD
      FB28 30 07CA 1494      BLBC R0,25$ ; If error detected, skip it
50 0000'8F 3C 07CD 1495      BSBW LEAVE MOP STATE ; Return circuit to normal mode
      F828' 30 07D0 1496      MOVZWL #LEV$C_LIN_DOWN,R0 ; Setup "line down" event
      07D5 1497      BSBW SET_DLC_EVT ; Queue the event

```

NETDLE
V04-000

- NETACP DLE processing
DLE\$PRC_EXIT - Handle MOM process termin

C 2

16-SEP-1984 01:24:27
5-SEP-1984 02:19:17

VAX/VMS Macro V04-00
[NETACP.SRC]NETDLE.MAR;1

Page 37
(19)

```
DB 11 07DB 1498 BRB 25$ ; Keep looping
    05 07DA 1499 30$ RSB
      07DB 1500
      07DB 1501
      07DB 1502 .END
```

NE
VO

```

SST1 = 00000000
SST2 = 00000006
ABD$C_FIB = 00000001
ABD$C_LENGTH = 00000008
ABD$C_NAME = 00000002
ABD$W_COUNT = 00000002
ABD$W_TEXT = 00000000
ACP$C_STA_F = 00000004
ACP$C_STA_H = 00000005
ACP$C_STA_I = 00000000
ACP$C_STA_N = 00000001
ACP$C_STA_R = 00000002
ACP$C_STA_S = 00000003
ATTACH_UN$OL_MSG = 00000700 R 04
BC_ACCESS = 000001C0 R 04
BC_B_FLAGS = 0000000B G
BC_B_REFCNT = 0000000C G
BC_B_TYPE = 0000000A G
BC_C_LENGTH = 0000002C G
BC_L_FLINK = 00000000 G
BC_M_DELETE = = 00000001 G
BC_QUEUE = 00000008 R 02
BC_Q_CUR_RCV = 0000001C G
BC_Q_PND_RCV = 00000014 G
BC_Q_UN$OL_MSGS = 00000024 G
BC_V_DELETE = = 00000000 G
BC_W_LD_CHAN = 00000010 G
BC_W_LP = 0000000E G
BC_W_LP_CHAN = 00000012 G
BC_W_SIZE = 00000008 G
BIT... = 00000001
CCB$U_UCB = = 00000000
CNF$C_R_FIELD = ***** X 04
CNF$G_T_FIELD = ***** X 04
CNF$K_Y_SEARCH = ***** X 04
CNF$P_U_T_FIELD = ***** X 04
CNF$_ADVANCE = = 00000000
CNF$_QUIT = = 00000002
CNF$_TAKE_CURR = = 00000003
CNF$_TAKE_PREV = = 00000001
CXB$B_TYPE = = 0000000A
CXB$C_HEADER = = 00000048
CXB$C_OVERHEAD = = 0000004C
CXB$W_LENGTH = = 0000000C
CXB$W_SIZE = = 00000008
DDT$U_UN$OL_INT = = 00000004
DLE$ACCESS = 00000075 R 04
DLE$BC_DOWN = 000003D2 RG 04
DLE$BC_UP = 00000339 RG 04
DLE$CANCEL = 00000331 R 04
DLE$DEACCESS = 000002A7 R 04
DLE$DISPATCH = 00000000 RG 04
DLE$LPD_STATUS = 00000157 RG 04
DLE$MOP_REQUEST = 00000604 RG 04
DLE$PRC_EXIT = 00000775 RG 04
DLE$SETMODE = 0000021F R 04
DLE_ACC = 00000000 R 02

```

```

DWBSB_SUBSTA = 00000046
DWBSL_DLL_UCB = = 00000048
DWBSV_BC = = 00000003
DWBSW_DLL_CHAN = = 0000004C
DWBSW_FLAGS = = 0000000E
DWBSW_PATH = = 0000003E
DYN$C_CXB = = 0000001B
EVC$C_DLL_LSC = = 00000140
EVC$C_DLL_POLD_MAIN = = 00000004
EVC$C_DLL_POLD_RUNG = = 00000003
EVC$C_DLL_RSC = = 00000141
EVC$C_NMA_ABS = = 00000007
EVC$C_NMA_PRSN_ERR = = 00000001
EVC$C_NMA_PRSN_LOE = = 00000004
EXESIN$IOQ = ***** X 04
INIT_UN$OL_CHAN = 00000442 R X 04
IOSM_CTRL = = 00000200
IOSM_STARTUP = = 00000040
IOS_ACCESS = = 00000032
IOS_ACPCONTROL = = 00000038
IOS_DEACCESS = = 00000034
IOS_READVBLK = = 00000031
IOS_SETMODE = = 00000023
IOCSVERIFYCHAN = ***** X 04
IOSB = 00000010 R X 02
IOWQE_C_LENGTH = 00000622 G
IOWQE_G_MSG = 00000046 G
IOWQE_G_NIHDR = 00000038 G
IOWQE_L_BC = 00000034 G
IOWQE_L_PID = 00000030 G
IOWQE_Q_IOSB = 00000024 G
IOWQE_W_CHAN = 0000002C G
IOWQE_W_MSGLEN = = 00000026
IRP$U_DIAGBUF = = 0000004C
IRP$U_EXTEND = = 00000054
IRP$U_IOST1 = = 00000038
IRP$U_IOST2 = = 0000003C
IRP$U_PID = = 0000000C
IRP$U_SVAPTE = = 0000002C
IRP$U_UCB = = 0000001C
IRP$U_WIND = = 00000018
IRP$V_FCODE = = 00000006
IRP$V_COMPLX = = 00000003
IRP$V_FCODE = = 00000000
IRP$V_FUNC = = 00000020
IRP$V_STS = = 0000002A
ISSUE_NI_READ = 000004C4 R 04
LD_PARAMS = 00000011 R R 03
LD_SETMODE = 00000053 R R 03
LEAVE_MOP_STATE = 000002F8 R 04
LEV$C_DLE_ACC = ***** X 04
LEV$C_LIN_DOWN = ***** X 04
LPD$B_SUB_STA = = 00000027
LPD$U_UCB = = 00000010
LPD$V_ACCESS = = 00000003
LPD$V_BC = = 0000000A
LPD$V_DLE = = 00000002

```

NETDLE
Symbol table

- NETACP DLE processing

E 2

16-SEP-1984 01:24:27 VAX/VMS Macro V04-00
5-SEP-1984 02:19:17 [NETACP.SRC]NETDLE.MAR;1

Page 39
(19)

```

LPDSV_RUN = 00000004
LPDSV_X25 = 00000007
LPDSW_CHAN = 00000014
LPDSW_PTH = 00000020
LPDSW_STS = 00000022
LP_PARAMS = 0000005B R 03
LP_SETMODE = 0000009D R 03
MAX_MOM_PROC = 0000000A
MOM_OBJ_NAM = 00000000 R 03
MOM_PRCNAM = 00000005 R 03
NET$AB_EVT_WQE ***** X 04
NET$ALLOCATE ***** X 04
NET$ALONPAGED ***** X 04
NETSC_ACT_TIMER = 0000001E
NETSC_EFN_ASYN = 00000002
NETSC_EFN_WAIT = 00000001
NETSC_IPL = 00000008
NETSC_MAXACCFLD = 00000027
NETSC_MAXLINNAM = 0000000F
NETSC_MAXLNK = 000003FF
NETSC_MAXNODNAM = 00000006
NETSC_MAXOBJNAM = 0000000C
NETSC_MAX_AREAS = 0000003F
NETSC_MAX_LINES = 00000040
NETSC_MAX_NCB = 0000006E
NETSC_MAX_NODES = 000003FF
NETSC_MAX_OBJ = 000000FF
NETSC_MAX_WQE = 00000014
NETSC_MINBUFSIZ = 000000C0
NETSC_TID_ACT = 00000003
NETSC_TID_RUS = 00000001
NETSC_TID_XRT = 00000002
NETSC_TRCTL_CEL = 00000002
NETSC_TRCTL_OVR = 00000005
NETSC_UTLBUFSIZ = 00001000
NETSDEALLOCATE ***** X 04
NETSEVT_INTRAW ***** X 04
NETSFIND_LPD ***** X 04
NETSGET_CPD_CRI ***** X 04
NETSGL_CNR_CRI ***** X 04
NETSGL_DLE_UCB ***** X 04
NETSLOCATE_LPD ***** X 04
NETSM_MAXLNKMSK = 000003FF
NET$STARTUP_OBJ_NAM ***** X 04
NFB$C_CRI_NAM = 04020041
NFB$C_CRI_OWPID = 04010010
NFB$C_CRI_SER = 04000002
NFB$C_CRI_STA = 04010013
NFB$C_CRI_VMSNAM = 04020042
NFB$C_OP_EQL = 00000000
NIHDRSIZ = 0000000E
NMASC_ACC_SHR = 00000001
NMASC_LINMC_SET = 00000001
NMASC_LINSS_ASE = 00000006
NMASC_LINSS_SYN = 0000000A
NMASC_PCLI_ACC = 00000B1E
NMASC_PCLI_BFN = 00000451

```

```

NMASC_PCLI_BUS = 00000AF1
NMASC_PCLI_CRC = 00000B1C
NMASC_PCLI_DCH = 00000B1B
NMASC_PCLI_MCA = 00000B0F
NMASC_PCLI_MLT = 00000B19
NMASC_PCLI_PAD = 00000B1A
NMASC_PCLI_PRM = 00000B18
NMASC_PCLI_PTY = 00000B0E
NMASC_STATE_OFF = 00000001
NMASC_STATE_ON = 00000000
NSP$C_EXT_LNK = 0000001E
NSP$C_MAXHDR = 00000009
RCV_DCE_MSG = 00000560 R 04
RCV_DLE_MSG_AST = 0000054E R 04
SET_DLL_EVT ***** X 04
SIZ... = 00000001
SS$_DEVALLOC ***** X 04
SS$_DEVINACT ***** X 04
SS$_DUPLNAM ***** X 04
SS$_FILNOTACC ***** X 04
SS$_ILLIOFUNC ***** X 04
SS$_IVMODE ***** X 04
SS$_NORMAL ***** X 04
SS$_NOSUCHDEV ***** X 04
STARTUP_MOM = 00000675 R 04
SYSSASSIGN ***** GX 04
SYSSDASSGN ***** GX 04
SYSSFAO ***** X 04
SYSSQIO ***** GX 04
SYSSQIOW ***** GX 04
TID_C_READSUP = 00000001
TR$C_MAXHDR = 0000001C
TR$C_NI_ALLEND1 = 040000AB
TR$C_NI_ALLEND2 = 00000000
TR$C_NI_ALLROU1 = 030000AB
TR$C_NI_ALLROU2 = 00000000
TR$C_NI_PREFIX = 000400AA
TR$C_NI_PROT = 00000360
TR$C_PRI_ECL = 0000001F
TR$C_PRI_RTHRU = 0000001F
UCB$C_DDT = 00000088
WQES$ALLOCATE ***** X 04
WQESB_EVL_DT1 = 0000001E
WQESB_EVL_DT2 = 0000001F
WQESC_LENGTH = 00000024
WQESC_QUAL_DLE = 00000004
WQESC_SUB_AST = 00000003
WQESDEALLOCATE ***** X 04
WQESINSQUE ***** X 04
WQESL_ACTION = 0000000C
WQESRESET_TIM ***** X 04
WQESW_EVL_CODE = 0000001C
WQESW_REQIDT = 00000012
_$$_ = 00000000

```

NE
VO

! Psect synopsis !

PSECT name	Allocation	PSECT No.	Attributes
. ABS .	00000000 (0.)	00 (0.)	NOPIC USR CON ABS LCL NOSHR NOEXE NORD NOWRT NOVEC BYTE
\$AB\$\$	00000622 (1570.)	01 (1.)	NOPIC USR CON ABS LCL NOSHR EXE RD WRT NOVEC BYTE
NET_IMPURE	00000018 (24.)	02 (2.)	NOPIC USR CON REL LCL NOSHR NOEXE RD WRT NOVEC LONG
NET_PURE	000000A5 (165.)	03 (3.)	NOPIC USR CON REL LCL NOSHR NOEXE RD NOWRT NOVEC LONG
NET_CODE	000007DB (2011.)	04 (4.)	NOPIC USR CON REL LCL NOSHR EXE RD NOWRT NOVEC BYTE

! Performance indicators !

Phase	Page faults	CPU Time	Elapsed Time
Initialization	27	00:00:00.11	00:00:00.57
Command processing	152	00:00:01.10	00:00:04.42
Pass 1	831	00:00:32.24	00:00:43.49
Symbol table sort	0	00:00:04.69	00:00:05.06
Pass 2	376	00:00:06.40	00:00:08.42
Symbol table output	31	00:00:00.21	00:00:00.22
Psect synopsis output	4	00:00:00.03	00:00:00.03
Cross-reference output	0	00:00:00.00	00:00:00.00
Assembler run totals	1423	00:00:44.80	00:01:02.23

The working set limit was 2000 pages.
178619 bytes (349 pages) of virtual memory were used to buffer the intermediate code.
There were 180 pages of symbol table space allocated to hold 3209 non-local and 73 local symbols.
1502 source lines were read in Pass 1, producing 26 object records in Pass 2.
58 pages of virtual memory were used to define 53 macros.

! Macro library statistics !

Macro library name	Macros defined
_\$255\$DUA28:[SHRLIB]NMALIBRY.MLB;1	1
_\$255\$DUA28:[SHRLIB]EVCDEF.MLB;1	1
_\$255\$DUA28:[NETACP.OBJ]NETDRV.MLB;1	0
_\$255\$DUA28:[NETACP.OBJ]NET.MLB;1	13
_\$255\$DUA28:[SYS.OBJ]LIB.MLB;1	10
_\$255\$DUA28:[SYSLIB]STARLET.MLB;2	17
TOTALS (all libraries)	42

3530 GETS were required to define 42 macros.

There were no errors, warnings or information messages.

MACRO/LIS=LIS\$:NETDLE/OBJ=OBJ\$:NETDLE MSRC\$:NETDLE/UPDATE=(ENH\$:NETDLE)+EXECMLS/LIB+LIB\$:NET/LIB+LIB\$:NETDRV/LIB+SHRLIB\$:EVCDEF/LIB+

The image displays a grid of 100 small, illegible technical diagrams or code snippets, likely representing various system components or configurations. The grid is organized into 10 rows and 10 columns. Several diagrams are clearly labeled with text:

- NETCONFIG LIS (Row 3, Column 6)
- NETCONECT LIS (Row 4, Column 4)
- NETDLR LIS (Row 2, Column 8)
- NETCLALL LIS (Row 8, Column 6)

The diagrams themselves are too small and faded to read, but they appear to be technical drawings or code listings related to the VAX/VMS system.

0276 AH-BT13A-SE
VAX/VMS V4.0

DIGITAL EQUIPMENT CORPORATION
CONFIDENTIAL AND PROPRIETARY

