


```

SSSSSSSS MM MM GGGGGGGG MM MM SSSSSSSS GGGGGGGG TTTTTTTTTT XX XX TTTTTTTTTT
SSSSSSSS MM MM GGGGGGGG MM MM SSSSSSSS GGGGGGGG TTTTTTTTTT XX XX TTTTTTTTTT
SS M M M M GG M M SS GG T T XX XX T T
SS M M M M GG M M SS GG T T XX XX T T
SS M M M M GG M M SS GG T T XX XX T T
SSSSSS M M M M GG M M SSSSSS GG T T XX XX T T
SSSSSS M M M M GG M M SSSSSS GG T T XX XX T T
SS M M M M GG GGGGGG M M M M SS GG GGGGGG T T XX XX T T
SS M M M M GG GGGGGG M M M M SS GG GGGGGG T T XX XX T T
SS M M M M GG GG M M M M SS GG GG T T XX XX T T
SSSSSSSS M M M M GGGGGG M M M M SSSSSSSS GGGGGG T T XX XX T T
SSSSSSSS M M M M GGGGGG M M M M SSSSSSSS GGGGGG T T XX XX T T

```

```

LL LL I I I I I I SSSSSSSS
LL LL I I I I I I SSSSSSSS
LL LL I I I I I I SS
LL LL I I I I I I SS
LL LL I I I I I I SS
LL LL I I I I I I SSSSSS
LL LL I I I I I I SSSSSS
LL LL I I I I I I SS
LL LL I I I I I I SS
LL LL I I I I I I SS
LLLLLLLLLLLL I I I I I I SSSSSSSS
LLLLLLLLLLLL I I I I I I SSSSSSSS

```

```

1
2
3 .TITLE SMG$MSGDEF SMG$ facility messages
4 .IDENT '1-026' ! File: SMGMSG.MSG Edit: PLL1026
5 *****
6 *
7 * COPYRIGHT (c) 1978, 1980, 1982, 1984 BY *
8 * DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS. *
9 * ALL RIGHTS RESERVED. *
10 *
11 * THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED *
12 * ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE *
13 * INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER *
14 * COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY *
15 * OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY *
16 * TRANSFERRED. *
17 *
18 * THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE *
19 * AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT *
20 * CORPORATION. *
21 *
22 * DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS *
23 * SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL. *
24 *
25 *
26 *****
27
28
29 1-026 Add comments for my messages. PLL 23-Apr-1984
30 1-025 Add comments concerning user actions. STAN 9-Apr-1984.
31 1-024 Add TRMNOTANS. PLL 6-Apr-1984
32 1-023 Change wording for STRTERESC. STAN 22-Mar-1984.
33 1-022 Add INVDIR. PLL 15-Mar-1984
34 1-021 More messages for the termtable compiler. PLL 1-Mar-1984
35 1-020 Add back in NOMOREKEYS. LEB 22-Feb-1984
36 1-019 Add UNDTERTYP. PLL 9-Feb-1984
37 1-018 Added FAIOPEFIL. PLL 2-Feb-1984
38 1-017 Add INVEXP. PLL 19-Jan-1984
39 1-016 More messages for ft support. PLL 19-Jan-1984
40 1-015 Add SMG$ EXCTABSIZ and SMG$ MISTERNAM. PLL 8-Dec-1983
41 1-014 More messages for foreign terminal support. PLL 29-Nov-1983
42 1-013 Add messages for foreign terminal support. PLL 16-Nov-1983
43 1-012 Add warning message (no change in virtual display). PLL 11-Oct-1983
44 1-011 Add line drawing message (diagonal line not allowed). PLL 26-Sep-1983
45 1-010 More of same. STAN 25-Aug-1983.
46 1-009 Change pasteboard characteristics messages. STAN 22-Aug-1983.
47 1-008 File error messages. STAN 18-Jun-1983.
48 1-007 Mailbox messages. STAN 13-Jun-1983.
49 1-006 Add NOT A TRM. STAN 1-Jun-1983.
50 1-005 Add PASALREXI. RKR 25-May-1983.
51 1-004 Add STRTERESC. PLL 4-May-1983
52 1-003 Some messages having to do with batching. STAN 3-May-1983
53 1-002 Add messages for input. SBL 25-Mar-1983
54 1-001 Original. PLL 16-Mar-1983
55
56

```

57 :
58 : * Symbols are defined following the standard for global names:
59 :
60 : SMGS_abcmnoxyz
61 :
62 : In addition, the library standards specify that the letters 'abc', 'mno',
63 : and 'xyz' are the first three letters of the first three words of the error
64 : message, not counting articles and prepositions.
65 :
66 : The names of all procedures using each error condition value should appear
67 : in the comments included with each error definition.
68 :
69 :
70 : MACRO-32 Programming:
71 :
72 : The macros call:
73 :
74 : \$SMGDEF
75 :
76 : will cause all symbols to be made available to the module.
77 : The Run-time Library declares these symbols as EXTERNAL;
78 : the macros are provided only for the convenience of the user.
79 :
80 : -

```

81 |
82 | Template for documenting messages.
83 | Each explanation follows the message it applies to and
84 | is followed by a blank line.
85 | Be sure not to use the sequence "++" after a "!" in regular comments
86 | as this sequence begins a documentation sequence and can be
87 | searched for if and when the process of extracting the
88 | documentation becomes automated.
89 |
90 | ++
91 | FACILITY:      SMG
92 | EXPLANATION:  x
93 | USER ACTION:  y
94 | --
95 |
96 | !
00000012 | .FACILITY      : Set LH to 18 (decimal).
97 |               SMG,18 /SYSTEM
98 | .SEVERITY      SUCCESS
99 |
100 | .BASE          0
101 |
102 | 00128001 | NORMAL        <normal successful completion>
103 | ++
104 | FACILITY:      SMG
105 | EXPLANATION:  Normal successful completion.
106 | USER ACTION:  none
107 | --
108 |
109 | .BASE          2
110 |
10128011 | PREDEFREP     <previous key-definition replaced>
112 | ++
113 | FACILITY:      SMG
114 | EXPLANATION:  A previous key definition was replaced by a new
115 |               definition.
116 | USER ACTION:  none
117 | --
118 |
119 | +
120 | The next three messages are used by the "batching"
121 | procedures, SMG$BEGIN_DISPLAY_UPDATE and SMG$END_DISPLAY_UPDATE.
122 | The text of the messages should change if we decide not
123 | to publicly use the term "batching".
124 | -
125 |
10128019 | BATSTIPRO     <batching is still in progress>
127 | ++
128 | FACILITY:      SMG
129 | EXPLANATION:  A user tried to end batching (updating) with
130 |               a call to SMG$END_DISPLAY_UPDATE or
131 |               SMG$END_PASTEBOARD_UPDATE. This did not
132 |               terminate batching because there were more calls
133 |               made to begin batching than to end batching.
134 | USER ACTION:  None. Some outer level routine probably still
135 |               wants batching to be in effect.
136 | --

```

```

00128021 137
          138      BATWASOFF      <batching was off>
          139      ++
          140      FACILITY:      SMG
          141      EXPLANATION:  A program tried to turn off batching when
          142      batching was already off.
          143      USER ACTION:  Probably none. Check that there was one call
          144      to turn on batching for each call to turn it off.
          145      --
00128029 146
          147      BATWAS_ON      <batching was on>
          148      ++
          149      FACILITY:      SMG
          150      EXPLANATION:  A program tried to turn on batching when
          151      batching was already on. This is normal in
          152      a modular environment.
          153      USER ACTION:  None. Check that there was one call
          154      to turn on batching for each call to turn it off.
          155      --
00128031 156
          157      PASALREXI      <pasteboard already exists for this device>
          158      ++
          159      FACILITY:      SMG
          160      EXPLANATION:  A user tried to create a pasteboard for a device,
          161      when one was already created. This is normal in
          162      a modular environment. The existing pasteboard id
          163      is returned.
          164      USER ACTION:  None. Make sure you don't delete a pasteboard
          165      that you actually didn't create.
          166      --
00128039 167
          168      NOT_A_TRM      <pasteboard attached to a device that is not a terminal>
          169      ++
          170      FACILITY:      SMG
          171      EXPLANATION:  This is an informational message telling you that
          172      the pasteboard has been created, but the output
          173      device is not a terminal.
          174      USER ACTION:  None.
          175      --
00128041 176
          177      NO_MORMSG      <no more broadcast messages are available>
          178      ++
          179      FACILITY:      SMG
          180      EXPLANATION:  A call to SMG$GET_BROADCAST_MESSAGE found that
          181      there were no more messages to be obtained.
          182      USER ACTION:  None.
          183      --
00128049 184
          185      WILUSERMS      <output will be performed by RMS later>
          186      ++
          187      FACILITY:      SMG
          188      EXPLANATION:  Normally the screen is updated at the end of
          189      every output operation. If, however, the 'device'
          190      is actually a file or an unknown terminal, then
          191      this message is given at the time output would
          192      have been sent to the screen.
          193      USER ACTION:  none
  
```

```

194      |--
195
00128051 196      NOTRMSOUT      <RMS is not being used to perform output>
197      ++
198      FACILITY:      SMG
199      EXPLANATION:   SMG$SNAPSHOT is used with files and unknown devices
200                    to capture the contents of the pasteboard at various
201                    times.  If SMG$SNAPSHOT is called for a pasteboard
202                    associated with a video terminal, then it takes no
203                    action and returns this informational message.
204      USER ACTION:   none
205      |--
206
00128059 207      NO CHADIS      <no change in virtual display>
208      ++
209      FACILITY:      SMG
210      EXPLANATION:   The requested number of columns to change was zero,
211                    so nothing in the virtual display was changed.
212      USER ACTION:   none
213      |--
214
00128061 215      PRISECMAP     <private terminal table used>
216      ++
217      FACILITY:      SMG
218      EXPLANATION:   The requested terminal definition was found in
219                    the caller's private copy of Termtable.
220      USER ACTION:   none
221      |--
222
00128069 223      GBLSECMAP     <system terminal table used>
224      ++
225      FACILITY:      SMG
226      EXPLANATION:   The requested terminal definition was found in
227                    the system Termtable. (Requested terminal definition
228                    did not exist in the caller's private Termtable.)
229      USER ACTION:   none
230      |--
231
232
233      .SEVERITY      FATAL
234      .BASE          64
235
00128204 236      FATERRLIB     <fatal error in library>
237      ++
238      FACILITY:      SMG
239      EXPLANATION:   An internal error has occurred within SMG.
240      USER ACTION:   Submit an SPR describing the problem.
241      |--
242
0012820C 243      INVARG        <invalid argument>
244      ++
245      FACILITY:      SMG
246      EXPLANATION:   The value of some argument is not in the correct range.
247      USER ACTION:   Examine each argument. Determine which one is
248                    out of range and correct your program.
249      |--
250

```

00128214	251	INVCOL	<invalid column>
	252	++	
	253	FACILITY:	SMG
	254	EXPLANATION:	An invalid column number was specified. It was either
	255		less than 0 or larger than the number of columns
	256		in the virtual display.
	257	USER ACTION:	Specify a valid column number. Columns are numbered
	258		beginning with 1.
	259	--	
0012821C	260	INVDIS_ID	<invalid display-id>
	261	++	
	262	FACILITY:	SMG
	263	EXPLANATION:	An invalid display-id was specified.
	264	USER ACTION:	Check that you are passing the display id by reference
	265		not by value. Ensure that the display id was
	266		previously set up by a call to SMG\$CREATE_VIRTUAL_DISPLAY.
	267	--	
	268		
00128224	269	INVPA_ID	<invalid pasteboard-id>
	270	++	
	271	FACILITY:	SMG
	272	EXPLANATION:	An invalid pasteboard id was specified.
	273	USER ACTION:	Check that you are passing the pasteboard id by reference
	274		not by value. (A reference to a 0 is valid, since 0
	275		is a legal pasteboard id.) Ensure that the pasteboard
	276		was previously set up by a call to
	277		SMG\$CREATE_PASTEBOARD and that the pasteboard has not
	278		been deleted.
	279	--	
	280		
0012822C	281	INVROW	<invalid row>
	282	++	
	283	FACILITY:	SMG
	284	EXPLANATION:	An invalid row number was specified. It was either
	285		less than 0 or larger than the number of rows
	286		in the virtual display.
	287	USER ACTION:	Specify a valid row number. Rows are numbered
	288		beginning with 1.
	289	--	
	290		
00128234	291	TOOMANDIS	<too many displays>
	292	++	
	293	FACILITY:	SMG
	294	EXPLANATION:	An internal limit on the number of virtual displays
	295		that your program may have has been exceeded.
	296		The limit is currently 255. This includes any
	297		virtual displays that some outer routine may be using.
	298		This includes displays on all pasteboards.
	299	USER ACTION:	Use fewer virtual displays.
	300		Make sure that your program is not in a loop
	301		creating virtual displays. Be sure that you delete
	302		a virtual display when you are all done with it.
	303	--	
	304		
0012823C	305	TOOMANPAS	<too many pasteboards>
	306	++	
	307		

```

308 | FACILITY: SMG
309 | EXPLANATION: An internal limit on the number of pasteboards
310 |               that your program may have has been exceeded.
311 |               The limit is currently 16.
312 | USER ACTION: Use fewer pasteboards.
313 | --
00128244 | 314
315 | WRONUMARG <wrong number of arguments>
316 | ++
317 | FACILITY: SMG
318 | EXPLANATION: An SMG routine was called with too few arguments
319 |               (less than the number of required arguments)
320 |               or too many arguments.
321 | USER ACTION: Correct the code to call the routine with
322 |               the proper number of arguments.
323 | --
0012824C | 324
325 | INVKBD_ID <invalid keyboard-id>
326 | ++
327 | FACILITY: SMG
328 | EXPLANATION: An invalid keyboard id was passed.
329 | USER ACTION: Check that you are passing the keyboard id by reference
330 |               not by value. Ensure that the keyboard id was
331 |               previously set up by a call to
332 |               SMG$CREATE_VIRTUAL_KEYBOARD.
333 | --
00128254 | 334
335 | INVKTB_ID <invalid key-table-id>
336 | ++
337 | FACILITY: SMG
338 | EXPLANATION: An invalid key table id was passed.
339 | USER ACTION: Check that you are passing the key table id by reference
340 |               not by value. Ensure that the key table id was
341 |               previously set up by a call to
342 |               SMG$CREATE_KEY_TABLE.
343 | --
0012825C | 344
345 | INVMAXLEN <invalid maximum length (greater than 512)>
346 | ++
347 | FACILITY: SMG
348 | EXPLANATION: The maximum length specified for an input string
349 |               was too long.
350 | USER ACTION: Correct your program so that it requests an input
351 |               string of 512 characters or less.
352 | --
00128264 | 353
354 | FILTOOLON <file-specification is too long (over 255 characters)>
355 | ++
356 | **** This message should be removed from here and from
357 | **** SMGKEYPAD.B32. It's referenced as an external but
358 | **** it's never used in the code. Be careful to make both
359 | **** edits at the same time (to avoid build problems).
360 | --
0012826C | 361
362 | PROTOOLON <prompt-string is too long>
363 | ++
364 | FACILITY: SMG

```

```

365      | EXPLANATION: The length of a prompt string exceeded 512 characters.
366      | USER ACTION: Shorten the prompt to 512 characters or less.
367      | --
00128274 368
369      | NOTPASTED <given display is not pasted to given pasteboard>
370      | ++
371      | FACILITY: SMG
372      | EXPLANATION: An attempt was made to unpaste or move a display
373      | that was not pasted to the specified pasteboard.
374      | USER ACTION: Check that you are referencing the correct virtual
375      | display. Verify that the display has not been
376      | unpasted or that you forgot to paste it.
377      | --
0012827C 378
379      | PBDIN_USE <operation invalid while pasteboard is buffered>
380      | ++
381      | FACILITY: SMG
382      | EXPLANATION: The operation you have tried to perform is not
383      | legal while output to the pasteboard is being batched.
384      | For example, you can't change the pasteboard
385      | characteristics while the pasteboard is batched.
386      | USER ACTION: Turn off pasteboard batching before attempting the
387      | operation. You may turn batching on again after the
388      | operation.
389      | --
00128284 390
391      | INVWIDARG <width of 0 is not permitted>
392      | ++
393      | FACILITY: SMG
394      | EXPLANATION: An attempt was made to change the characteristics
395      | of the terminal, setting it's width to 0.
396      | USER ACTION: Correct the code. A width of 0 is illegal.
397      | --
0012828C 398
399      | INVPAARG <height of 0 is not permitted>
400      | ++
401      | FACILITY: SMG
402      | EXPLANATION: An attempt was made to change the characteristics
403      | of the terminal, setting it's height (page size) to 0.
404      | USER ACTION: Correct the code. A height of 0 is illegal.
405      | --
00128294 406
407      | INVCOLARG <unknown color specified>
408      | ++
409      | FACILITY: SMG
410      | EXPLANATION: An attempt was made to change the characteristics
411      | of the terminal, changing its background color
412      | to a value that was not legal.
413      | USER ACTION: Check the symbolic name for the background color
414      | desired. Specify it correctly.
415      | --
0012829C 416
417      | DIALINNOT <diagonal line not allowed>
418      | ++
419      | FACILITY: SMG
420      | EXPLANATION: The vertices specified will result in a diagonal line,
421      | rather than a vertical or horizontal line.

```

```

422      | USER ACTION: Re-specify the vertices so that the line drawn will be
423      | vertical or horizontal.
424      | --
001282A4 425      |
426      | TABID_MIS      <terminal table id mismatch>
427      | ++
428      | FACILITY:      SMG
429      | EXPLANATION:   The Termtable internal consistency check failed. The
430      |              routines which fetch information from Termtable have
431      |              a different version number than the Termtable data.
432      | USER ACTION: Probably the routines which fetch the data are newer
433      |              than your Termtable.exe. Re-compile Termtable.txt to
434      |              update your Termtable.exe.
435      | --
001282AC 436      |
437      | UNDTERNAM     <undefined terminal name>
438      | ++
439      | FACILITY:      SMG
440      | EXPLANATION:   The requested terminal definition was not found in
441      |              the caller's private copy of Termtable or the system
442      |              copy of Termtable.
443      | USER ACTION: If you intended to use a private terminal definition,
444      |              make sure that Termtable.exe exists in your private
445      |              directory and that the logical name TERMSTABLOC points
446      |              to it. If you expected your terminal to be defined in
447      |              the system Termtable, check with your system manager.
448      | --
001282B4 449      |
450      | INVERTAB     <invalid terminal table>
451      | ++
452      | FACILITY:      SMG
453      | EXPLANATION:   An invalid terminal table address was specified.
454      | USER ACTION: Check that you are passing the terminal table argument
455      |              by reference and not by value. Make sure the terminal
456      |              table address was acquired by calling
457      |              SMGSINIT_TERM_TABLE.
458      | --
001282BC 459      |
460      | INVREQCOD    <invalid request code>
461      | ++
462      | FACILITY:      SMG
463      | EXPLANATION:   Data is requested from Termtable via request codes
464      |              which are available as symbolic names. The code you
465      |              have specified is invalid.
466      | USER ACTION: Check the spelling of the symbolic name you are using.
467      | --
001282C4 468      |
469      | NOTBOOCAP    <not a boolean capability>
470      | ++
471      | FACILITY:      SMG (termtable compiler)
472      | EXPLANATION:   The Termtable compiler expected a boolean capability
473      |              name but encountered something else.
474      | USER ACTION: Check your terminal definition. Perhaps you have
475      |              misspelled the boolean capability name or omitted
476      |              another statement such as STRING or NUMERIC which
477      |              would have terminated boolean capabilities.
478      | --

```

```

001282CC 479
          480 SYNERR <syntax error>
          481 ++
          482 FACILITY: SMG (termtable compiler)
          483 EXPLANATION: The Termtable compiler encountered an invalid
          484 syntax. For instance, there may be a misplaced or
          485 missing equals sign.
          486 USER ACTION: Check your terminal definition.
          487 --
001282D4 488
          489 UNDTERTYP <undefined terminal type>
          490 ++
          491 FACILITY: SMG
          492 EXPLANATION: The definition for the requested terminal type was
          493 not found in the caller's private copy of Termtable
          494 or the system Termtable.
          495 USER ACTION: If you intended to use a private definition, make
          496 sure that Termtable.exe exists in your private directory
          497 and that the logical name TERMSTABLOC points to it.
          498 If you expected your terminal definition to exist in
          499 the system Termtable, consult your system manager.
          500 --
001282DC 501
          502 MISTERNAM <definition must begin with a terminal name>
          503 ++
          504 FACILITY: SMG (termtable compiler)
          505 EXPLANATION: Capabilities were not preceeded by the name of a
          506 terminal.
          507 USER ACTION: Check your terminal definitions. Make sure that
          508 each definition starts with NAME = <terminal_name>.
          509 --
001282E4 510
          511 INVCTRL <unrecognized control code>
          512 ++
          513 **** This should not be documented because I think it will go
          514 **** away when the official V4 is released.
          515 --
001282EC 516
          517 ILLVAL <Boolean value must be 0 or 1>
          518 ++
          519 FACILITY: SMG (termtable compiler)
          520 EXPLANATION: A boolean capability was given a value other than
          521 0 or 1.
          522 USER ACTION: Check your terminal definitions. Boolean capabilities
          523 must be 0 or 1 (off or on, respectively).
          524 --
001282F4 525
          526 INVEXP <invalid expression>
          527 ++
          528 FACILITY: SMG (termtable compiler)
          529 EXPLANATION: The Termtable compiler encountered an invalid
          530 arithmetic expression.
          531 USER ACTION: Check your definition. Make sure that you have
          532 used only valid operators and operands in your
          533 expressions.
          534 --
          535

```

```

001282FC 536 ERRAT_LIN <Error in line !UL at or near '!AF'> /FAO=3
          537 ++
          538 FACILITY: SMG (termtable compiler)
          539 EXPLANATION: General information message included with many
          540 Termtable compiler messages. Attempts to identify
          541 specifically where an error occurred.
          542 USER ACTION: Check the specified line in your definition.
          543 --
          544
00128304 545 ERRLIN <Error in line !UL> /FAO=1
          546 ++
          547 FACILITY: SMG (termtable compiler)
          548 EXPLANATION: General information message included with many
          549 Termtable compiler messages. Attempts to identify
          550 specifically which line contained an error.
          551 USER ACTION: Check the specified line in your definition.
          552 --
          553
0012830C 554 UNTERNOP <undefined terminal - couldn't access private terminal table>
          555 ++
          556 FACILITY: SMG
          557 EXPLANATION: The requested terminal definition was not found in the
          558 caller's private copy of Termtable or the system
          559 Termtable. The caller's private Termtable couldn't be
          560 be accessed, either because it didn't exist or because
          561 RMS could not open the file.
          562 USER ACTION: If you intended to use a definition from your private
          563 Termtable, make sure that Termtable.exe exists in your
          564 private directory and that the logical name TERM$TABLOC
          565 points to it. Make sure that you have read access to
          566 the file.
          567 --
          568
00128314 569 UNTERNOS <undefined terminal - couldn't access system terminal table>
          570 ++
          571 FACILITY: SMG
          572 EXPLANATION: The requested terminal definition was not found in
          573 the caller's private Termtable or the system Termtable.
          574 The system Termtable was unavailable.
          575 USER ACTION: The system Termtable should be mapped as a global
          576 section and therefore should always be available.
          577 Consult your system manager regarding this.
          578 --
          579
0012831C 580 MISFILSPE <missing file specification in REQUIRE statement>
          581 ++
          582 FACILITY: SMG (termtable compiler)
          583 EXPLANATION: The REQUIRE statement needs a file name in order to
          584 locate external definitions which should become part
          585 of your Termtable.
          586 USER ACTION: Check your Termtable.txt. Add a file name to the
          587 REQUIRE statement.
          588 --
          589
00128324 590 UNRECSTA <unrecognized statement>
          591 ++
          592 FACILITY: SMG (termtable compiler)
  
```

	593	:	EXPLANATION:	The Termtable compiler encountered a statement that
	594	:		it does not recognize.
	595	:	USER ACTION:	Check your definition. Make sure you have spelled
	596	:		keywords correctly and that statements appear only
	597	:		in valid sequences.
	598	:	--	
0012832C	599	:		
	600	:	FAIOPEFIL	<failed to open file !AF> /FA0=2
	601	:	++	
	602	:	FACILITY:	SMG (termtable compiler)
	603	:	EXPLANATION:	The Termtable compiler could not open the file
	604	:		specified in a REQUIRE.
	605	:	USER ACTION:	Make sure that the specified file exists and that
	606	:		you have read access to it.
	607	:	--	
	608	:		
00128334	609	:	NO_ARGS	<missing arguments for substitution>
	610	:	++	
	611	:	FACILITY:	SMG
	612	:	EXPLANATION:	You requested a capability that requires user
	613	:		arguments (such as a row and column number) but
	614	:		did not provide any.
	615	:	USER ACTION:	Check the number of arguments required by this
	616	:		capability and correct your call to SMG\$GET_TERM_DATA.
	617	:	--	
	618	:		
0012833C	619	:	NOTNUMCAP	<not a numeric capability>
	620	:	++	
	621	:	FACILITY:	SMG (termtable compiler)
	622	:	EXPLANATION:	The Termtable compiler expected a numeric capability
	623	:		name but encountered something else.
	624	:	USER ACTION:	Check your terminal definition. Perhaps you have
	625	:		misspelled the numeric capability name or omitted
	626	:		another statement such as STRING or BOOLEAN which
	627	:		would have terminated numeric capabilities.
	628	:	--	
	629	:		
00128344	630	:	NOTSTRCAP	<not a string capability>
	631	:	++	
	632	:	FACILITY:	SMG (termtable compiler)
	633	:	EXPLANATION:	The Termtable compiler expected a string capability
	634	:		name but encountered something else.
	635	:	USER ACTION:	Check your terminal definition. Perhaps you have
	636	:		misspelled the string capability name or omitted
	637	:		another statement such as BOOLEAN or NUMERIC which
	638	:		would have terminated string capabilities.
	639	:	--	
	640	:		
0012834C	641	:	MISENDSTA	<missing END statement>
	642	:	++	
	643	:	FACILITY:	SMG (termtable compiler)
	644	:	EXPLANATION:	The Termtable compiler expected an END statement
	645	:		to terminate the current terminal definition and
	646	:		this END statement was missing.
	647	:	USER ACTION:	Check your terminal definitions.
	648	:	--	
	649	:		

```

00128354 650 MISNAMREQ <expected NAME or REQUIRE>
          651 ++
          652 FACILITY: SMG (termtable compiler)
          653 EXPLANATION: The Termtable compiler expected Termtable.txt to
          654 begin with a terminal definition (NAME statement)
          655 or a REQUIRE. Something else was encountered.
          656 USER ACTION: Check your Termtable.txt.
          657 --
0012835C 658
          659 ILLBATFNC <operation not permitted while display is batched>
          660 ++
          661 FACILITY: SMG
          662 EXPLANATION: An attempt was made to perform an operation that
          663 is not permitted while a virtual display is being
          664 batched (for example, performing input or MOVING
          665 the virtual display).
          666 USER ACTION: Terminate batching first by calling
          667 SMG$END_DISPLAY_UPDATE.
          668 --
00128364 669
          670 INVDIR <invalid directive>
          671 ++
          672 FACILITY: SMG (termtable compiler)
          673 EXPLANATION: The Termtable compiler accepts only a few FAO
          674 directives. It encountered one that it does not
          675 handle.
          676 USER ACTION: Check your terminal definition. Make sure that
          677 you use only valid FAO directives.
          678 --
0012836C 679
          680 TRMNOTANS <terminal is not ANSI compatible>
          681 ++
          682 FACILITY: SMG
          683 EXPLANATION: A call to SMG$GET_PHYSICAL_CURSOR was made
          684 specifying that the terminal is to be queried
          685 to determine where the cursor is.
          686 This could not be done because the terminal
          687 was not ANSI, and this feature is available
          688 only on ANSI terminals.
          689 USER ACTION: Rerun your application on an ANSI terminal,
          690 such as a VT100.
          691 --
          692 .SEVERITY ERROR
          693 .BASE 128
00128402 694
          695 EOF <end-of-file>
          696 ++
          697 FACILITY: SMG
          698 EXPLANATION: End of file condition was detected on input.
          699 USER ACTION: If necessary, modify your program to recognize this
          700 condition and respond to it.
          701 --
          702
0012840A 703
          704 KEYDEFPRO <key definition is protected - cannot be changed or deleted>
          705 ++
          706 FACILITY: SMG
  
```

```

707      | EXPLANATION: The specified key is already defined, and since its
708      |             definition is protected, it can not be changed or
709      |             re-defined.
710      | USER ACTION: none
711      | --
00128412 712
713      | INVDEFATT      <invalid key-definition attributes>
714      | ++
715      | FACILITY:      SMG
716      | EXPLANATION:  When a key is defined, attributes such as NOECHO may be
717      |             specified with the definition. An attempt was made to
718      |             specify an unknown attribute.
719      | USER ACTION:  Check the list of valid attributes and correct your
720      |             program.
721      | --
0012841A 722
723      | INVKEYNAM      <invalid key name>
724      | ++
725      | FACILITY:      SMG
726      | EXPLANATION:  The specified key name was less than 1 character or
727      |             more than 31 characters.
728      | USER ACTION:  Choose a key name with 1 to 31 characters.
729      | --
00128422 730
731      | INVSTANAM      <invalid state name>
732      | ++
733      | FACILITY:      SMG
734      | EXPLANATION:  The specified state name was less than 1 character or
735      |             more than 31 characters.
736      | USER ACTION:  Choose a state name with 1 to 31 characters.
737      | --
738
739      | .SEVERITY      WARNING
740      | .BASE          512
00129000 741
742      | KEYNOTDEF      <key is not defined>
743      | ++
744      | FACILITY:      SMG
745      | EXPLANATION:  An attempt was made to perform an operation, such as
746      |             SMG$GET_KEY_DEF, on a key which was not defined.
747      | USER ACTION:  Check your program to see if this key should have
748      |             been defined.
749      | --
00129008 750
751      | NOMOREKEYS     <no more keys defined>
752      | ++
753      | FACILITY:      SMG
754      | EXPLANATION:  SMG$LIST_KEY_DEFS, when called repeatedly, returns all
755      |             the key definitions in a key table. When there are no
756      |             more definitions, this error is returned.
757      | USER ACTION:  Modify your program to expect this condition, if necessary.
758      | --
00129010 759
760      | STRTERESC      <illegal escape sequence embedded in string>
761      | ++
762      | FACILITY:      SMG
763      | EXPLANATION:  An SMG output routine was passed an escape sequence

```

```

764
765
766
767
768
769
770
771
772
00129018 773
774
775
776
777
778
779
780
781
782
783
00129020 784
785
786
787
788
789
790
791
792
793
794
795
796 !

```

embedded in the output string. The output string was written to the virtual display but the string was terminated at the escape sequence.
 USER ACTION: Check your output string to determine what escape sequence was being passed. If you need the action provided by this escape sequence, there is most likely a SMG routine that provides that functionality.
 --
 GBLNOTCRE <global section not created>
 ++
 FACILITY: SMG
 EXPLANATION: The system program that maps Termtree.exe as a global section was unsuccessful.
 USER ACTION: This message should be handled only by system managers. If there is already an existing global section for Termtree, the system must be rebooted in order to create a new global section.
 --
 ! the following is used with GBLNOTCRE
 <Termtree section already exists>
 ++
 FACILITY: SMG
 EXPLANATION: The system program which maps Termtree as a global section was unsuccessful. Before a new global section can be created, the previous one must be deleted.
 USER ACTION: The system must be rebooted in order to map a new Termtree.exe as the global section.
 --
 .END
 End of file SMGMSG.MSG

There were 0 errors, 0 warnings, and 0 informational messages issued.
MESSAGE/NOSYMBOLS/LIS=LISS:SMGMSGTXT/OBJ=OBJ\$:SMGMSGTXT MSRC\$:SMGMSG

