PRINTED IN U.S.A.
Remington Rand Univac
DIVISION OF SPERRY RAND CORPORATION
PHILADELPHIA, PA.

```
0000                    FLO                          1.  FORTRAN II COMPILER  PASS 1
0001                                                     D. E. KNUTH
0002
0003                                                     TO BEGIN READING THIS LISTING, LOOK FIRST
0004                                                     AT THE CONSTANTS AT THE END AND FAMILIARIZE
0005                                                     YOURSELF WITH THEIR NAMES AND VALUES
0020
0041                    TYP                  0000009000
0042          STORE     EQU     4195
0043          UNIQU     BLR     4196
0044          COMON     BLR     4198
0045          WDDO      BLR     4100
0046          SIGN%     BLR     4101
0047          UN-       BLR     4102
0048          BIN-      BLR     4103
0049          SIGN-     BLR     4104
0050          SIGN&     BLR     4105
0051          BIN&      BLR     4106
0052          WDIF      BLR     4107
0053          IF%       BLR     4108
0054          TARA*     BLR     4109
0055          TARA%     BLR     4110
0056          SIGN*     BLR     4111
0057          BIN*      BLR     4112
0058          SIGN,     BLR     4113
0059          SIGN$     BLR     4114
0060          SIGN/     BLR     4115
0061          BIN**     BLR     4116
0062          SIGN#     BLR     4117
0063          BIN!#     BLR     4118
0064          SQRTF     BLR     4119
0065          SINF      BLR     4120
0066          COSF      BLR     4121
0067          TANF      BLR     4122
0068          ATANF     BLR     4123
0069          LNF       BLR     4124
0070          EXPF      BLR     4125
0071          ABSF      BLR     4126
0072          OPC       BLR     4127
0073          GO%       BLR     4128
0074          LABL      BLR     4129
0075          ASSI      BLR     4130
0076          WDGO      BLR     4131
0077          WDNO      BLR     4132
0078          WDLIS     BLR     4133
0079          WDFOR     BLR     2200
0080          SIGN'     BLR     4135
0081          WDTRC     BLR     4136
0082          WDCOR     BLR     4137
```

IN CONSIDERATION OF THE RECEIPT OF THIS DOCUMENT, THE RECIPIENT AGREES NOT TO REPRODUCE, COPY, USE OR TRANSMIT THIS DOCUMENT AND/OR THE INFORMATION THEREIN CONTAINED IN WHOLE OR IN PART, OR TO SUFFER SUCH ACTION BY OTHERS, FOR ANY PURPOSE, EXCEPT WITH THE WRITTEN PERMISSION OF SPERRY RAND CORPORATION, AND FURTHER AGREES TO SURRENDER SAME TO SPERRY RAND CORPORATION, UPON DEMAND

```
0083                    WDTRU    BLR   4136
0084                    DIM%     BLR   4139
0085                    NORMX    BLR   4140
0086                    WDPOZ    BLR   4141
0087                    WDSTP    BLR   4142
0088                    WDEND    BLR   4143
0089                    WDFUN    BLR   4144
0090                    WDSUB    BLR   4145
0091                    WDRED    BLR   4146
0092                    WDPRT    BLR   4147
0093                    WDFMT    BLR   4149
0094                    WDRTN    BLR   4150
0095                    WDDIM    BLR   4151
0096                    WDCOM    BLR   4152
0097                    WDEQU    BLR   4153
0098                    FLOTF    BLR   4154
0099                    FIXF     BLR   4155
0100                    EQU%     BLR   4156
0101                    DONT1    BLR   4157
0102                    FC%      BLR   4158
0103                    WDPCH    BLR   4159
0104                    WDCAL    BLR   4160
0105                    BCOMP    BLR   4161
0106                    BLAND    BLR   4162
0107                    BOR      BLR   4163
0108                    DO$1     BLR   4164
0109                    I02.1    BLR   4165
0110                    WDPRG    BLR   4166
0111  A0000             BLR      1100   1119    TYPE SWITCHING FOR BINARY OPERATORS
0112  B0000             BLR      4000   4008    ARITH ROUTINE
0113  C0000             BLR      4010   4015    ASIGN ROUTINE
0114                    BLR      C0009  C0012
0115  E0000             BLR      4050   4074    CONTROL IN SCANNER
0116  F0000             BLR      4024   4029    CONTROL IN FUNCTION CALL
0117                    BLA      F0004
0118  H0000             EQU      0000            HSR BAND
0119                    OFF      9000
0132                    ON       9000
0133                    ON       9001
0134                    ON       9002
0135                    BLR      H0001  H0096 005
0136                    BLR      H0102  H0197 005
0137  HWD1              EQU      H0011
0138  HDW2              EQU      0000
0139  HDW3              EQU      0021
0140                    ON       8001
0141                    ON       8002
0142  I0000             BLR      1300   1399    ASM1 OP TABLES
0143                    BLA      I0025  I0073
0144  J0000             BLR      1700   1739    MACRO TABLES
```

```
0145                    BLA   J0005
0146          K0000     EQU    0200                          PRINTER BAND - CARD IMAGES
0147                    BLR   K0000      K0005 005
0148                    BLR   K0081      K0086 005
0149                    BLR   K0165      K0170 005
0150                    BLR   K0050      K0055 005
0151                    BLR   K0134      K0139 005
0152                    BLR   K0018      K0023 005
0153                    BLR   K0103      K0108 005
0154                    BLR   K0041      K0046 005
0155                    BLR   K0125      K0130 005
0156                    BLR   K0009      K0014 005
0157                    BLR   K0094      K0099 005
0158                    BLR   K0178      K0183 005
0159                    BLR   K0062      K0067 005
0160          L0000     BLR    1280       1282              PROCESSING OF LABELS
0161                    BLR   L0004      L0006
0162          N0001     BLR    4031       4039              INPUT ROUTINE
0163          00001     BLR    1550       1599              HEADER CARD INFORMATION
0164          P0000     EQU    0400                          PRINTER BAND - COMPILED INSTRUCTIONS
0165                    BLR   P0000      P0005 005
0166                    BLR   P0081      P0086 005
0167                    BLR   P0165      P0170 005
0168                    BLR   P0050      P0055 005
0169                    BLR   P0134      P0139 005
0170                    BLR   P0018      P0023 005
0171                    BLR   P0103      P0108 005
0172                    BLR   P0041      P0046 005
0173                    BLR   P0125      P0130 005
0174                    BLR   P0009      P0017 005
0175                    BLR   P0094      P0099 005
0176                    BLR   P0178      P0183 005
0177                    BLR   P0062      P0067 005
0178          Q0000     BLR    1000       1045              SUBROUTINE ENTRANCES TABLE
0179          R0000     EQU    0800                          RPU BAND - OBJECT DECK
0180                    OFF    9000
0193                    ON     9000
0194                    ON     9001
0195                    ON     9002
0196                    BLR   R0101      R0196 005
0197                    BLR   R0002      R0097 005
0198                    BLR   R0103      R0198 005
0199          RWD1      EQU   R0108
0200                    ON     8001
0201                    ON     8002
0202          S0000     BLR    4040       4049              SEND ROUTINE
0203                    BLA   S0001      S0002
0204                    BLA   S0004
0205          T0000     BLR    1050       1096              CONSTANTS FOR DIVRT
0206                    BLA   T0006
```

```
0207                                                V0000    BLR   4080      4085          ASM2 ROUTINE
0208                                                         BLA   V0004
0209                                                W0000    BLR   1750      1754          NAMES OF LIBRARY PACKAGES
0210                                                X0000    BLR   1150      1173          PROCESSING OF FORMAT STRINGS
0211                                                Z0000    BLR   1420      1519          SCRAMBLE TABLE FOR SRCH ROUTINE
0212                                                50001    BLR   4181      4186          CONTROL IN PUNCH ROUTINE ASM5
0213                                                90000    BLR   2201      2211
0214                                                         BLR   0000      0001
0215  0000  888 0 30  4140  0042                     0000    LDL   NORMX     8ME
0216  0001  888 0 HH  HHHH  HHHH                     0001    CON   HHHHHH    HHHHHH        USED IN TESTING END OF DO LOOP
0217                                                         BLR   0100      0110 010
0218  0110  888 0 00  0100  0100                     0110    JMP   0100                    IN CASE MACHINE HAS HSR INTERRUPT
0219                                                RAND     BLR   1190      1229          OPERAND STACK
0220                                                         BLR   1185      1189          PROTECTION ON BOTTOM OF OPERAND STACK
0221  1185  888 0 02  4098  5000                     1185    CON   02409     85000         CONSTANT ZERO
0222  1186  888 0 02  4098  5000                     1186    CON   02409     85000         CONSTANT ZERO
0223  1187  888 0 02  4098  5000                     1187    CON   02409     85000         CONSTANT ZERO
0224  1188  888 0 02  4098  5000                     1188    CON   02409     85000         CONSTANT ZERO
0225  1189  888 0 02  4098  5000                     1189    CON   02409     85000         CONSTANT ZERO
0226  1190  888 0 02  4098  5000                     RAND     CON   02409     85000
0227                                                MODE     BLR   1520      1549          MODE STACK
0228                                                DUMMY    BLR   4088      4099
0229  4088  888 0 00  0000  0000                     4088    CON   00000     00000         DUMMY DO VARIABLE IN I-O LIST
0230  4089  888 0 02  1208  8988                     4089    ALF   *I*
0231  4090  888 0 69  4135  0000                     4090    CON   69413     50000
0232  4091  888 0 00  0000  000H                     4091    CON   00000     0000H         APOSTROPHE
0233  4092  888 0 00  0000  0000                     4092    CON   00000     00000
0234                                                OOPO     EQU   4093                    SPECIAL LPREN WHICH INDICATES EXTRA RPREN
0235  4098  888 0 05  0000  0000                     4098    CON   05000     00000
0236  4099  888 0 00  0000  0000                     4099    CON   00000     00000         CONSTANT ZERO
0237  4096  888 0 05  0000  0000                     4096    CON   05000     00000
0238                                                KON1     EQU   4097                    CONSTANT 1
0239  4094  888 0 05  0000  0000                     4094    CON   05000     00000
0240                                                KON2     EQU   4095                    CONSTANT 2
0241                                                SCAN1    EQU   E0000
0242                                                $        EQU   T0014
0243                                                .        EQU   T0024
0244                                                OBIN&    EQU   T0002
0245                                                CONO     EQU   T0001
0248
0476                                                         OFF   9000
0570                                                         ON    9000
0571                                                80000    BLR   4800      4879          TRANSLATE TABLE - 90CARD TO MC-6
0572                                                         BLA   80004     80079 005
0573  4800  888 0 00  0000  0008                     80000    CON   00000     00008         0-0
0574  4801  888 0 00  0000  0000                     80001    CON   00000     00000         0-1
0575  4802  888 0 00  0000  0001                     80002    CON   00000     00001         0-2
0576  4803  888 0 00  0020  0008                     80003    CON   00002     00008         0-3
0577  4805  888 0 00  0000  0005                     80005    CON   00000     00005         0-5
0578  4806  888 0 00  0020  0004                     80006    CON   00002     00004         0-6
```

```
0579   4807   BBB 0 00   0010   0002   80007   CON   00001   00002   0-7
0580   4808   BBB 0 00   0030   0008   80008   CON   00003   00008   0-8
0581   4810   BBB 0 00   0000   0007   80010   CON   00000   00007   1-0
0582   4811   BBB 0 00   0010   0003   80011   CON   00001   00003   1-1
0583   4812   BBB 0 00   0020   0009   80012   CON   00002   00009   1-2
0584                                             BLA   80013
0585   4815   BBB 0 00   0010   0007   80015   CON   00001   00007   1-5
0586   4816   BBB 0 00   0030   0004   80016   CON   00003   00004   1-6
0587   4817   BBB 0 00   0030   0002   80017   CON   00003   00002   1-7
0588   4818   BBB 0 00   0010   000H   80018   CON   00001   0000H   1-8
0589   4820   BBB 0 00   0000   0009   80020   CON   00000   00009   2-0
0590   4821   BBB 0 00   0020   0003   80021   CON   00002   00003   2-1
0591   4822   BBB 0 00   0000   0002   80022   CON   00000   00002   2-2
0592                                             BLA   80023
0593   4825   BBB 0 00   0000   0006   80025   CON   00000   00006   2-5
0594   4826   BBB 0 00   0020   0005   80026   CON   00002   00005   2-6
0595   4827   BBB 0 00   0010   0001   80027   CON   00001   00001   2-7
0596                                             BLA   80028
0597   4830   BBB 0 00   0000   0008   80030   CON   00000   00008   3-0
0598   4831   BBB 0 00   0030   0007   80031   CON   00003   00007   3-1
0599   4832   BBB 0 00   0010   0006   80032   CON   00001   00006   3-2
0600                                             BLA   80033
0601   4835   BBB 0 00   0030   0009   80035   CON   00003   00009   3-5
0602   4836   BBB 0 00   0000   000F   80036   CON   00000   0000F   3-6
0603   4837   BBB 0 00   0030   0000   80037   CON   00003   00000   3-7
0604                                             BLA   80038
0605   4840   BBB 0 00   0000   0003   80040   CON   00000   00003   0-4
0606   4841   BBB 0 00   0010   0005   80041   CON   00001   00005   0-A
0607   4842   BBB 0 00   0020   0006   80042   CON   00002   00006   0-B
0608                                             BLA   80043
0609   4845   BBB 0 00   0010   0009   80045   CON   00001   00009   0-9
0610   4846   BBB 0 00   0010   0004   80046   CON   00001   00004   0-F
0611   4847   BBB 0 00   0020   0001   80047   CON   00002   00001   0-G
0612                                             BLA   80048
0613   4850   BBB 0 00   0010   0008   80050   CON   00001   00008   1-4
0614   4851   BBB 0 00   0030   0006   80051   CON   00003   00006   1-A
0615   4852   BBB 0 00   0020   0007   80052   CON   00002   00007   1-B
0616                                             BLA   80053
0617   4855   BBB 0 00   0020   0008   80055   CON   00002   00008   1-9
0618   4856   BBB 0 00   0000   000A   80056   CON   00000   0000A   1-F
0619   4857   BBB 0 00   0000   000C   80057   CON   00000   0000C   1-G
0620   4858   BBB 0 00   0010   000C   80058   CON   00001   0000C   1-H
0621   4860   BBB 0 00   0000   0004   80060   CON   00000   00004   2-4
0622   4861   BBB 0 00   0030   0005   80061   CON   00003   00005   2-A
0623   4862   BBB 0 00   0030   0008   80062   CON   00003   00008   2-B
0624                                             BLA   80063
0625   4865   BBB 0 00   0020   0002   80065   CON   00002   00002   2-9
0626   4866   BBB 0 00   0030   000A   80066   CON   00003   0000A   2-F
0627   4867   BBB 0 00   0010   000A   80067   CON   00001   0000A   2-G
0628   4868   BBB 0 00   0020   000A   80068   CON   00002   0000A   2-H
```

```
0629    4870   888 0 00   0030   0003    80070   CON   00003    00003          3-4
0630                                             BLA   80071
0631    4872   888 0 00   0010   0008    80072   CON   00001    00008          3-8
0632    4873   888 0 00   0000   000H    80073   CON   00000    0000H          3-C
0633    4875   888 0 00   0030   0001    80075   CON   00003    00001          3-9
0634                                             BLA   80076
0635    4877   888 0 00   0000   000G    80077   CON   00000    0000G          3-G
0636                                             BLA   80078
0637                                             ON     9001
0638                                             ON     8001
0639                                    INCR1    EQU    0057                   INTERLACE FOR NON-CORE PROGRAMS
0640                                    MEMLL    BLR    3100     3999          POOLED MEMORY AREA
0641                                    MEML1    EQU    3099                   MEML1 IS MEMLL - 1
0642                                    MEML2    EQU    3299                   AREA BETWEEN MEMLL AND MEML2 IS USED FOR
0643                                                                            OVERLAYABLE PROGRAM
0644                                    MEMU2    EQU    4000                   TOP OF POOLED MEMORY
0645                                    10000    BLR    1250     1258          PANIC - ALARM ROUTINE
0646                                             BLR   10009    10015 002
0647                                    20000    EQU    0600                   PRINTER BAND - ALARM ROUTINE
0648                                             BLR   20000    20005 005
0649                                             BLR   20081    20086 005
0650                                             BLR   20165    20170 005
0651                                             BLR   20050    20055 005
0652                                             BLR   20134    20139 005
0653                                             BLR   20018    20023 005
0654                                             BLR   20103    20108 005
0655                                             BLR   20041    20046 005
0656                                             BLR   20125    20130 005
0657                                             BLR   20009    20014 005
0658                                             BLR   20094    20099 005
0659                                             BLR   20178    20183 005
0660                                             BLR   20062    20067 005
0661                                    30000    BLR    1650     1699          ALARM DICTIONARY OF WORDS
0662                                             HHH       H
0663                                             ON     8002
0664                                             ON     9002
```

```
0665                                                                                    G.  GENERATOR CONTROL
0675   4140  BBB 0 30  4042  4044   NORMX   LDL   NORM        SCAN      G1. SCAN NEXT ITEM.
0676   4044  BBB 0 50  4246  4248   SCAN    STL   GENX        SCANX         THIS SHOWS TYPICAL TRANSFER OF CONTROL
0677   4248  BBB 0 30  4050  4202   SCANX   LDL   E0000       NXTCH         BETWEEN TWO COROUTINES
0678   4028  BBB 0 05  4030  4232   GEN     LDX   LAST
0679   4232  BBB 0 50  4248  4200          STL   SCANX
0680   4200  BBB 0 30  4402  4204          LDL   LEOFF
0681   4204  BBB 0 50  4206  4208          STL   LESW
0682   4208  BBB 0 60  4030  4246          STA   LAST        GENX
0683   4042  BBB 0 77  4042  4245   NORM    ATL               1F        G2. ISIT AN OPERATOR
0684   4245  BBB 0 70  4247  4400   1       ADD   BIG30       -OP1
0685
0686   4400  BBB 1 0G  0001  4404   -OP1    IIR3  0001                  G3. OPERAND STACKED
0687   4404  BBB 1 54  0000  4602          STL3  0000
0688   4602  BBB 0 25  4604  4406          LDA   BIG25                 G4. IS IT AN ARRAY
0689   4406  BBB 0 87  4017  4009          TGR   1F    +08
0690   4009  BBB 0 70  000A  4214          ADD   RA
0691   4214  BBB 0 87  4217  4017          TGR   ARRAY       1F
0692   4017  BBB 0 30  4219  4044   1       LDL               SCAN      G5. SCAN NEXT ITEM
0693   4219  BBB 0 30  4221  4023          LDL   LPREN
0694   4023  BBB 0 82  4226  4042          TEQ   FUNCT       NORM
0696
0697   4401  BBB 0 70  4203  4606   &OP1    ADD   BIG71       -OP2      G6. WHAT KIND OPERATOR
0698   4607  BBB 0 00  000A  000A   &OP2    JMP   RA
0701
0703
0706   4606  BBB 0 70  4408  4211   -OP2    ADD   BIG01       -OP4
0707   4211  BBB 0 50  4213  4215   -OP4    STL   OHOLD       OPX       G7. PUT OP IN OHOLD.
0710   4215  BBB 0 25  4417  4419   OPX     LDA   RATOR                 G10.P(RATOR):P(OHOLD)
0711   4419  BBB 0 70  4421  000A          ADD               RA
0712   4421  BBB 0 30  0001  4403          LDL    0001
0713   4403  BBB 0 25  4213  4415          LDA   OHOLD
0714   4415  BBB 0 35  4617  4619          ERS   X0
0715   4619  BBB 0 87  4222  4422          TGR   1F
0716   4422  BBB 0 30  4224  4426          LDL   2F          REMRT
0717   4426  BBB 0 08  4417  4229   REMRT   LIR1  RATOR       REM
0718   4224  BBB 0 07  HHHH  4227   2       IIR    HHHH
0719   4227  BBB 0 39  0001  000A          ERS1   0001       RA
0727   4222  BBB 0 05  4213  4615   1       LDX   OHOLD                 G19.COMMA OR SEMICOLON
0728   4615  BBB 0 25  4267  4819          LDA   XM1
0729   4819  BBB 0 35  000C  4223          ERS   RX
0730   4223  BBB 0 70  4225  4428          ADD   BIG99       -OP3
0731   4429  BBB 0 00  000A  000A   &OP3    JMP   RA
0732   4428  BBB 0 25  000C  4432   -OP3    LDA   RX          3F
0733   4212  BBB 0 25  0008  4432   &OP4    LDA   RL          3F
0734   4234  BBB 1 07  0001  4238   MDOP2   IIR2   0001       MDOP1
0735   4235  BBB 1 07  0004  4238   MDOP    IIR2   0004       MDOP1
0736   4238  BBB 1 50  0000  4428   MDOP1   STL2  0000        -OP3
0737   4432  BBB 0 30  4140  4242   3       LDL   NORMX       INSRT     G20.OPERATOR STACKED
```

```
0738     4242  888 0 08  4417  4445      INSRT      LIRI RATOR      INS
0740
```

```
                                                                                S.  SCANNER CONTROL
  0746
- 0750  4050  888 0 30  4252  4202   SCAN1   LDL              NXTCH     S1. NEXT CHARACTER
  0753  4252  888 0 08  4050  4205           LIR1 E0000       KIND      S2. WHAT KIND
  0754
  0756
  0758
  0761
  0762
  0765  4053  888 0 30  4405  4207   E0003   LDL  805                    S3. LOOK FOR IJKLMN
  0766  4207  888 0 50  4209  4411           STL  TEMP2
  0767  4411  888 0 30  4413  4265           LDL  LIT8
  0768  4265  888 0 87  4018  4218           TGR              1F
  0769  4018  888 0 30  4220  4622           LDL# 00001       00005
  0770  4622  888 0 87  4218  4425           TGR  1F
  0771  4425  888 0 25  4408  4210           LDA  BIG01       2F
  0772  4218  888 0 26  4210  4210   1       CLA  2F
  0773  4210  888 0 60  4412  4414   2       STA  TYPE
  0774  4414  888 0 25  4016  4418           LDA  LIT1        1F
- 0775  4625  888 0 70  4016  4418   5       ADD  LIT1        1F
  0776  4418  888 0 60  4420  4272   1       STA  TEMP3
  0777  4272  888 0 30  4424  4626           LDL  LIT5
  0778  4626  888 0 87  4629  4829           TGR  3F          2F
  0779  4829  888 0 25  4209  4611   2       LDA  TEMP2
  0780  4611  888 0 37  0100  4465           SHL   0100
  0781  4465  888 0 35  4467  4269           ERS# HHHH0       HHHHH
  0782  4269  888 0 20  000C  4423           BUF  RX                    S4. NEXT CHARACTERS
  0783  4423  888 0 60  4209  4629           STA  TEMP2       3F
  0784  4629  888 0 30  4231  4202   3       LDL              NXTCH
  0785  4231  888 0 08  4055  4205           LIR1 E0005       KIND
  0786  4056  888 0 30  4055  4407   E0006   LDL  E0005       SETNS
  0787  4059  888 0 30  4055  4407   E0009   LDL  E0005       SETNS
  0788  4058  888 0 25  4420  4625   E0008   LDA  TEMP3       5B
  0789  4057  888 0 25  4420  4625   E0007   LDA  TEMP3       5B
  0790  4055  888 0 06  4608  4608   E0005   CLX                        S5. SEARCH SYMBOL TABLE
  0791  4608  888 0 30  4410  4612           LDL  SEND        SRCH1
  0792  4051  888 0 65  4209  4261   E0001   STX  TEMP2
  0793  4261  888 0 26  4614  4614           CLA
  0794  4614  888 0 60  4412  4814           STA  TYPE
  0795  4814  888 0 25  4016  4618           LDA  LIT1
  0796  4618  888 0 60  4420  4055           STA  TEMP3       E0005
  0797  4410  888 0 50  4420  4472   SEND    STL  TEMP3       SEND1     S10.TRANSLATE TO GEN CODE.
  0798  4472  888 0 25  4624  4076   SEND1   LDA  TEMP4
  0799  4076  888 0 77  4076  4079           ATL
  0800  4079  888 0 06  4632  4632           CLX
  0801  4632  888 0 32  0900  4244           SHR   0900
  0802  4244  888 0 70  4446  000A           ADD              RA
  0803  4446  888 0 25  0008  4040           LDA  RL          S0000
  0804  4040  888 0 25  4420  4672   S0000   LDA  TEMP3
  0805  4672  888 0 30  4824  4276           LDL  OOVAR
```

```
0806   4276   888 J 82   4279   4479                TEQ   2F          3F
0807   4479   888 J 20   4412   4264   3            BUF   TYPE        SCAN9
0808   4279   888 J 25   4431   4264   2            LDA   BIG21       SCAN9
0809   4043   888 J 35   4645   4479   S0003        ERS               3B
0810   4645   888 J H0   HHHH   0000                CON   H0HHH       H0000
0811   4045   888 J 35   4617   4469   S0005        ERS   X0
0812   4469   888 0 20   4420   4264                BUF   TEMP3       SCAN9
0813   4046   888 0 70   4448   4451   S0006        ADD               -SEND
0814   4448   888 0 31   0000   0000                CON   31000       00000
0815   4452   888 0 05   4804   4256   &SEND        LDX   NOTAG
0816   4256   888 0 32   0F00   000C                SHR    0F00       RX
0817   4451   888 0 25   4603   4605   -SEND        LDA   BIG60
0818   4605   888 0 20   4420   4479                BUF   TEMP3       3B
0819   4049   888 0 35   4201   4264   S0009        ERS   X0M         SCAN9
0820   4048   888 0 35   4201   4264   S0008        ERS   X0M         SCAN9
0821   4047   888 0 35   4201   4264   S0007        ERS   X0M         SCAN9
0822   4264   888 0 30   4050   4028   SCAN9        LDL   SCAN1       GEN          S20•SEND TO GEN
```

```
0826                                                                                    N.  'GET NEXT CHARACTER' ROUTINE
0827    4407  888 0 65  4409  4461    SETNS     STX   NEXTC                               SUBROUTINE SETNS PUTS BACK PREV CHAR ON CARD
0828    4461  888 0 25  4613  4665              LDA   NXTW                            N1. WAS CHAR PUT BACK
0829    4665  888 0 60  4202  000B              STA   NXTCH     RL
0830    4613  888 0 05  4409  4661    NXTW      LDX   NEXTC
0831    4661  888 0 25  4813  4315              LDA   NXTN
0832    4315  888 0 60  4202  0008              STA   NXTCH     RL
0833    4202  888 0 25  4456  4258    NXTCH     LDA   NZONS     1F                      NXTCH IS SET TO EITHER NXTW OR NXTN
0834    4813  888 0 25  4456  4258    NXTN      LDA   NZONS     1F
0835    4258  888 0 05  000A  4262    1         LDX   RA
0836    4262  888 0 50  4464  4216              STL   EXIT1                           N2. END OF WORD
0837    4216  888 0 70  000A  4321              ADD   RA        -INP1
0840    4322  888 0 07  0001  4075    &INP1     IIR    0001
0841    4075  888 0 70  4427  4230              ADD   NWORD                           N3. END OF CARD
0842    4230  888 0 60  4427  000A              STA   NWORD     RA
0843    4427  888 0 00  4038  4038    NWORD     JMP   N0008
0844    4037  888 0 08  0303  4240    N0007     LIR1  K0103     1F
0845    4031  888 0 08  0200  4240    N0001     LIR1  K0000     1F                      N4. GET NEW WORD
0846    4032  888 0 08  0281  4240    N0002     LIR1  K0081     1F
0847    4033  888 0 08  0365  4240    N0003     LIR1  K0165     1F
0848    4034  888 0 08  0250  4240    N0004     LIR1  K0050     1F
0849    4035  888 0 08  0334  4240    N0005     LIR1  K0134     1F
0850    4036  888 0 08  0218  4240    N0006     LIR1  K0018     1F
0851    4240  888 0 29  0000  4652    1         LDA1   0000
0852    4652  888 0 09  0005  4257              LDX1   0005     SHFT
0853    4257  888 0 60  4609  4311    SHFT      STA   NNUMS     BKSW
0854                                            OFF    9000
0872                                            ON     9001
0873                                            ON     9002
0899                                            ON     9000
-- 0900    4038  888 0 08  0241  4240    N0008     LIR1  K0041     1B
   0901    4321  888 0 26  4311  4311    -INP1     CLA   BKSW
   0902    4311  888 0 31  4664  4664    BKSW      CLL   1F
   0903    4253  888 0 31  4664  4664    BKON      CLL   1F
   0904    4664  888 0 20  000C  4268    1         BUF   RX
   0905    4268  888 0 82  4621  4275              TEQ             2F      +04
   0906    4621  888 0 05  4623  4275              LDX   BIG05     2F
   0907    4275  888 0 25  4627  4679    2         LDA#  40000     00000
   0908    4679  888 0 35  4609  4511              ERS   NNUMS
   0909    4511  888 0 32  0400  4468              SHR    0400
   0910    4468  888 0 70  000C  4823              ADD   RX
   0911    4823  888 0 35  4475  4077              ERS#  HHHHH     00000
   0912    4077  888 0 77  4077  4430              ATL
   0913    4430  888 0 20  4282  4434              BUF#  00005     00000
   0914    4434  888 0 32  0500  4442              SHR    0500
   0915    4442  888 0 60  4456  4458              STA   NZONS
   0916    4458  888 0 06  4711  4711              CLX
   0917    4711  888 0 25  4609  4911              LDA   NNUMS
   0918    4911  888 0 32  0900  4273              SHR    0900
```

```
0919  4273  BBB J 65  4609  4361          STX  NNUMS
0920  4361  BBB J 37  0400  4668          SHL   0400
0921  4668  BBB 0 20  0008  4522          BUF  RL
0922  4522  BBB J 35  4274  4476          ERS# 0000H     80000
0923  4476  BBB 0 70  4228  000A          ADD            RA
0924  4228  BBB J 05  4800  4302          LDX  80000     4F
0925  4675  BBB 0 25  4277  4879  BKOF    LDA  BIG50     3F
0926                                      ON    9001
0927                                      ON    9002
0928                                      ON    8001
0929                                      ON    8002
0930  4879  BBB 0 32  0900  4041  3       SHR   0900                 N10.EXTRACT NEXT CHAR
0931  4041  BBB 0 60  4456  4658          STA  NZONS
0932  4658  BBB 0 25  000C  4462          LDA  RX
0933  4462  BBB 0 37  0400  4669          SHL   0400
0934  4669  BBB 0 05  4609  4561          LDX  NNUMS
0935  4561  BBB 0 32  0900  4473          SHR   0900
0936  4473  BBB 0 60  4609  4302          STA  NNUMS     4F
0937  4302  BBB 0 30  4254  4656  4       LDL  STAN
- 0938  4656  BBB 0 50  4257  4464          STL  SHFT      EXIT1
0939  4254  BBB 0 60  4609  4311  STAN    STA  NNUMS     BKSW        N20.GET NEW CARD
0940  4039  BBB J 07  4030  4642  N0009   IIR  N0000
0941  4642  BBB 0 30  4444  4646          LDL  SHFT4
0942  4646  BBB 0 50  4257  4809          STL  SHFT
0943  4809  BBB 0 60  4427  4329          STA  NWORD     CREAD
0944  4444  BBB 0 20  4277  4529  SHFT4   BUF  BIG50
0945  4529  BBB 0 32  0400  4236          SHR   0400     SHFTF
0946  4236  BBB 0 32  0F00  4254  SHFTF   SHR   0F00     STAN
0947                                      HHH
0948  4329  BBB 0 25  0131  0133  CREAD   LDA  CMOVE                 N21.MOVE BUFFERS
0949  0133  BBB 0 05  0135  0337          LDX  CHALT     BU
0950  0150  BBB 0 25  000C  0337  BU1     LDA  RX        BU
0951  0337  BBB 0 60  0139  0141  BU      STA  CHI       CRDSW
0952  0141  BBB 0 31  0144  0144  CRDSW   CLL  3F
0954  0154  BBB 0 31  0144  0144  CRDC    CLL  3F
0955  0144  BBB 0 08  0150  0347  3       LIR1  0150     2F
0956  0347  BBB 0 42  0151  0350  2       HBT  4F
0957  0350  BBB 0 0G  9999  0354          IIR1  9999
0958  0354  BBB 0 82  000C  0347          TEQ  RX        2B
0959  0135  BBB 0 67  2223  0023  CHALT   HLT   2223
0960  0023  BBB 0 30  0154  0156          LDL  CRDC      HCC
0961  0156  BBB 0 72  000A  0159  HCC     HCC  RA        -CRD
0962  0160  BBB 0 67  2222  000A  &CRD    HLT   2222     RA
0963  0159  BBB 0 25  0154  0356  -CRD    LDA  CRDC
0964  0356  BBB 0 60  0141  0008          STA  CRDSW     RL
0965                                      OFF   9000
1013                                      ON    9000
1014                                CTP   NEW1 77000     0B3AG
1015                                      OFF   9000
1016                                      ON    9001
```

```
1017                                                    ON    9002
1019                                                    ON    9000
1020  0151  888 0 96  0000  0013      4                 HBU   H0000
1021  0013  888 0 30  0015  0017                        LDL   H10
1022  0017  888 0 25  0021  0823                        LDA   H0021
1023  0823  888 0 82  0226  0154                        TEQ         CRDC
1024  0226  888 0 25  4607  0059                        LDA   &0P2                 &0P2 IS A 'JMP RA'
1025  0059  888 0 60  0141  0139                        STA   CRDS#      CHI
1026  0131  888 0 30  0333  0156      CMOVE             LDL           HCC
1027  0333  888 0 25  0031  0033                        LDA   H0031
1028  0033  888 0 05  0036  0038                        LDX   H0036
1029                                                    CTP
1030  0038  888 0 60  0281  0083                        STA   K0081
1031  0083  888 0 65  0286  0088                        STX   K0086
1032  0088  888 0 25  0112  0114                        LDA   H0112
1033  0114  888 0 05  0117  0119                        LDX   H0117
1034                                                    CTP
1035  0119  888 0 60  0334  0136                        STA   K0134
1036  0136  888 0 65  0339  0341                        STX   K0139
1037  0341  888 0 25  0051  0053                        LDA   H0051
1038  0053  888 0 05  0056  0058                        LDX   H0056
1039                                                    CTP
1040  0058  888 0 60  0365  0367                        STA   K0165
1041  0367  888 0 65  0370  0372                        STX   K0170
1042  0372  888 0 25  0011  0213                        LDA   H0011
1043  0213  888 0 05  0016  0018                        LDX   H0016
1044                                                    CTP
1045  0018  888 0 60  0200  0002                        STA   K0000
1046  0002  888 0 65  0205  0007                        STX   K0005
1047  0007  888 0 25  0071  0073                        LDA   H0071
1048  0073  888 0 05  0076  0078                        LDX   H0076
1049                                                    CTP
1050  0078  888 0 60  0250  0052                        STA   K0050
1051  0052  888 0 65  0255  0057                        STX   K0055
1052  0057  888 0 25  0132  0134                        LDA   H0132
1053  0134  888 0 05  0137  0939                        LDX   H0137
1054                                                    CTP
1055  0939  888 0 60  0218  0020                        STA   K0018
1056  0020  888 0 65  0223  0025                        STX   K0023
1057  0025  888 0 25  0027  0029                        LDA   LEVEL
1058  0029  888 0 70  0231  0034                        ADD   BAND
1059                                                    OFF   9000
1064                                                    ON    9000
1065  0034  888 0 20  0236  0238                        BUF#  33000       03333
1066  0238  888 0 17  0238  0841                        MTC
1067  0841  888 0 35  0043  0045                        ERS   XM
1068  0045  888 0 60  0325  0327                        STA   K0125
1069  0327  888 0 65  0330  0332                        STX   K0130
1070                                                    ON    9001
1071                                                    ON    9002
```

```
1072  0352  888 0 25  0152  0554          LDA  H0152
1073  0554  888 0 05  0157  0359          LDX  H0157
1074                                      CTP
1075  0359  888 0 60  0303  0105          STA  K0103
1076  0105  888 0 65  0308  0310          STX  K0108
1077  0310  888 0 25  0172  0174          LDA  H0172
1078  0174  888 0 05  0177  0179          LDX  H0177
1079                                      CTP
1080  0179  888 0 60  0241  0243          STA  K0041
1081  0243  888 0 65  0246  0048          STX  K0046
1082                                      ON    8001
1083                                      ON    8002
1084  0048  888 0 25  0050  0252          LDA  LC
1085  0252  888 0 70  0054  0257          ADD  BIG04      -CRD2
1086  0258  888 0 60  0050  0452  &CRD2    STA  LC
1087  0452  888 0 11  0218  0189          PRN  K0018      -CRD3
1088  0257  888 0 60  0050  0652  -CRD2    STA  LC
1089  0652  888 0 11  0202  0189          PRN  K0002      -CRD3
1090  0190  888 0 05  0392  0194  &CRD3    LDX             1F
1091  0392  888 0 67  3333  0533          HLT   3333      THETA
1092  0194  888 0 60  0533  0150  1       STA  THETA      BU1
1093  0189  888 0 05  0200  0202  -CRD3    LDX  K0000
1094  0202  888 0 25  0205  0207          LDA  K0005
1095  0207  888 0 35  0009  0211          ERS  H5
1096  0211  888 0 32  0500  0019          SHR   0500
1097  0019  888 0 37  0500  0227          SHL   0500
1098  0227  888 0 20  000C  0431          BUF  RX
1099  0431  888 0 60  0233  0035          STA  COL15
1100  0035  888 0 35  0037  0039          ERS  X05
1101  0039  888 0 30  1241  0443          LDL  2F
1102  0443  888 0 82  4329  0846          TEQ  CREAD
1103  0846  888 0 25  0200  0402          LDA  K0000
1104                                      OFF   9000
1116                                      ON    9000
1117  0402  888 0 05  0205  0407          LDX  K0005
1118  0407  888 0 12  0407  0010          CTM
1119  0010  888 0 35  0012  0014          ERS  X5
1120  0014  888 0 31  0217  0217          CLL
1121  0217  888 0 82  0220  4322          TEQ              &INP1
1122  0220  888 0 05  0022  4464          LDX  X9          EXIT1
1123  1241  888 0 10  0001  0000  2       CON  10000       10000
1124                                      ON    9001
1125                                      ON    8001
1126                                      HHH        H
1127                                      ON    9002
1128                                      ON    8002
```

```
1129  4729  888 0 60  4420  4612  SRCH    STA  TEMP3     SRCH1      T.  SYMBOL TABLE SEARCH.
1130  4612  888 0 65  4624  4676  SRCH1   STX  TEMP4
1131  4676  888 0 25  4628  4630          LDA  MZERO
1132  4630  888 0 70  4209  4662          ADD  TEMP2
1133  4662  888 0 50  4464  4416          STL  EXIT1
1134  4416  888 0 37  0100  4620          SHL   0100                  T1. SCRAMBLE
1135  4620  888 0 77  4620  4673          ATL
1136  4673  888 0 85  4325  4502          MUL# 10101      01010
1137  4502  888 0 70  4420  4323          ADD  TEMP3
1138  4323  888 0 32  0600  4482          SHR   0600
1139  4482  888 0 07  00HH  4435          IIR   00HH
1140  4435  888 0 35  000C  4239          ERS  RX
1141  4239  888 0 70  4241  000A          ADD             RA
1142  4241  888 0 08  1420  4447          LIR1 Z0000
1143  4447  888 0 30  4209  4761          LDL  TEMP2
1144  4761  888 0 29  0000  4702          LDA1  0000      1F         T2. IS STACK EXHAUSTED
1145  4702  888 0 70  4454  4307  1       ADD             -SCRM
1146  4454  888 0 99  9999  0000          CON  99999      90000
1147  4307  888 0 25  000B  4961  -SCRM   LDA  RL
1148  4961  888 0 05  4624  4876          LDX  TEMP4      INS99
1149  4308  888 0 05  000A  4312  &SCRM   LDX  RA                     T3. DOES SYMBOL MATCH
1150  4312  888 0 70  4864  000A          ADD             RA
1151  4864  888 0 25  0002  4654          LDA   0002
1152  4654  888 0 82  4457  4657          TEQ  2F
1153  4657  888 0 25  000C  4512          LDA  RX
1154  4512  888 0 70  4314  000A          ADD             RA
1155  4314  888 0 25  0001  4453          LDA   0001
1156  4453  888 0 37  0600  4712          SHL   0600
1157  4712  888 0 32  0200  4702          SHR   0200      1B
1158  4457  888 0 07  0001  4610  2       IIR   0001                  T4. GET TABLE ENTRY
1159  4610  888 0 70  000C  4515          ADD  RX
1160  4515  888 0 77  4515  4318          ATL
1161  4318  888 0 70  4270  000A          ADD             RA
1162  4270  888 0 05  0000  4902          LDX   0000
1163  4902  888 0 65  4624  4464          STX  TEMP4      EXIT1
```

```
1169  4445  888 0 50  4464  4876      INS     STL  EXIT1     INS99     L.  LINKED MEMORY SUBROUTINES.
1188  4876  888 0 31  4929  4929      INS99   CLL                      L1. IS AVAIL EMPTY
1189  4929  888 0 60  4631  4233              STA  TEMP1
1190  4233  888 0 25  4635  4237              LDA  AVAIL
1191  4237  888 0 82  4440  4640              TEQ                   1F
1192  4440  888 0 25  4292  4644              LDA  MEMU                L2. MEML:MEMU
- 1193  4644  888 0 75  4095  4648              SUB  KON2
1194  4648  888 0 30  4600  4352              LDL  MEML
1195  4352  888 0 87  4255  4455              TGR                   2F
1196  4255  888 0 60  4292  4844              STA  MEMU                L3. RESERVE TWO
1197  4844  888 0 77  4844  4647              ATL                   3F
1198  4455  888 0 25  4507  4259      2       LDA# 01020    00000          I'M FULL
1199  4259  888 0 30  4912  4514              LDL                   ALARM
1200  4912  888 0 67  1212  4455              HLT   1212            2B
1201  4640  888 0 77  4640  4243      1       ATL                      L4. INSERT ITEM
1202  4243  888 0 70  4295  000A              ADD                   RA
1203  4295  888 0 25  0000  4552              LDA   0000
1204  4552  888 0 60  4635  4647              STA  AVAIL            3F
1205  4647  888 0 25  4249  4601      3       LDA  1F
1206  4601  888 0 70  000B  4306              ADD  RL
1207  4306  888 0 32  0600  4715              SHR   0600
1208  4715  888 0 35  4667  4869              ERS  X0C
1209  4869  888 0 24  0000  4752              BUF1  0000
- 1210  4752  888 0 32  0400  000C              SHR   0400            RX          ASSUMPTION MADE THAT RX WAS POSITIVE
1211  4249  888 0 60  0000  4952      1       STA   0000
1212  4952  888 0 05  4631  4433              LDX  TEMP1
1213  4433  888 0 25  000B  4437              LDA  RL
1214  4437  888 0 70  4439  4492              ADD  1F
1215  4492  888 0 54  0000  000A              STL1  0000            RA
1216  4439  888 0 65  0001  4464      1       STX   0001            EXIT1
1217  4229  888 0 50  4464  4616      REM     STL  EXIT1                     L10.IS STACK EMPTY
1218  4616  888 0 54  0000  4653              LDL1  0000
1219  4653  888 0 26  4506  4506              CLA
1220  4506  888 0 82  000C  4459              TEQ  RX
1221  4459  888 0 05  4635  4637              LDX  AVAIL                     L11.REMOVE ITEM
1222  4637  888 0 06  0000  4441              IIR1  0000
1223  4441  888 0 20  4443  4495              BUF  1F
1224  4495  888 0 60  4631  4633              STA  TEMP1
1225  4633  888 0 25  000B  4087              LDA  RL
1226  4087  888 0 50  4635  4287              STL  AVAIL                     L12.MAKE LOCATION AVAIL
1227  4287  888 0 30  4639  4641              LDL                   BR
1228  4639  888 0 77  4639  4692              ATL
1229  4692  888 0 37  0400  4449              SHL   0400
1230  4449  888 0 35  0043  4631              ERS  XM               TEMP1
1231  4443  888 0 60  0000  4853      1       STA   0000
1232  4853  888 0 69  0000  4464              STX1  0000            EXIT1
1233  4833  888 1 29  0000  4303      BR2     LDA3  0000            BR1
1234  4303  888 0 35  0043  4641      BR1     ERS  XM               BR
1235  4641  888 0 20  4643  000A      BR      BUF                   RA
```

```
1236   4643   888 0 08   0000   4848          LIR1  0000
1237   4848   888 0 29   0000   0008          LDA1  0000      RL
1238   4205   888 0 30   000C   4659   KIND   LDL   RX                    KIND SUBROUTINE IS 5-WAY BRANCH TO
1239   4659   888 0 25   4362   4714          LDA   LITB                  RB1   IF CHARACTER IS BLANK
1240   4714   888 0 88   0000   4518          TEQ1  0000                  RB1+1 IF SPECIAL CHARACTER
1241   4518   888 0 25   4628   4280          LDA   MZERO                 RB1+2 NUMERIC 999990000N
1242   4280   888 0 70   000C   4285          ADD   RX          1F        RB1+3 ALPHABETIC
1243   4285   888 0 82   4438   4638   1      TEQ               1F        RB1+4 DECIMAL POINT
1244   4438   888 0 30   4290   4892          LDL#  00003       00001
1245   4892   888 0 88   0001   4296          TEQ1  0001
1246   4296   888 0 30   4298   4250          LDL   KON30
1247   4250   888 0 88   0001   4854          TEQ1  0001
1248   4854   888 0 70   4706   4309          ADD               -KIND
1249   4706   888 0 99   9990   0000          CON   99999       00000
1250   4309   888 0 04   0002   0002   -KIND  JMP1  0002
1251   4310   888 0 04   0003   0003   &KIND  JMP1  0003
1252   4638   888 0 25   4490   4342   1      LDA#  00001       0000A
1253   4342   888 0 88   0004   4496          TEQ1  0004
1254   4496   888 0 04   0001   0001          JMP1  0001
```

```
1255  4655  888 0 50  4464  4266  NOMLZ   STL  EXIT1                    C.  CONSTANT SCANNER
1256  4266  888 0 25  4209  4562          LDA  TEMP2                        NORMALIZE IS USED TO CONVERT TO
1257  4562  888 0 31  4915  4915          CLL                               FLOATING POINT FORM
1258  4915  888 0 82  4464  4718          TEQ  EXIT1
1259  4718  888 0 06  4271  4271          CLX
1260  4271  888 0 08  0000  4474          LIR1 0000      1F
1261  4474  888 0 32  0100  4828  1       SHR  0100
1262  4828  888 0 82  4281  4481          TEQ  1F
1263  4481  888 0 32  0100  4485          SHR  0100
1264  4485  888 0 82  4838  4288          TEQ  2F
1265  4288  888 0 60  4209  4762          STA  TEMP2
1266  4762  888 0 0G  0002  4466          IIR1 0002
1267  4466  888 0 25  4209  4474          LDA  TEMP2     1B
1268  4281  888 0 0G  0050  4685  1       IIR1 0050      3F
1269  4838  888 0 0G  0051  4685  2       IIR1 0051      3F
1270  4685  888 0 75  4420  4523  3       SUB  TEMP3
1271  4523  888 0 32  0200  4078          SHR  0200
1272  4078  888 0 37  0600  4487          SHL  0600
1273  4487  888 0 20  000C  4464          BUF  RX        EXIT1
1274  4064  888 0 05  4209  4962  E0014   LDX  TEMP2     2F        C1. SET TYPE INTEGER
1275  4962  888 0 26  4365  4365  2       CLA  1F
1276
1277  4052  888 0 07  0001  4365  E0002   IIR  0001      1F        C2. SET FLOATING TYPE.
1278  4054  888 0 06  4962  4962  E0004   CLX  2B
1279  4365  888 0 60  4412  4914  1       STA  TYPE
1280  4914  888 0 65  4209  4263          STX  TEMP2                C3. NEXT CHARACTER
1281  4263  888 0 26  4666  4666          CLA  1F
1282  4666  888 0 60  4420  4060  1       STA  TEMP3     E0010
1283  4060  888 0 30  4463  4202  E0010   LDL            NXTCH
1284  4463  888 0 08  4060  4205          LIR1 E0010     KIND      C4. WHAT KIND
1285  4062  888 0 25  4209  4663  E0012   LDA  TEMP2
1286  4663  888 0 37  0100  4317          SHL  0100
1287  4317  888 0 20  000C  4471          BUF  RX
1288  4471  888 0 60  4209  4863          STA  TEMP2
1289  4863  888 0 07  0001  4316          IIR  0001
1290  4316  888 0 70  4420  4666          ADD  TEMP3     1B
1291  4063  888 0 60  4631  4283  E0013   STA  TEMP1                  C5. E H OR M
1292  4263  888 0 25  4402  4304          LDA  LEOFF
1293  4304  888 0 30  4206  4508          LDL  LESW
1294  4508  888 0 82  4313  4061          TEQ            E0011
1295  4313  888 0 25  4631  4483          LDA  TEMP1
1296  4483  888 0 30  4424  4326          LDL  LIT5
1297  4326  888 0 82  4179  4379          TEQ  EROUT
1298  4379  888 0 30  4413  4565          LDL  LIT8
1299  4565  888 0 82  4918  4168          TEQ  HROUT
1300  4168  888 0 30  4470  4722          LDL# 00001     00004
1301  4722  888 0 82  4525  4061          TEQ  MROUT     E0011
1302  4061  888 0 30  4513  4407  E0011   LDL  5F        SETNS     C6. ADJUST FOR TYPE
1303  4513  888 0 25  4412  4364  5       LDA  TYPE
```

```
1304  4964  888 0 31  4517  4517                CLL
1306  4517  888 0 82  4670  4320                TEQ       1F
1307  4670  888 0 30  4206  4655                LDL  LESW  NOMLZ
1308  4320  888 0 25  4209  4713  1             LDA  TEMP2
1309  4713  888 0 37  0400  4206                SHL   0400 LESW
1310  4206  888 0 30  4708  4260  LESW          LDL  1F    CONST   C7. IS IT A LABEL
1311  4402  888 0 30  4708  4260  LEOFF         LDL  1F    CONST
1312  4708  888 0 50  4420  4922  1             STL  TEMP3
1313  4922  888 0 25  4209  4913                LDA  TEMP2
1314  4913  888 0 31  4516  4516                CLL
1315  4516  888 0 82  4319  4519                TEQ  1F
1316  4519  888 0 25  4412  4564                LDA  TYPE  2F
1317  4319  888 0 07  0002  4564  1             IIR   0002 2F      C8. LOOK UP IN TABLE
1318  4564  888 0 37  0400  4671  2             SHL   0400
1319  4671  888 0 20  4723  4725                BUF  KON.5
1320  4725  888 0 60  4412  4472                STA  TYPE  SEND1
1321  4179  888 0 25  4412  4764  EROUT         LDA  TYPE          C10.NORMALIZE
1322  4764  888 0 87  4717  4917                TGR       1F
1323  4717  888 0 30  4064  4407                LDL  E0014 SETNS
1324  4917  888 0 30  4719  4655  1             LDL       NOMLZ
1325  4719  888 0 60  4209  4065                STA  TEMP2 E0015
1326  4065  888 0 30  4167  4202  E0015         LDL       NXTCH   C11.NEXT CHARACTER
1327  4167  888 0 08  4065  4205                LIR1 E0015 KIND
1328  4066  888 0 25  4298  4450  E0016         LDA  KON30         C12.WHAT KIND
1329  4450  888 0 82  4503  4703                TEQ  6F
1330  4703  888 0 25  4305  4707                LDA  LITA
1331  4707  888 0 82  4460  4660                TEQ  7F
1332  4660  888 0 25  4363  4765                LDA# 00001 0000C
1333  4765  888 0 82  4503  4069                TEQ  6F    E0019
1334  4067  888 0 30  4503  4407  E0017         LDL  6F    SETNS
1335  4069  888 0 30  4871  4407  E0019         LDL  CALRM SETNS
1336  4068  888 0 30  4871  4407  E0018         LDL  CALRM SETNS
1337  4871  888 0 30  4513  4965  CALRM         LDL  5B
1338  4965  888 0 25  4367  4514                LDA       ALARM
1339  4367  888 0 03  3000  0000                CON  03300 00000       BAD CONSTANT
1340  4460  888 0 25  4563  4503  7             LDA  2F    6F
1341  4503  888 0 60  4420  4172  6             STA  TEMP3
1342  4172  888 0 26  4925  4925                CLA  1F
1343  4925  888 0 60  4624  4070  1             STA  TEMP4 E0020
1344  4070  888 0 30  4372  4202  E0020         LDL       NXTCH   C13.NEXT NUMBERS
1345  4372  888 0 08  4070  4205                LIR1 E0020 KIND
1346  4074  888 0 30  4526  4407  E0024         LDL  9F    SETNS
1347  4073  888 0 30  4526  4407  E0023         LDL  9F    SETNS
1348  4071  888 0 30  4526  4407  E0021         LDL  9F    SETNS
1349  4072  888 0 25  4624  4563  E0022         LDA  TEMP4 2F
1350  4563  888 1 37  0100  4368  2             SHL2  0100
1351  4368  888 0 20  000C  4925                BUF  RX    1B
1352  4526  888 0 25  4420  4572  9             LDA  TEMP3
1353  4572  888 0 36  4175  4175                CAA                C14.ADJUST EXPONENT
1354  4175  888 0 20  4624  4726                BUF  TEMP4
```

```
1355    4726  888 0 37  0800  4687                SHL   0800
1356    4687  888 0 70  4209  4963                ADD   TEMP2       -ERUT
1357    4964  888 0 60  4209  4871  &ERUT         STA   TEMP2       CALRM
1358    4963  888 0 31  4716  4716  -ERUT         CLL
1359    4716  888 0 87  4206  4919                TGR   LESW
1360    4919  888 0 25  4209  4763                LDA   TEMP2
1361    4763  888 0 82  4206  4871                TEQ   LESW        CALRM
1362    4260  888 0 60  4209  4916  CONST         STA   TEMP2
1363    4916  888 0 50  4568  4520                STL   EXIT2
1364    4520  888 0 05  4623  4375                LDX   BIG05
1365    4375  888 0 26  4278  4278                CLA
1366    4278  888 0 30  4480  4729                LDL                 SRCH
1367    4480  888 0 25  000B  4634                LDA   RL
1368    4634  888 0 20  4436  000A                BUF                 RA
1369    4436  888 0 08  0000  4568                LIR1  0000          EXIT2
1370    4525  888 0 26  4478  4478  MROUT         CLA   1F                        C20.GET N CHARACTERS
1371    4478  888 0 60  4420  4772  1             STA   TEMP3
1372    4772  888 0 25  4209  4366                LDA   TEMP2
1373    4366  888 0 31  4169  4169                CLL
1374    4169  888 0 82  4972  4923                TEQ   9F
1375    4923  888 0 75  4016  4369                SUB   LIT1
1376    4369  888 0 60  4209  4566                STA   TEMP2
1377    4966  888 0 30  4768  4202                LDL                 NXTCH
1378    4768  888 0 25  000C  4173                LDA   RX
1379    4173  888 0 32  0500  4681                SHR   0500
1380    4681  888 0 70  000A  4636                ADD   RA
1381    4636  888 0 70  000A  4291                ADD   RA
1382    4291  888 0 37  0500  4649                SHL   0500
1383    4649  888 0 20  000C  4903                BUF   RX
1384    4903  888 0 37  0400  4510                SHL   0400
1385    4510  888 0 05  4420  4373                LDX   TEMP3
1386    4373  888 0 32  0900  4478                SHR   0900          1B
1387    4918  888 0 30  4972  4674  HROUT         LDL   9F          HOLSB       C30.GET N CHARACTERS
1388    4674  888 0 50  4926  4678  HOLSB         STL   EXIT3
1389    4678  888 0 25  4675  4477                LDA   BKOF
1390    4477  888 0 60  4311  4766                STA   BKSW
1391    4766  888 0 06  4569  4569                CLX
-1392   4569  888 0 65  4420  4573                STX   TEMP3
1393    4573  888 0 25  4209  4966                LDA   TEMP2       1F
1394    4966  888 0 31  4769  4769  1             CLL
1395    4769  888 0 82  4773  4973                TEQ   8F
1396    4973  888 0 75  4016  4969                SUB   LIT1
1397    4969  888 0 60  4624  4176                STA   TEMP4
1398    4176  888 0 30  4878  4202                LDL   2F          NXTCH
1399    4878  888 0 25  4420  4874  2             LDA   TEMP3
1400    4874  888 0 37  0100  4328                SHL   0100
1401    4328  888 0 20  000C  4682                BUF   RX
1402    4682  888 0 60  4420  4324                STA   TEMP3
-1403   4324  888 0 25  4624  4966                LDA   TEMP4       1B
1404    4773  888 0 25  4209  4567  8             LDA   TEMP2                   C31.ZERO FILL
```

```
1405    4967   888 0 30   4720   4524            LDL   LIT4
1406    4524   888 0 87   4677   4327            TGR   8F
1407    4327   888 0 70   4016   4920            ADD   LIT1
1408    4920   888 0 60   4209   4767            STA   TEMP2
1409    4767   888 0 06   4878   4878            CLX   2B
1410    4677   888 0 25   4253   4505      8     LDA   BKON
1411    4505   888 0 60   4311   4926            STA   BKSW      EXIT3
1412    4972   888 0 07   0002   4575      9     IIR    0002                 C32.TYPE UNSPECIFIED.
1413    4575   888 0 60   4412   4967            STA   TYPE
1414    4967   888 0 25   4420   4206            LDA   TEMP3     LESW
```

```
1415  4135  888 0 25  1064  4968        SIGN'   LDA  $                    Q.  SPECIAL SCANNING ROUTINES
1422  4968  888 0 30  4170  4028                LDL  DOES#     GEN        Q1. SEND SEMICOLON
1425  4170  888 0 25  0233  4885        DOES#   LDA  COL15     3F         Q2. END OF DO RANGE
1426  4376  888 0 25  0233  4885        DOEOF   LDA  COL15     3F
1428
1429                                            OFF   9000
1444                                            ON    9000
1445  4885  888 0 31  4488  4488        3       CLL                        Q3. ANY LABEL
1446  4488  888 0 82  4050  4491                TEQ  SCAN1
1447  4491  888 0 30  4843  4695                LDL# 10000     80000
1448  4695  888 0 82  3100  4498                TEQ  MEMLL
1449  4498  888 0 30  4650  4353                LDL  3F
1450  4353  888 0 50  4257  4859                STL  SHFT                  Q4. SCAN FROM COL 1
1451  4859  888 0 25  4370  4264                LDA  LABEL     SCAN9
1452  4650  888 0 35  4553  4254        3       ERS            STAN
1453  4953  888 0 HH  HHH0  HHHH                CON  HHHHH     0HHHH
1456                                            ON    9001
1457                                            ON    9002
1458                                            ON    8002
1459                                            ON    8001
1460  4710  888 0 05  4030  4882        DIVT2   LDX  LAST                   Q10.ADJUST CO-ROUTINE LINKS.
1461  4882  888 0 65  4834  4086                STX  DSAVE     DIVT1
1462  4086  888 0 05  4042  4294        DIVT1   LDX  NORM
1463  4294  888 0 65  4246  4698                STX  GENX      DIVRT
1464  4698  888 0 60  4300  4753        DIVRT   STA  DIVBS
1465  4753  888 0 25  4248  4500                LDA  SCANX
1466  4500  888 0 30  4953  4705                LDL  2F                    Q11.NEXT ITEM.
1467  4705  888 0 82  4908  4358                TEQ  1F
1468  4358  888 0 60  4910  4908                STA  SCNXX     1F
1469  4908  888 0 25  4300  4504  1             LDA  DIVBS     3F
1470  4504  888 0 70  4906  000A  3             ADD            RA
1471  4906  888 0 25  0000  4704                LDA   0000                 Q12.SEND TO GEN.
1472  4704  888 0 31  4907  4907                CLL
1473  4907  888 0 82  4360  4560                TEQ  1F
1474  4560  888 0 30  4953  4028                LDL  2F        GEN
1475  4953  888 0 07  0001  4356  2             IIR   0001
1476  4356  888 0 70  4300  4904                ADD  DIVBS
1477  4904  888 0 60  4300  4504                STA  DIVBS     3B
1478  4360  888 0 25  4834  4286  1             LDA  DSAVE
1479  4286  888 0 82  4910  4839                TEQ  SCNXX
1480  4839  888 0 50  4834  4486                STL  DSAVE
1481  4486  888 0 30  4910  4028                LDL  SCNXX     GEN
```

1482
1483
1484

I. ASSEMBLER STRUCTURE

```
1506  4556  888 0 05  4016  4570  ASM32  LDX  LIT1   ASM3    I.  I80. ASSEMBLER 3
1507  4557  888 0 05  4509  4570  ASM33  LDX         ASM3
1508  4509  888 0 01  0000  0001         CON  01000  00001
1509  4709  888 0 65  4770  4357  ASM34  STX  COMT   ASM33
1510  4760  888 0 65  4770  4556  ASM35  STX  COMT   ASM32
1511  4970  888 0 35  4724  4576  ASM36  ERS  XC
1512  4976  888 0 20  4528  4680         BUF  LIR1
1513  4660  888 0 05  4332  4570         LDX         ASM3
1514  4332  888 0 00  5010  0010         CON  00501  00010
1515  4521  888 0 05  4924  4570  ASM37  LDX         ASM3
1516  4924  888 0 00  0010  0001         CON  00001  00001
1517  4570  888 0 65  4624  4776  ASM3   STX  TEMP4  ASM31
1518  4776  888 0 60  4420  4174  ASM31  STA  TEMP3           I80.IS NXLOC SET
1519  4174  888 0 50  4926  4728         STL  EXIT3
1520  4728  888 0 25  4880  4532         LDA  NXLOC
1521  4532  888 0 31  4335  4335         CLL
1522  4335  888 0 82  4688  4888         TEQ  2F
1523  4888  888 0 50  4880  4732         STL  NXLOC  3F
1524  4688  888 0 05  4732  4084  2      LDX  3F     FARNL
1525  4732  888 0 30  4284  4686  3      LDL         FILUP   I81.FILL PREV INST
1526  4284  888 0 25  0008  4338         LDA  RL
1527  4338  888 0 32  0800  4849         SHR   0800
1528  4849  888 0 37  0500  4557         SHL   0500
1529  4557  888 0 32  0600  4721         SHR   0600          I82.ASSEMBLER 4.
1530  4721  888 0 25  4374  4976         LDA  OLDLC
1531  4976  888 0 20  4928  4330         BUF  RWORD
1532  4330  888 0 65  4374  4527         STX  OLDLC
1533  4527  888 0 05  4579  4881         LDX  IWORD
1534  4881  888 0 30  4683  4535         LDL         ASM4
1535  4683  888 0 05  4624  4727         LDX  TEMP4
- 1536  4727  888 0 65  4928  4530         STX  RWORD
1537  4930  888 0 05  4420  4574         LDX  TEMP3
1538  4974  888 0 65  4579  4926         STX  IWORD  EXIT3
```

```
1539  4289  888 0 65  4568  4921    ASM43   STX  EXIT2     ASM44      I.  I90. ASSEMBLER 4.
1540  4921  888 0 60  4209  4171    ASM44   STA  TEMP2
1541  4171  888 0 05  4774  4927            LDX               INCUQ
1542  4774  888 0 25  0008  4178            LDA  RL
1543  4178  888 0 31  4331  4331            CLL  1F
1544  4494  888 0 65  4568  4331    ASM42   STX  EXIT2     1F         I90.SET *********
1545  4331  888 0 32  0400  4538    1       SHR   0400
1546  4538  888 0 35  4724  4177            ERS  XC
1547  4177  888 0 20  0008  4531            BUF  RL
1548  4531  888 0 35  4667  4371            ERS  XOC
1549  4371  888 0 20  4974  4377            BUF  BIG10     1F
1550  4700  888 0 50  4568  4377    ASM41   STL  EXIT2     1F
1551  4377  888 0 05  4779  4731    1       LDX  CHOLD
1552  4731  888 0 65  4770  4775            STX  COMT
1553  4775  888 0 05  4577  4979            LDX  B10
1554  4979  888 0 65  0503  4905            STX  P0103
1555  4905  888 0 65  0508  4960            STX  P0108     1F
1556  4535  888 0 65  4209  4571    ASM4    STX  TEMP2
1557  4971  888 0 50  4568  4960            STL  EXIT2     1F         I91.PRINT, MAYBE
1558  4960  888 0 60  4631  4883    1       STA  TEMP1     PRTSW
1559                                        OFF   9000
1571                                        ON    9000
1572  4975  888 0 05  0503  4355    PRON    LDX  P0103
1573  4355  888 0 25  0508  4771            LDA  P0108
1574  4771  888 0 35  0009  4971            ERS  H5
1575  4971  888 0 32  0500  4730            SHR   0500
1576  4730  888 0 37  0500  4738            SHL   0500
1577  4738  888 0 20  000C  4542            BUF  RX
1578  4542  888 0 17  4542  4895            MTC
1579  4895  888 0 60  0503  4555            STA  P0103
1580  4555  888 0 65  0508  4777            STX  P0108
1581  4777  888 0 25  4631  4333            LDA  TEMP1
1582  4333  888 0 30  4735  4887            LDL  PROF      1F
1583  4533  888 0 60  4209  4977    PRNT    STA  TEMP2
1584  4977  888 0 25  000C  4887            LDA  RX        1F
1585  4887  888 0 50  4689  4691    1       STL  -PR2
1586  4691  888 0 17  4691  4694            MTC
1587  4694  888 0 32  0F00  4757            SHR   0F00
1588  4757  888 0 35  4909  4378            ERS# HHHOH     OHHHH
1589  4378  888 0 65  0565  4578            STX  P0165
1590  4578  888 0 60  0570  4778            STA  P0170
1591  4778  888 0 25  4209  4978            LDA  TEMP2
1592  4978  888 0 17  4978  4931            MTC
1593  4931  888 0 60  0534  4886            STA  P0134
1594  4886  888 0 65  0539  4891            STX  P0139
1595                                        ON    9001
1596                                        ON    9002
1597                                        ON    8001
1598                                        ON    8002
```

```
1599  4891  888 0 25  0050  4354          LDA  LC
1600  4354  888 0 70  4756  4380          ADD  BIG02     -PR1
1601  4381  888 0 60  0050  4554  &PR1    STA  LC
1602  4554  888 0 11  0417  4689          PRN  P0017     -PR2
1603  4380  888 0 60  0050  4754  -PR1    STA  LC
1604  4754  888 0 11  0401  4689          PRN  P0001     -PR2
1605  4690  888 0 00  0190  0190  &PR2    JMP  &CRD3
1606  4883  888 0 25  4770  4930  PRTSW   LDA  COMT      1F
1607  4735  888 0 25  4770  4930  PROF    LDA  COMT      1F
1608  4930  888 0 60  4779  4581  1       STA  CHOLD                 I92•ASSEMBLER 5
1609  4581  888 0 05  4733  4935          LDX  85
1610  4935  888 0 32  0500  4293          SHR   0500
1611  4293  888 0 37  0500  4251          SHL   0500
1612  4251  888 0 65  0503  4755          STX  P0103
1613  4755  888 0 60  0508  4180          STA  P0108
1614  4180  888 0 05  4405  4957          LDX  805
1615  4957  888 0 65  4770  4580          STX  COMT
1616  4580  888 0 25  4631  4933          LDA  TEMP1
1617  4933  888 0 30  4385  4337          LDL            ASM5
1618  4385  888 0 26  4938  4938          CLA                        I93•ASSEMBLER 5
1619  4938  888 0 20  4209  4780          BUF  TEMP2
1620  4780  888 0 30  4568  4337          LDL  EXIT2     ASM5
1621
```

```
1629                                                                                    I.  I95. ASSEMBLER 5
1632    4337  888 0 50  4464  4980      ASM5      STL  EXIT1      ASM5T
1633    4980  888 0 00  4181  0000      ASM5T     JMP  50001      0000
1634                                               OFF   9000
1688                                               ON    9000
1689                                               ON    9001
1690                                               ON    9002
1691    4181  888 0 60  0928  4781      50001     STA  R0128      1F          I95.STORE WORD
1692    4182  888 0 60  0948  4781      50002     STA  R0148      1F
1693    4183  888 0 60  0968  4781      50003     STA  R0168      1F          I96.END OF CARD
1694    4184  888 0 60  0918  4781      50004     STA  R0118      1F
1695    4185  888 0 60  0938  4781      50005     STA  R0138      1F
1696    4781  888 0 25  4980  4932      1         LDA  ASM5T
1697    4932  888 0 70  4097  4900                ADD  KON1       8F
1698    4900  888 0 60  4980  4464      8         STA  ASM5T      EXIT1
1699    4186  888 0 60  0958  4981      50006     STA  R0158      PCHS#
1700    4981  888 0 31  4484  4484      PCHS#     CLL  1F                     I97.CHECK CARD
1701    4651  888 0 31  4484  4484      PCHON     CLL  1F
1702    4484  888 0 08  1000  4537      1         LIR1  1000      2F
1703    4537  888 0 0G  9999  4341      2         IIR1  9999
1704    4341  888 0 82  4894  4344                TEQ  9F
1705    4344  888 0 22  4898  4537                RBT            2B
1706    4898  888 0 46  0800  4956                RBU  R0000
1707    4956  888 0 25  0911  4382                LDA  R0111
1708    4382  888 0 82  4894  4585                TEQ  9F
1709    4585  888 0 08  0000  4188                LIR1  0000
1710    4188  888 0 05  4890  4742                LDX            3F
1711    4890  888 0 08  9881  4493                LIR1  9881
1712    4493  888 0 05  4345  4297                LDX            2F
1713    4345  888 0 30  0872  4582                LDL  R0072
1714    4582  888 0 82  4894  4785                TEQ  9F
1715    4785  888 0 05  4737  0150                LDX            8U1
1716    4737  888 0 67  1112  4894                HLT   1112     9F
1717    4894  888 0 08  9997  4497      9         LIR1  9997                  I98.COMPUTE CHECK SUM.
1718    4497  888 0 05  4299  4742                LDX            3F
1719    4299  888 0 08  9987  4954                LIR1  9987
1720    4954  888 0 05  4558  4297                LDX            2F
1721    4558  888 0 60  0978  4782                STA  R0178      1F
1722    4782  888 0 81  0800  4758      1         RCC  R0000      -ASM5       I99.PUNCH
1723    4759  888 0 05  4982  0150      &ASM5     LDX            8U1
1724    4982  888 0 67  1111  4782                HLT   1111     18
1725    4758  888 0 25  0908  4383      -ASM5     LDA  RWD1
1726                                     PCHOF     EQU  -ASM5
1727    4383  888 0 70  4016  4583                ADD  LIT1
1728    4583  888 0 60  0908  4783                STA  RWD1
1729    4763  888 0 07  4181  4900                IIR  50001      8B
1730    4742  888 0 29  0911  4297      3         LDA1 R0111      2F
1731    4297  888 0 74  0931  4984      2         ADD1 R0131      -ASSM
1732    4985  888 0 74  0951  4958      &ASSM     ADD1 R0151      -ASSM
```

```
1733    4984   BBB J 74  0951  4958     -ASSM     ADD1 R0151     -ASSM
1734    4959   BBB J 74  0971  000C     &ASSM     ADD1 R0171     RX
1735    4958   BBB J 74  0971  000C     -ASSM     ADD1 R0171     RX
1736                                               ON    8001
1737                                               ON    8002
```

```
1738                                                                                    1.
1739   4084  888 0 25  0027  4983   FARNL    LDA  LEVEL                                 FIND AND RESERVE NEXT LOCATION
1740   4983  888 0 70  4336  4489            ADD  INCRE                                 IN PROGRAM INTERLACE
1741   4489  888 0 30  4541  4693            LDL  KN200                                 RX IS EXIT. RA GETS 02LLLL0000
1742   4693  888 0 82  4696  4896            TEQ  1F
1743   4896  888 0 87  4499  4955            TGR            2F     +05
1744   4499  888 0 75  0008  4955            SUB  RL        2F
1745   4955  888 0 60  0027  4684   2        STA  LEVEL
1746   4684  888 0 70  0231  000C            ADD  BAND      RX
1747   4696  888 0 70  0231  4884   1        ADD  BAND
1748   4884  888 0 60  0231  4134            STA  BAND
1749   4134  888 0 26  4955  4955            CLA  2B
1750   4686  888 0 50  4388  4340   FILUP    STL  -FIL2                                 FILL BLANK ADDRESSES IN PREV INSTRUCTION
1751   4340  888 0 77  4340  4893            ATL                                        RA # PLACE TO FILL WITH. FORM ORLLLL0000
1752   4893  888 0 25  4928  4334            LDA  RWORD                                 RL # EXIT LINE.
1753   4334  888 0 05  000A  4588            LDX  RA
1754   4588  888 0 37  0800  4699            SHL   0800
1755   4699  888 0 70  4301  4936            ADD  BIG90     -FIL1
1756   4937  888 0 07  HHHH  4540   &FIL1    IIR   HHHH
1757   4540  888 0 35  0008  4544            ERS  RL
1758   4544  888 0 20  4579  4534            BUF  IWORD
1759   4534  888 0 60  4579  4734            STA  IWORD
1760   4734  888 0 25  0008  4788            LDA  RL
1761   4788  888 0 35  4740  4942            ERS  X1
1762   4942  888 0 20  000C  4346            BUF  RX
1763   4346  888 0 35  4201  4359            ERS  XOM
1764   4359  888 0 60  4928  4936            STA  RWORD     -FIL1
1765   4936  888 0 25  0008  4940   -FIL1    LDA  RL
1766   4940  888 0 35  4617  4934            ERS  X0
1767   4934  888 0 32  0100  4988            SHR   0100
1768   4988  888 0 70  4301  4388            ADD  BIG90     -FIL2
1769   4389  888 0 20  4928  4384   &FIL2    BUF  RWORD
1770   4384  888 0 35  4201  4559            ERS  XOM
1771   4559  888 0 60  4928  4584            STA  RWORD
1772   4584  888 0 25  0008  4889            LDA  RL
1773   4889  888 0 32  0400  4546            SHR   0400
1774   4546  888 0 35  4724  4784            ERS  XC
1775   4784  888 0 20  4579  4536            BUF  IWORD
1776   4536  888 0 60  4579  4388            STA  IWORD     -FIL2
1777   4736  888 0 05  000A  4190   GOTO     LDX  RA                                    'GO TO' SUBROUTINE
1778   4190  888 0 25  4928  4386            LDA  RWORD                                 RX IS OR00000000. RL IS EXIT LINE.
1779   4386  888 0 37  0800  4697            SHL   0800                                 IF PREV INST HAS BLANK ADDRESS.MERELY FILUP.
1780   4697  888 0 70  4225  4586            ADD  BIG99     -GOTO
1781   4587  888 0 25  000C  4686   &GOTO    LDA  RX        FILUP
1782   4586  888 0 25  4880  4786   -GOTO    LDA  NXLOC                                 ELSE IF NXLOC IS NONZERO. ASSEMBLE A JMP
1783   4786  888 0 70  4201  4986            ADD  XOM       -GOT1                       INSTRUCTION
1784   4986  888 0 00  0008  0000   -GOT1    JMP  RL         0000
1785                              JMPRL    EQU  -GOT1
1786   4987  888 0 25  4740  4192   &GOT1    LDA  X1
```

```
1787    4192    888 J 35    000C    4746                ERS   RX
1788    4746    888 J 60    4624    4187                STA   TEMP4
1789    4187    888 J 75    000C    4776                SUB   RX          ASM31
1790    4927    888 J 30    4196    4148    INCUQ       LDL   UNIQU                 UNIQU TO RL
1791    4148    888 J 07    0001    4501                IIR    0001                 INCREMENT UNIQU BY 1
1792    4501    888 J 70    0008    4387                ADD   RL                    EXIT TO RX
1793    4387    888 J 60    4196    000C                STA   UNIQU       RX
```

```
1794  4744  888 0 65  4013  4787  ASIGN   STX  C0003                 I.  I50.  ASIGN SUBROUTINE
1801  4787  888 0 70  4603  4589          ADD  BIG60      -ASN4      I50.IS IT A TEMP
1802  4589  888 0 50  4014  4339  -ASN4   STL  C0004      1F
1803  4339  888 0 35  0043  4545  1       ERS  XM         ASGN1
1804  4545  888 0 30  4897  4641  ASGN1   LDL  6F         8R
1805  4897  888 0 60  4631  4539  6       STA  TEMP1                 I51.WHAT IS TABLE ENTRY
1806  4539  888 0 35  4741  4343          ERS  XMH
1807  4343  888 0 77  4343  4946          ATL
1808  4946  888 0 06  4899  4899          CLX
1809  4899  888 0 32  0400  4739          SHR   0400
1810  4739  888 0 70  4941  000A          ADD          RA
1811  4941  888 0 00  4010  0000          JMP  C0000    0000
1812  4019  888 0 37  0700  4939  C0009   SHL   0700
1813  4939  888 0 70  4191  4944          ADD  TEMP5
1814  4944  888 0 60  4191  4543          STA  TEMP5
1815  4543  888 0 25  4631  4189          LDA  TEMP1
1816  4189  888 0 37  0400  4339          SHL   0400     1B
1817  4590  888 0 60  4209  4789  &ASN4   STA  TEMP2      TRSW
1818  4789  888 0 05  000A  4743  TRSW    LDX  RA         1F
1819  4989  888 0 05  000A  4743  TRON    LDX  RA         1F
1820  4743  888 0 30  4745  4347  1       LDL  TROFF                 I52.REINSTATE TEMP
1821  4347  888 0 08  4701  4445          LIR1 TEMP5      INS
1822  4745  888 0 07  HHHH  4348  TROFF   IIR   HHHH
1823  4348  888 0 35  4209  4390          ERS  TEMP2
1824  4390  888 0 20  4408  4790          BUF  BIG01
1825  4790  888 0 08  1749  4943          LIR1 W9999
1826  4943  888 0 77  4943  4013          ATL              C0003
1827  4010  888 0 25  4631  4990  C0000   LDA  TEMP1
1828  4990  888 0 70  4392  4395          ADD  BIG70      -ASN1
1829  4396  888 0 07  HHHH  4349  &ASN1   IIR   HHHH
1830  4349  888 0 39  0001  4391          ERS1  0001      1F
1831  4395  888 0 07  0001  4391  -ASN1   IIR   0001      1F
1832  4391  888 0 30  4196  4548  1       LDL  UNIQU
1833  4548  888 0 70  0008  4591          ADD  RL
1834  4591  888 0 60  4196  4748          STA  UNIQU
1835  4748  888 0 25  4631  4791          LDA  TEMP1
1836  4791  888 0 20  0008  4945          BUF  RL
1837  4945  888 0 64  0000  4897          STA1  0000      6B
1838  4011  888 0 00  4013  4013  C0001   JMP  C0003
```

```
  1839                                                                  I.  I25. ASSEMBLER 2.
  1850   4950  888 0 60  4991  4193   ASM2     STA  TMP10                I25.ASSEMBLE 2.5 ON M
  1851   4193  888 0 50  4195  4547            STL  EXIT.
  1852   4547  888 0 35  4617  4592            ERS  X0
  1853   4592  888 0 60  4194  4596            STA  TEMP7
  1854   4596  888 0 30  4948  4550            LDL  1F
  1855   4550  888 0 25  4991  4393            LDA  TMP10     ASM25
  1856   4948  888 0 60  4750  4792   1        STA  TEMP8
  1857   4792  888 0 65  4394  4796            STX  TEMP9
  1858   4796  888 0 25  4991  4593            LDA  TMP10                I26.ASSEMBLE 2.5 ON C
  1859   4593  888 0 37  0400  4950            SHL   0400
- 1860   4950  888 0 30  4992  4393            LDL            ASM25
  1861   4992  888 0 77  4992  4595            ATL
  1862   4595  888 0 25  4394  4996            LDA  TEMP9                I27.ASSEMBLE 3
  1863   4996  888 0 37  0100  4901            SHL   0100
  1864   4901  888 0 20  000C  4793            BUF  RX
  1865   4793  888 0 60  4624  4993            STA  TEMP4
  1866   4993  888 0 25  0008  4747            LDA  RL
  1867   4747  888 0 32  0400  4594            SHR   0400
  1868   4594  888 0 35  4724  4794            ERS  XC
  1869   4794  888 0 20  4750  4994            BUF  TEMP8
- 1870   4994  888 0 30  4195  4776            LDL  EXIT.     ASM31
```

```
1871                                                                    I.  I30. ASSEMBLERS 2.5 AND 2.8
1872
1873
1875    4393  888 0 35  0043  4795    ASM25    ERS  XM                  I30.WHAT ADDRESS
1876    4795  888 0 60  4191  4995             STA  TEMP5
1877    4995  888 0 70  4947  4397             ADD                -HF1
1878    4947  888 0 99  0001  0000             CON  99000         10000
1879    4398  888 0 05  4016  4197    &HF1     LDX  LIT1          1F
1880    4397  888 0 70  4549  4597    -HF1     ADD                -HF2
1881    4549  888 0 00  0098  0000             CON  00009         80000
1882    4597  888 0 06  4351  4351    -HF2     CLX
1883    4351  888 0 25  4191  4197             LDA  TEMP5         1F
1884    4197  888 0 20  4194  0008    1        BUF  TEMP7         RL
1885    4598  888 0 50  4551  4797    &HF2     STL  EXIT5
1886    4797  888 0 77  4797  4751             ATL
1887    4751  888 0 25  4997  4749             LDA  1F
1888    4749  888 0 75  0008  000A             SUB  RL            RA      I31.WHAT KIND OF OPERAND
1889    4997  888 1 29  0000  4798    1        LDA3  0000         8F
1890    4798  888 0 77  4798  4951    9        ATL
1891    4951  888 0 32  0900  4998             SHR   0900
1892    4998  888 0 35  4413  4949             ERS  LIT8                  TREAT TEMP STORE(4) AS SIMPLE VAR(0)
-1893   4949  888 0 70  4199  000A             ADD                RA
1894    4199  888 0 25  0008  4080             LDA  RL            V0000
1895    4080  888 0 30  4195  4399    V0000    LDL  EXIT6
1896    4399  888 0 05  4194  4599             LDX  TEMP7         ASM28
1897    4081  888 0 30  4195  4799    V0001    LDL  EXIT6         EEE
-1898   4799  888 0 25  4999  4514    EEE      LDA                ALARM
1899    4999  888 0 21  0005  0000             CON  21000         50000       EXP #     ERROR
!1900   0042  888 0 25  0044  4514    BME      LDA                ALARM
1901    0044  888 0 03  0400  0000             CON  03040         00000       BAD MESS
!!1902  4082  888 0 25  0084  0886    V0002    LDA# 00057         67814
!!1903  0886  888 0 05  0288  0090             LDX  TMP13
!1904   0090  888 0 32  0600  0099             SHR   0600         LOOP1
!!1905  4085  888 0 30  0087  0089    V0005    LDL                LSW
!!1906  0087  888 0 05  0289  0291             LDX# 00200         00000
!1907   0291  888 0 35  0043  0245             ERS  XM
1908    0245  888 0 20  4194  4551             BUF  TEMP7         EXIT5
!!1909  4599  888 0 50  0201  0003    ASM28    STL  EXIT4                 I35.ASSIGN VARIABLE
!1910   0003  888 0 65  4191  0643             STX  TEMP5         9F
!!1911  0643  888 0 05  0445  0047    9        LDX  NPAR
!1912   0047  888 0 30  0049  4744             LDL                ASIGN
!1913   0049  888 0 09  0001  0203             LDX1  0001
!1914   0203  888 0 65  4770  0222             STX  COMT
!!1915  0222  888 0 50  0024  0426             STL  TEMP6                 I36.CHECK OP CODE
!1916   0426  888 0 30  4191  0843             LDL  TEMP5
!1917   0843  888 0 25  4247  0249             LDA  BIG30
!!1918  0249  888 0 82  1852  2052             TEQ  1F
!1919   2052  888 0 70  000A  0457             ADD  RA
!!1920  0457  888 0 82  0060  0260             TEQ  2F
```

```
 1921   0260  888 0 25  4604  0106                LDA  BIG25
 1922   0106  888 0 82  0109  0309                TEQ  3F
 1923   0309  888 0 70  000A  0314                ADD  RA
 1924   0314  888 0 82  0317  0517                TEQ  4F
 1925   0517  888 0 07  0001  0120                IIR   0001
 1926   0120  888 0 30  0322  0124                LDL            6F
 1927   0322  888 0 30  4986  0138                LDL  JMPRL     NPAR2
 1928   0060  888 0 30  0317  0319  2             LDL  4F        ATL
 1929   0319  888 0 25  0121  4556  ATL           LDA  BIG77     ASM32
 1930   0317  888 0 07  0002  0320  4             IIR   0002     5F
 1931   1852  888 0 07  0001  0320  1             IIR   0001     5F
 1932   0109  888 0 07  0000  0320  3             IIR   0000     5F
 1933   0320  888 0 30  0201  0124  5             LDL  EXIT4     6F
 1934   0124  888 0 74  0000  0403  6             ADD1  0000
 1935   0403  888 0 32  0400  0210                SHR   0400
 1936   0210  888 0 35  4724  0626                ERS  XC
 1937   0626  888 0 05  0028  0030                LDX# 00100     00010
 1938   0030  888 0 20  4623  4570                BUF  BIG05     ASM3
 1939   4015  888 0 30  0417  0219  C0005         LDL  FCEX
 1940   0219  888 0 25  4013  0065                LDA  C0003                    CHECK IF DOING A FUNCTION CALL.
 1941   0065  888 0 82  0068  0268                TEQ            1F
 1942   0068  888 0 05  000A  0072                LDX  RA        CASIN
 1943   0268  888 0 29  0001  0603  1             LDA1  0001                 I38.CHECK FOR ZERO
 1944   0603  888 0 31  0206  0206                CLL
 1945   0206  888 0 82  0809  1409                TEQ            1F
 1946   0809  888 0 30  0201  0803                LDL  EXIT4
 1947   0803  888 0 25  0005  0607                LDA  AREX
 1948   0607  888 0 82  0410  0610                TEQ  AREX1
 1949   0610  888 0 25  4191  1243                LDA  TEMP5
 1950   1243  888 0 70  4408  0261                ADD  BIG01
 1951   0261  888 0 05  0063  4570                LDX  LIT11     ASM3
 1952   1409  888 0 35  4667  0419  1             ERS  XOC                   I39.CHECK FOR IIR
 1953   0419  888 0 82  0422  0622                TEQ            1F
 1954   0422  888 0 25  4191  1643                LDA  TEMP5
 1955   1643  888 0 30  4604  0256                LDL  BIG25
 1956   0256  888 0 82  0259  0622                TEQ            1F
 1957   0259  888 0 29  0001  1403                LDA1  0001
 1958   1403  888 0 70  0805  0008                ADD  BIG07
 1959   0008  888 0 30  0201  4556                LDL  EXIT4     ASM32      I40.ASSIGN CONSTANT
 1960   0622  888 0 05  0224  0072  1             LDX            CASIN
 1961   0224  888 0 25  0826  0228                LDA            NPAR1
 1962   0826  888 0 12  2333  6523                ALF  CONST
 1963                                            OFF   8002
 1964                                            OFF   9002
 1965                                            HHH
 1966                                            ON    9002
 1967                                            ON    8002
 1968   0445  888 0 29  0001  0228  NPAR          LDA1  0001     NPAR1      I42.ASSEMBLE 3
 1969   0228  888 0 60  4770  0138  NPAR1         STA  COMT      NPAR2
 1970   0138  888 0 25  000B  0342  NPAR2         LDA  RL
```

```
1971  0342  888 0 35  4740  0592                ERS  X1
1972  0592  888 0 20  4016  0818                BUF  LIT1
1973  0818  888 0 60  4624  1626                STA  TEMP4
1974  1626  888 0 07  HHHH  0229                IIR   HHHH
1975  0229  888 0 35  0008  0433                ERS  RL
1976  0433  888 0 20  4191  1843                BUF  TEMP5
1977  1843  888 0 30  0201  4776                LDL  EXIT4      ASM31
1978  4083  888 0 30  0085  4303  V0003        LDL               BR1
1979  0065  888 0 09  0001  1603                LDX1  0001
1980  1603  888 0 65  1405  1407                STX  TMP11                  I44.GET SUBSCRIPT
1981  1407  888 0 37  0400  0814                SHL   0400
1982  0814  888 0 30  0216  4641                LDL               BR
1983  0216  888 0 09  0001  1803                LDX1  0001
1984  1803  888 0 65  1605  1607                STX  TMP12
1985  1607  888 0 60  4191  2043                STA  TEMP5
1986  2043  888 0 35  0645  0247                ERS  H1
1987  0247  888 0 30  4974  0276                LDL  BIG10
1988  0276  888 0 82  0005  0079                TEQ  AREX
1989  0079  888 0 05  0881  0283                LDX               CLACC
1990  0881  888 0 25  4191  0093                LDA  TEMP5
1991  0093  888 0 05  4604  0306                LDX  BIG25
1992  0306  888 0 30  0005  4599                LDL  AREX         ASM28
1993  0005  888 0 25  1405  1807  AREX         LDA  TMP11                  I45.WHAT KIND ARRAY
1994  1807  888 0 30  4336  0438                LDL  INCRE
1995  0438  888 0 06  1641  1641                CLX
1996  1641  888 0 65  2243  0845                STX  ACC
1997  0845  888 0 32  0900  0657                SHR   0900
1998  0657  888 0 70  0459  000A                ADD               RA
1999  0459  888 0 07  0007  4019                IIR   0007        C0009
2000  4020  888 0 82  1623  1823  C0010        TEQ  C0R10
2001  1823  888 0 05  0225  0427                LDX               1F          I46.PARAMETER CODE
2002  0225  888 0 00  0000  0070                CON  00000        00070
2003  0410  888 0 05  0212  0427  AREX1         LDX  2F           1F
2004  0212  888 0 00  0000  0025  2             CON  00000        00025
2005  0427  888 0 25  1405  2007  1             LDA  TMP11
2006  2007  888 0 37  0600  0416                SHL   0600
2007  0416  888 0 32  0200  0221                SHR   0200
2008  0221  888 0 30  2023  0425                LDL  3F           4F
2009  0425  888 0 05  0627  4709  4             LDX  1F           ASM34
2010  2023  888 0 30  0625  1627  3             LDL  8F           ADDNX
2011  1627  888 0 25  0429  0631  ADDNX         LDA# 70000        0000A
2012  0631  888 0 05  0633  4570                LDX  LIT10        ASM3
2013  0625  888 0 25  1405  2407  8             LDA  TMP11
2014  2407  888 0 35  4741  2443                ERS  XMH
2015  2443  888 0 06  1046  1046                CLX  7F
2016  1046  888 0 75  4623  0476  7             SUB  BIG05        AREX2
2017  0627  888 0 21  2127  1914  1             ALF  PARAM
2018  1623  888 0 30  0825  1827  C0R10         LDL               CORES
2019  0825  888 0 05  0212  1414                LDX  2B
2020  1414  888 0 32  0200  0419                SHR   0200
```

```
2021  0619  888 0 30  0421  0425          LDL  5F        46
2022  4021  888 0 82  0424  0624  C0011   TEQ  C0R11                 147•SAD CODE
2023  0624  888 0 25  1405  2607          LDA  TMP11
2024  2607  888 0 35  4741  2643          ERS  XMH
2025  2643  888 0 30  1245  4260          LDL            CONST
2026  1245  888 0 05  0447  0072          LDX            CASIN
2027  0447  888 0 25  0008  0251          LDA  RL
2028  0251  888 0 05  0253  0055          LDX  1F
2029  0055  888 0 30  1857  0659          LDL            7F
2030  1857  888 0 30  0859  1627          LDL            ADDNX
2031  0859  888 0 25  1405  2807          LDA  TMP11
2032  2807  888 0 37  0600  0616          SHL   0600
2033  0616  888 0 05  000A  0420          LDX  RA
2034  0420  888 0 32  0200  1625          SHR   0200
2035  1625  888 0 26  1046  1046          CLA  78
2036  0253  888 0 13  1116  4475  1       ALF  FUDGE
- 2037  0424  888 0 30  1826  1827  C0R11   LDL            CORES
2038  1826  888 0 20  0633  0235          BUF  LIT10
2039  0235  888 0 05  000A  0239          LDX  RA
2040  0239  888 0 32  0100  2843          SHR   0100
2041  2843  888 0 25  0805  3007          LDA  BIG07
2042  3007  888 0 30  0421  4570          LDL  5F        ASM3
2043  0421  888 0 25  2223  1825  5       LDA# 70000     C000A
2044  1825  888 0 06  0428  0428          CLX
2045  0428  888 0 30  0230  4570          LDL            ASM3
2046  0230  888 0 05  0032  4927          LDX            INCUQ
2047  0032  888 0 50  4880  0625          STL  NXLOC     8B
2048  0283  888 0 31  1886  1886  CLACC   CLL                          SUBROUTINE TO STORE A IN TEMP IF IT IS IN USE
2049  1886  888 0 25  2243  1645          LDA  ACC
2050  1645  888 0 82  000C  0248          TEQ  RX                      IN THE OBJECT PROGRAM
2051  0248  888 0 65  4926  0278          STX  EXIT3
2052  0278  888 0 05  0080  0082          LDX  2F
2053  0082  888 0 30  0284  2086          LDL  1F
2054  2086  888 0 08  4701  4229          LIR1 TEMPS     REM           IF TEMPS STACK IS EMPTY, RESERVE A NEW PLACE
2055  0080  888 0 05  0284  4927  2       LDX  1F        INCUQ         IN UNIQUE.
2056  0284  888 0 25  2243  1845  1       LDA  ACC
2057  1845  888 0 70  0647  000A          ADD            RA
2058  0647  888 0 08  0000  0453          LIR1  0000
2059  0453  888 0 29  0000  0602          LDA1  0000
2060  0602  888 0 35  4667  0819          ERS  X0C
2061  0819  888 0 06  1622  1622          CLX
2062  1622  888 0 65  2243  2045          STX  ACC
2063  2045  888 0 05  000A  0449          LDX  RA
2064  0449  888 0 07  HHHH  2252          IIR   HHHH
2065  2252  888 0 35  0008  0456          ERS  RL
2066  0456  888 0 77  0456  1859          ATL
2067  1859  888 0 20  000C  0263          BUF  RX
2068  0263  888 0 70  4247  0300          ADD  BIG30
2069  0300  888 0 64  0000  1402          STA1  0000
- 2070  1402  888 0 25  4603  0855          LDA  BIG60
```

```
2071  0855  888 0 20  000B  2059          BUF  RL
2072  2059  888 0 05  1750  0352          LDX  W0000
2073  0352  888 0 30  4926  4709          LDL  EXIT3     ASM34
2074  1827  888 0 50  0201  2003  CORES    STL  EXIT4                THIS SUBROUTINE PUTS OUT THE CORE ONLY
2075  2003  888 0 25  4196  0448          LDA  UNIQU                PAIR OF INSTRUCTIONS
2076  0448  888 0 30  0850  2452          LDL  3F
2077  2452  888 0 05  0254  0659          LDX  1F        7F
2078  0659  888 0 70  0461  4709  7       ADD  BIG69     ASM34
2079  0850  888 0 25  2652  0454  3       LDA# 05000     A0000
2080  0454  888 0 05  0656  0458          LDX  2F
2081  0458  888 0 30  0460  4760          LDL            ASM35
2082  0460  888 0 25  1405  0208          LDA  TMP11
2083  0208  888 0 37  0600  0201          SHL   0600     EXIT4
2084  0254  888 0 01  221F  3695  1       ALF  (CORE
2085  0656  888 0 22  2306  538C  2       ALF  ONLY)
2086  4022  888 0 30  0824  1627  C0012   LDL            ADDNX      I48.ORDINARY CODE
2087  0824  888 0 25  4740  0242          LDA  X1
2088  0242  888 0 35  1405  0408          ERS  TMP11
2089  0408  888 0 05  000A  0412          LDX  RA
2090  0412  888 0 07  HHHH  0215          IIR   HHHH
2091  0215  888 0 35  1405  0608          ERS  TMP11
2092  0608  888 0 77  0608  0411          ATL
2093  0411  888 0 25  1405  0808          LDA  TMP11
2094  0808  888 0 37  0600  0617          SHL   0600
2095  0617  888 0 32  0100  0621          SHR   0100
2096  0621  888 0 20  000B  0476          BUF  RL        AREX2
2097  0476  888 0 70  4194  0097  AREX2    ADD  TEMP7                I49.COMPILE OP
2098  0097  888 0 30  1605  1408          LDL  TMP12
2099  1408  888 0 50  4770  4551          STL  COMT      EXIT5
2101
```

```
2103  0089  888 0 06  0092  0092  LSW     CLX  1F                    I.  I60. LSW  FOR ASSIGNING STATEMENT LABELS.
2108  0108  888 0 06  0092  0092  LSWOF   CLX  1F                    I60.CHECK LABEL
2109  0509  888 0 05  0054  0092  LSWON   LDX  BIGO4      1F
2110  0092  888 0 50  456B  0520  1       STL  EXIT2
2111  0520  888 0 30  4277  0129          LDL  BIG50
2112  0129  888 0 87  0532  0732          TGR               1F
2113  0532  888 0 30  4603  0155          LDL  BIG60
2114  0155  888 0 87  0732  0158          TGR  1F           2F
2115  0732  888 0 25  0934  0336  1       LDA               NOMAL
2116  0934  888 0 03  1900  0000          CON  03190        00000       BAD LABEL
2117  0158  888 0 30  0360  4303  2       LDL               BR1         I61.IN DO LOOP
2118  0360  888 0 70  000C  0165          ADD  RX
2119  0165  888 0 32  0800  0176          SHR   0800
2120  0176  888 0 70  0178  000A          ADD               RA
2121  0178  888 0 29  0000  1230          LDA1  0000        L9950       I62.ASSIGN
2122  1280  888 0 05  0282  4084  LOOOO   LDX               FARNL
2123  0282  888 0 24  0000  1602          BUF1  0000
2124  1602  888 0 64  0000  1282          STA1  0000        LOOO2
2125  1281  888 0 06  0158  0158  LOOO1   CLX  2B
2126  1282  888 0 35  4741  4568  LOOO2   ERS  XMH          EXIT2
2127  1286  888 0 35  4201  0103  LOOO6   ERS  XOM          1F
2128  1284  888 0 35  4201  0103  LOOO4   ERS  XOM          1F          I64.TEMP ASSIGN
2129  0103  888 0 60  4209  0111  1       STA  TEMP2
2130  0111  888 0 05  0113  4084          LDX               FARNL
2131  0113  888 0 77  0113  0116          ATL
2132  0116  888 0 0G  0000  0720          IIR1  0000
2133  0720  888 0 32  0400  0527          SHR   0400
2134  0527  888 0 35  4724  0376          ERS  XC
2135  0376  888 0 20  4209  0611          BUF  TEMP2
2136  0611  888 0 0B  0415  1614          LIR1 LLIST
2137  1614  888 0 05  0008  1418          LDX  RL
2138  1418  888 0 30  0620  4445          LDL               IN5
2139  0620  888 0 25  000C  1624          LDA  RX
2140  1624  888 0 37  0400  0831          SHL   0400
2141  0831  888 0 30  0833  4303          LDL               BR1
2142  0833  888 0 35  0435  0237          ERS  XCO
2143  0237  888 0 20  0415  1417          BUF  LLIST
2144  1417  888 0 70  1419  1822          ADD  ONE15
2145  1822  888 0 64  0000  1285          STA1  0000        LOOO5
2146  1285  888 0 30  0287  4303  LOOO5   LDL               BR1
2147  0287  888 0 35  4741  0293          ERS  XMH
2148  0293  888 0 31  0296  0296          CLL
2149  0296  888 0 82  0899  1099          TEQ               1F
2150  0899  888 0 30  456B  0920          LDL  EXIT2
2151  0920  888 0 25  0522  0324          LDA  LABLX
2152  0324  888 0 82  0727  1099          TEQ               1F
2153  0727  888 0 29  9999  0401          LDA1  9999
2154  0401  888 0 35  4741  3043          ERS  XMH
2155  3043  888 0 24  0000  1802          BUF1  0000
```

```
2156    1802  888 0 64  0000  2002          STA1  0000    L8LX1
2157    1099  888 0 29  9999  1282    1     LDA1  9999    L0002
```

```
2158  0072  888 0 07  HHHH  0075      CASIN    IIR    HHHH                  I.  I70. CASIN  ASSIGNING CONSTANTS.
2159  0075  888 0 39  0000  2402               ERS1   0000                  I70.ALREADY ASSIGNED
2160  2402  888 0 31  1805  1805               CLL
2161  1805  888 0 82  1608  1808               TEQ                  1F
2162  1808  888 0 65  4926  0628               STX    EXIT3
2163  0628  888 0 07  HHHH  1231               IIR    HHHH                  I71.PICK UNIQUE
2164  1231  888 0 35  4196  0648               ERS    UNIQU
2165  0648  888 0 24  0000  2602               BUF1   0000
2166  2602  888 0 64  0000  2802               STA1   0000
2167  2802  888 0 09  0001  2403               LDX1   0001
2168  2403  888 0 65  4209  0811               STX    TEMP2                 I72.COMPILE CONSTANT
2169  0811  888 0 05  0413  4494               LDX                  ASM42
- 2170  0413  888 0 05  4926  4927               LDX    EXIT3         INCUQ
- 2171  1808  888 0 20  4408  0660      1        BUF    BIG01
  2172  0660  888 0 77  0660  000C               ATL                  RX
```

```
2173   0173  888 0 65  0175  0377    ASM1     STX  PAR2      ASM11       I.  I1.  ASSEMBLR 1
2174   0377  888 0 50  0379  0181    ASM11    STL  EXIT7     LOOP
2175   0181  888 0 06  0184  0184    LOOP     CLX
2176   0184  888 0 32  0800  0099             SHR   0800     LOOP1
2177   0099  888 0 65  0288  0290    LOOP1    STX  TMP13
2178   0290  888 0 37  0400  0297             SHL   0400
2179   0297  888 0 70  1299  000A             ADD           RA
2180   1299  888 0 05  1300  0717             LDX  10000     1F      +15
2181   0717  888 0 30  0519  0321    1        LDL           2F
2182   0519  888 0 05  1340  0542             LDX  10040     1F
2183   0321  888 0 87  0524  000C    2        TGR           RX
2184   0524  888 0 25  000C  0128             LDA  RX        TASM2
2185   0128  888 0 30  0130  4350    TASM2    LDL  IX        ASM2
2186   0130  888 0 25  0288  0181    IX       LDA  TMP13     LOOP
2187   1300  888 0 25  0175  0577    10000    LDA  PAR2
2188   0577  888 0 32  0500  0185             SHR   0500
2189   0185  888 0 35  0022  0379             ERS  X9        EXIT7
2190   1324  888 0 26  0379  0379    10024    CLA  EXIT7
2191                                                                 LIST OF INSTRUCTIONS
2192   1399  888 0 25  9901  9999    10099    LDA   9901      9999        LDA1
2193   1398  888 0 25  9902  9999    10098    LDA   9902      9999        LDA2
2194   1397  888 0 30  9901  9999    10097    LDL   9901      9999        LDL1
2195   1396  888 0 30  9902  9999    10096    LDL   9902      9999        LDL2
2196   1395  888 0 60  9901  9999    10095    STA   9901      9999        STA1
2197   1394  888 0 50  9901  9999    10094    STL   9901      9999        STL1
2198   1393  888 0 87  9905  9999    10093    TGR   9905      9999        TGR5
2199   1392  888 0 87  9903  9999    10092    TGR   9903      9999        TGR3
2200   1391  888 0 82  9904  9903    10091    TEQ   9904      9903        TEQ43
2201   1390  888 0 82  9904  9905    10090    TEQ   9904      9905        TEQ45
2202   1389  888 0 00  9902  9999    10089    JMP   9902      9999        JMP2
2203   1388  888 0 0G  0000  9999    10088    IIR1  0000      9999        IIR10
2204   1387  888 0 85  9901  9999    10087    MUL   9901      9999        MUL1
2205   1386  888 0 26  9999  9999    10086    CLA   9999      9999        CLA
2206   1385  888 0 75  9901  9999    10085    SUB   9901      9999        SUB1
2207   1384  888 0 75  000B  9999    10084    SUB   000B      9999        SUBRL
2208   1383  888 0 87  9905  9904    10083    TGR   9905      9904        TGR54
2209   1382  888 0 87  9903  9904    10082    TGR   9903      9904        TGR34
2210   1381  888 0 20  9901  9999    10081    BUF   9901      9999        BUF1
2211   1380  888 0 20  000B  9999    10080    BUF   000B      9999        BUFRL
2212   1379  888 0 60  9903  9999    10079    STA   9903      9999        STA3
2213   1378  888 0 70  9999  000A    10078    ADD   9999      000A        ADD0A
2214   1377  888 0 00  9999  0000    10077    JMP   9999      0000        JMP
2215   1376  888 0 25  000B  9999    10076    LDA   000B      9999        LDARL
2216   1375  888 0 0G  8888  9999    10075    II=1  8888      9999        IIR1N
2217   1374  888 0 30  9905  9999    10074    LDL   9905      9999        LDL5
2218   1302  888 0 25  0104  0506    10002    LDA  PAR1                        I1. CHECK SPECIAL CASES
2219   0506  888 0 30  1908  0510             LDL  COP
2220   0510  888 0 82  0521  0313             TEQ  2F     +08 3F
2221   1301  888 0 25  0104  0313    10001    LDA  PAR1        3F
```

```
2222  0313  888 0 30  0115  0917      3          LDL  C4#5
2223  0917  888 0 82  0521  0130                 TEQ  2F          IX
2224  0521  888 0 25  0123  0181      2          LDA               LOOP
2225  0143  888 0 98  0900  0000                 CON  98090       00000          LDA2 PO1
- 2226  1303  888 0 25  0104  0706      I0003      LDA  PAR1
2227  0706  888 0 30  0115  1917                 LDL  C4#5
2228  1917  888 0 82  0542  0130                 TEQ  1F          IX
2229  0542  888 0 25  0344  0181      1          LDA               LOOP
2230  0344  888 0 97  9811  0000                 CON  97981       10000          LDL1 LDA2 PORL
2231  1304  888 0 07  HHHH  0307      I0004      IIR   HHHH                      I4. CHECK SUBSCRIPT
2232  0307  888 1 39  0001  2603                 ERS3  0001
2233  2603  888 0 70  2005  000A                 ADD               RA
2234  2005  888 0 25  0000  3002                 LDA   0000
- 2235  3002  888 0 37  0400  1609                 SHL   0400
2236  1609  888 0 30  2243  2245                 LDL   ACC
2237  2245  888 0 82  0130  0848                 TEQ   IX
2238  0848  888 0 07  HHHH  0451                 IIR   HHHH
2239  0451  888 1 39  0000  2803                 ERS3  0000
2240  2803  888 0 70  2405  000A                 ADD               RA
2241  2405  888 0 25  0000  3003                 LDA   0000
2242  3003  888 0 37  0400  0810                 SHL   0400
2243  0810  888 0 82  0542  1303                 TEQ   1F          I0003
2244  1305  888 0 05  0130  0283      I0005      LDX   IX          CLACC          I5. CLEAR ACC
2248  1306  888 0 26  0709  0709      I0006      CLA                              I6. SET ACC AVAIL
2249  0709  888 0 60  2243  0130                 STA   ACC         IX
2252  1307  888 0 00  1300  1300      I0007      JMP   I0000                      I7. TRACE
2253                                   TRCSW      EQU   I0007
2254                                   TRCOF      EQU   I0000
2255  1855  888 0 25  4779  1881      TRCON      LDA   CHOLD
2256  1881  888 0 30  0483  4260                 LDL               CONST
2257  0483  888 0 05  0285  0072                 LDX               CASIN
2258  0285  888 0 25  0008  0489                 LDA   RL
2259  0489  888 0 70  0054  2057                 ADD   BIG04
2260  2057  888 0 05  2259  0661                 LDX   1F
2261  0661  888 0 30  0130  4709                 LDL   IX          ASM34
2262  2259  888 0 32  1113  9135      1          ALF   TRACE
2263  1308  888 0 25  0104  1906      I0008      LDA   PAR1                      I8. OP V2
2264  1906  888 0 05  1389  0191                 LDX   I0089       1F
2268  1309  888 0 05  0104  2106      I0009      LDX   PAR1                      I9. PO V1
2269  2106  888 0 25  0175  0777                 LDA   PAR2
2270  0777  888 0 32  0500  0385                 SHR    0500
2271  0385  888 0 60  0104  2306                 STA   PAR1
2272  2306  888 0 65  0175  0977                 STX   PAR2
2273  0977  888 0 32  0500  0585                 SHR    0500
2274  0585  888 0 05  0387  0191                 LDX               1F
2275  0387  888 0 00  9901  9999                 JMP    9901        9999
2276  0191  888 0 30  1908  0710      1          LDL   COP
2277  0710  888 0 82  0513  0713                 TEQ   3F
2278  0713  888 0 25  000C  2117                 LDA   RX
2279  2117  888 0 20  4247  0149                 BUF   BIG30
```

```
2280  0149  888 0 30  1310  4350          LDL  I0010     ASM2
2281  0513  888 0 25  0175  1177  3       LDA  PAR2
2282  1177  888 0 35  4617  1619          ERS  X0
2283  1619  888 0 20  000C  0128          BUF  RX        TASM2
2284  1310  888 0 25  0104  2506  I0010   LDA  PAR1      1F          I10.OP RL
2285  1311  888 0 05  0104  2706  I0011   LDX  PAR1                  I11.P0 RL
2286  2706  888 0 25  0175  1777          LDA  PAR2
2287  1777  888 0 32  0500  0785          SHR   0500
2288  0785  888 0 60  0104  2906          STA  PAR1
2289  2906  888 0 65  0175  2506          STX  PAR2      1F
2290  2506  888 0 35  0009  0181  1       ERS  H5        LOOP
2291  1312  888 0 05  0514  0513  I0012   LDX            3B          I12.OP RL NXT
2292  0514  888 0 00  000B  9999          JMP  RL         9999
2293  1313  888 0 25  0175  1977  I0013   LDA  PAR2                  I13.LIR3 NXT SUB
2294  1977  888 0 32  0400  0384          SHR   0400
2295  0384  888 0 30  0186  0188          LDL  1F        CALPK
2296  0188  888 0 50  0201  0004  CALPK    STL  EXIT4
2297  0004  888 0 35  0406  2008          ERS  X45
2298  2008  888 0 70  1410  000A          ADD            RA
2299  1410  888 0 08  0000  0816          LIR1  0000
2300  0816  888 0 34  1750  0552          LDL1 #0000
2301  0552  888 0 25  4628  0180          LDA  MZERO
2302  0180  888 0 24  1750  0752          BUF1 #0000
2303  0752  888 0 60  4770  0572          STA  COMT
2304  0572  888 0 82  0201  0375          TEQ  EXIT4
2305  0375  888 0 64  1750  0952          STA1 #0000
2306  0952  888 0 0G  0000  0556          IIR1  0000
2307  0956  888 0 05  0201  0204          LDX  EXIT4     SUBDF
2308  0186  888 0 25  0175  2177  1       LDA  PAR2
2309  2177  888 0 32  0600  0386          SHR   0600
2310  0386  888 0 30  0130  4970          LDL  IX        ASM36
2311  1314  888 0 25  4824  0126  I0014   LDA  DOVAR                  I14.STORE INTO RB1
2312  0126  888 0 70  0328  000A          ADD            RA
2313  0328  888 0 25  0001  0404          LDA   0001
2314  0404  888 0 60  4770  1323          STA  COMT      I0023
2315  1323  888 0 25  4528  0930  I0023   LDA  LIR1      TAS32
- 2316  0930  888 0 30  0130  4556  TAS32   LDL  IX        ASM32
2317  4528  888 0 08  0000  0000  LIR1    LIR1  0000      0000
2318  1315  888 0 25  4617  0719  I0015   LDA  X0                   I15.ATL CONDITIONALLY
2319  0719  888 0 35  4579  0331          ERS  IWORD
2320  0331  888 0 30  4528  0380          LDL  LIR1
2321  0380  888 0 82  0130  0183          TEQ  IX
2322  0183  888 0 30  0130  0319          LDL  IX        ATL
2323                                                     I16.SHIFT
2327  1318  888 0 25  0175  2377  I0018   LDA  PAR2                  I18.UNARY OPERATOR
2328  2377  888 0 37  0400  0584          SHL   0400
2329  0584  888 0 70  000A  0389          ADD  RA        -I18
2330  0390  888 0 05  0104  0507  &118    LDX  PAR1
2331  0507  888 0 32  0500  0315          SHR   0500     1F
2332  0389  888 0 25  0104  0315  -I18    LDA  PAR1      1F
```

```
2333  0315  888 0 31  0118  0118      1          CLL
2334  0118  888 0 82  0130  0721                 TEQ   IX
2335  0721  888 0 60  0175  1313                 STA   PAR2        I0013
2336  1319  888 0 05  1121  4084      I0019      LDX                FARNL      I19.GO TO 3F.2
2337  1121  888 0 60  0323  0125                 STA   THREF
2338  0125  888 0 30  0927  4736                 LDL   TOBSW       GOTO
2339  0927  888 0 05  0329  4084      TOBSW      LDX   1F          FARNL
2340  0140  888 0 05  0329  4084      TOB        LDX   1F          FARNL
2341  0329  888 0 60  0531  0733      1          STA   TWOB        2F
2342  0742  888 0 25  0544  0733      TOBIO      LDA   NINEF       2F
2343  0733  888 0 60  4880  0130      2          STA   NXLOC       IX
2344  1320  888 0 05  0722  4084      I0020      LDX                FARNL      I20.TGR 9F 3F
2345  0722  888 0 32  0400  0529                 SHR    0400
2346  0529  888 0 35  4724  0576                 ERS   XC
2347  0576  888 0 60  0544  0146                 STA   NINEF
2348  0146  888 0 37  0400  0153                 SHL    0400
2349  0153  888 0 20  0355  0357                 BUF   BIG87
2350  0357  888 0 05  0559  0161                 LDX#  02000       00001
2351  0161  888 0 30  0163  4570                 LDL                ASM3
2352  0163  888 0 25  0323  0925                 LDA   THREF
2353  0925  888 0 30  0130  0932                 LDL   IX          FILNX
2354  0932  888 0 60  4880  4686      FILNX      STA   NXLOC       FILUP
2355  1321  888 0 25  0544  0346      I0021      LDA   NINEF                  I21.NINEF DO
2356  0346  888 0 20  4408  0560                 BUF   BIG01
2357  0560  888 0 60  0544  0130                 STA   NINEF       IX
2358  1322  888 0 05  0724  4084      I0022      LDX                FARNL      I22.BUF       1F
2359  0724  888 0 60  0323  1125                 STA   THREF
2360  1125  888 0 32  0400  1132                 SHR    0400
2361  1132  888 0 35  4724  0776                 ERS   XC
2362  0776  888 0 20  1178  0580                 BUF   BIG20
2363  0580  888 0 05  0382  0784                 LDX#  00200       00010
2364  0784  888 0 30  0130  4570                 LDL   IX          ASM3
```

```
2365
2373  0373  BBB 1 29  0000  0604   ARITH   LDA3  0000
2374  0604  BBB 0 32  0400  1411           SHR   0400
2375  1411  BBB 0 35  0613  0615           ERS   KON3
2376  0615  BBB 0 77  0615  1618           ATL
2377  1618  BBB 0 70  000A  2423           ADD   RA
2378  2423  BBB 0 70  000B  0828           ADD   RL
2379  0828  BBB 0 77  0828  1631           ATL
2380  1631  BBB 1 29  9999  0601           LDA3  9999
- 2381  0601  BBB 0 32  0400  2408           SHR   0400
2382  2408  BBB 0 35  0613  0815           ERS   KON3
2383  0815  BBB 0 70  000B  0820           ADD   RL
2384  0820  BBB 0 70  2022  000A           ADD               RA
2385  2022  BBB 0 00  4000  4000           JMP   B0000
2386  4000  BBB 0 0G  0000  0654   B0000   IIR1  0000        2F
2387  4001  BBB 0 0G  0001  0654   B0001   IIR1  0001        2F
2388  4002  BBB 0 0G  0000  0654   B0002   IIR1  0000        2F
2389  4003  BBB 0 0G  0002  0654   B0003   IIR1  0002        2F
2390  4004  BBB 0 0G  0003  2608   B0004   IIR1  0003        1F
- 2391  4005  BBB 0 0G  0003  2608   B0005   IIR1  0003        1F
2392  4006  BBB 0 0G  0000  0654   B0006   IIR1  0000        2F
2393  4007  BBB 0 0G  0003  2608   B0007   IIR1  0003        1F
2394  4008  BBB 0 0G  0003  0612   B0008   IIR1  0003
2395  0612  BBB 0 05  4756  0658           LDX   BIG02       4F
-- 2396  2608  BBB 0 05  4408  0658   1       LDX   BIG01       4F
2397  0654  BBB 0 06  0658  0658   2       CLX   4F
2398  0658  BBB 0 65  0860  000A   4       STX   OTYPE       RA
2399  0199  BBB 0 05  0801  0804   BINSB   LDX   CSUB        1F
2400  0800  BBB 0 05  1908  0804   BINOP   LDX   COP         1F
2401  0804  BBB 0 30  4215  1617   1       LDL   OPX         BINAL
2402  1617  BBB 0 50  1819  0821   BINAL   STL   &SAC
2403  0821  BBB 0 65  0104  0707           STX   PAR1
2404  0707  BBB 1 29  0000  1404           LDA3  0000
2405  1404  BBB 0 05  000A  2808           LDX   RA
2406  2808  BBB 0 35  4247  0649           ERS   BIG30
2407  0649  BBB 0 32  0F00  0062           SHR   0F00
2408  0062  BBB 0 35  0022  1824           ERS   X9
2409  1824  BBB 0 70  000A  0629           ADD   RA
2410  0629  BBB 0 77  0629  0232           ATL
2411  0232  BBB 0 25  0234  0436           LDA#  80000       0000H
2412  0436  BBB 1 39  9999  1401           ERS3  9999
2413  1401  BBB 0 70  0008  0606           ADD   RL
2414  0606  BBB 0 70  000A  1611           ADD   RA          -BM
2415  1612  BBB 0 30  1814  0042   &BM     LDL   ANSL        BME
2416  1611  BBB 0 77  1611  2014   -BM     ATL
2417  2014  BBB 0 37  0300  1620           SHL   0300
2418  1620  BBB 0 70  2222  000A           ADD               RA
2419  2222  BBB 0 0G  0000  0829           IIR1  0000
2420  0829  BBB 1 0G  9999  1233           IIR3  9999
```

B. ARITHMETIC OPERATORS
ARITH SUBROUTINE
DECIDES WHETHER WE HAVE FLT-FLT, FLT-FIX, FIX-FLT, OR FIX-FIX ON BINARY OPERATORS AND ALSO DETERMINES TYPE OF RESULT.

BINSB GENERATES REFERENCE TO BINARY SUBROUTINE. BINOP IS FOR BINARY MACHINE OP. RB1 IS THE Q-TABLE ENTRY FOR THE ++ CASE.

PICK UP THE PROPER J TABLE ENTRY -- SEE THE J-TABLE, J0000 THRU J0015.

```
2421  1233  888 0 25  0008  0437          LDA  RL
2422  0437  888 0 35  4617  0069          ERS  X0
2423  0069  888 0 32  0500  0077          SHR   0500
2424  0077  888 0 70  000A  0482          ADD  RA
2425  0482  888 0 70  000C  0487          ADD  RX
2426  0487  888 0 70  0689  000A          ADD            RA
2427  0689  888 0 25  1700  0302          LDA  J0000
2428  0302  888 0 09  0000  1604          LDX1  0000     7F
2429  1604  888 0 30  0806  0173  7       LDL            ASM1
2430  0806  888 0 70  0860  0463          ADD  OTYPE     SACC
2431  0463  888 0 70  4974  1818  SACC    ADD  BIG10     -SAC      MARK COMPUTER RESULT AS IN ACCUMULATOR
2432  1818  888 1 64  0000  1804  -SAC    STA3  0000               UNLESS TYPE IS 9 (FOR STORE OPERATORS).
2433  1804  888 1 0G  0000  3008          IIR3  0000
2434  3008  888 0 60  2243  1819          STA  ACC       &SAC
2435  1814  888 1 0G  0000  2018  ANSL    IIR3  0000               ANSL MEANS  L #  L OP R
2436  2018  888 0 30  2243  2445          LDL  ACC
2437  2445  888 0 82  1048  1248          TEQ            DOCK3
2438  1048  888 0 31  0651  0651          CLL
2439  0651  888 0 50  2243  1248          STL  ACC       DOCK3
2440  1248  888 1 0G  9999  4215  DOCK3   IIR3  9999     OPX
2441  1841  888 0 30  4215  0067  UNOP    LDL  OPX       1F        UNOP ENTRIES ARE STANDARD OPTIONS FOR
2442  0442  888 0 25  4301  0653  UNOP3   LDA  BIG90               UNARY OPERATORS
2443  0653  888 0 60  0860  0067          STA  OTYPE     1F
2444  0067  888 1 29  0000  2004  1       LDA3  0000     UNOP1
2445  2645  888 0 35  0009  1811  UNOP2   ERS  H5        1F
2446  2004  888 0 50  1819  1811  UNOP1   STL  &SAC      1F
2447  1811  888 0 65  0104  0907  1       STX  PAR1
2448  0907  888 0 32  0500  0515          SHR   0500
2449  0515  888 0 35  0613  1415          ERS  KON3
2450  1415  888 0 70  1817  000A          ADD            RA
2451  1817  888 0 29  0000  1604          LDA1  0000     7B             SELECT J-TABLE ENTRY.
2452  4104  888 0 25  1907  0909  SIGN-   LDA  TWO9S                 81. MINUS SIGN
2453  0909  888 0 70  000C  0714          ADD  RX        -L1
2455  0715  888 0 05  2317  4428  &L1     LDX  OUN-      -OP3
2456  0714  888 0 30  0316  4211  -L1     LDL  OBIN-     -OP4
2458  4105  888 0 25  1907  1909  SIGN&   LDA  TWO9S                 83. PLUS SIGN.
2459  1909  888 0 70  000C  0914          ADD  RX        -L2
2460  0915  888 0 00  4140  4140  &L2     JMP  NORMX
2462  0914  888 0 30  1052  4211  -L2     LDL  OBIN&     -OP4
2463  4103  888 0 25  4417  0919  BIN-    LDA  RATOR               84. SUBTRACTION OP
2464  0919  888 0 70  1921  000A          ADD            RA
2465  1921  888 0 30  0001  2404          LDL   0001
2466  2404  888 0 25  1406  1809          LDA  OIF%
2467  1809  888 0 82  1412  1812          TEQ            1F
2468  1412  888 0 30  4213  0265          LDL  OHOLD
2469  0265  888 0 25  4392  0094          LDA  BIG70
2470  0094  888 0 82  0497  1812          TEQ            1F
2471  0497  888 1 29  0000  2604          LDA3  0000
2472  2604  888 0 37  0900  1416          SHL   0900
2473  1416  888 0 77  1416  2019          ATL
```

```
2474  2019  888 1 29  9999  1601          LDA3  9999
2475  1601  888 0 37  0900  0813          SHL   0900
2476  0813  888 0 82  1616  1812          TEQ               1F
2477  1616  888 0 30  2218  4426          LDL   COLON       REMRT
2478  1812  888 1 29  0000  2804  1       LDA3  0000
2479  2804  888 0 70  4424  2027          ADD   LIT5
2480  2027  888 1 64  0000  4106          STA3  0000        BIN&
2481  4102  888 1 29  0000  3004  UN-     LDA3  0000                  8o. NEGATION OP
2482  3004  888 0 70  4424  2227          ADD   LIT5
2483  2227  888 1 64  0000  4215          STA3  0000        OPX
2484  4106  888 0 08  1100  0373  BIN&    LIR1  A0000       ARITH       88. ADDITION OP
2485  1100  888 0 08  1000  0199  A0000   LIR1  Q0000       BINS8
2486  1101  888 0 25  1903  0305  A0001   LDA               BINER
2487  1903  888 0 07  0500  0000          CON   07050       00000           I&A ERR
- 2488  1102  888 0 25  0304  0305  A0002   LDA               BINER
2489  0304  888 0 06  0500  0000          CON   06050       00000           A&I ERR
- 2490  0305  888 0 30  1814  4514  BINER   LDL   ANSL        ALARM
2491  1103  888 0 25  4417  1919  A0003   LDA   RATOR
2492  1919  888 0 70  2121  000A          ADD               RA
2493  2121  888 0 25  0001  2605          LDA   0001
2494  2605  888 0 30  2009  2011          LDL   0ARA%
2495  2011  888 0 82  2214  2414          TEQ   2F
2496  2414  888 0 30  1816  2418          LDL   0ARA*
2497  2418  888 0 82  2214  2421          TEQ   2F          -ADD
2498  2421  888 1 29  9999  1801  -ADD    LDA3  9999
2499  1801  888 0 30  1051  0853          LDL   CONO
2500  0853  888 0 82  0856  1056          TEQ   ANSR
2501  1056  888 0 08  1030  0800          LIR1  Q0030       BINOP
2502  0856  888 1 29  0000  2805  ANSR    LDA3  0000                  ANSR MEANS   R EQUALS  L OP R
2503  2805  888 1 64  9999  2001          STA3  9999
2504  2001  888 1 0G  0000  3005          IIR3  0000
2505  3005  888 0 30  2243  2845          LDL   ACC
2506  2845  888 0 82  1648  1248          TEQ               DOCK3
2507  1648  888 1 0G  9999  2852          IIR3  9999
2508  2852  888 0 60  2243  4215          STA   ACC         OPX
2509  2214  888 1 29  0000  1606  2       LDA3  0000
2510  1606  888 0 06  2409  2409          CLX
2511  2409  888 0 32  0100  1413          SHR   0100
2512  1413  888 0 37  0700  2623          SHL   0700
2513  2623  888 0 70  000A  2421          ADD   RA          -ADD
2514  2422  888 0 07  HHHH  2025  &ADD     IIR   HHHH
2515  2025  888 1 39  0000  1806          ERS3  0000
2516  1806  888 0 70  2609  000A          ADD               RA
2517  2609  888 0 30  0001  2006          LDL   0001
2518  2006  888 0 26  2809  2809          CLA
2519  2809  888 0 75  000C  2614          SUB   RX
2520  2614  888 0 36  2017  2017          CAA
2521  2017  888 0 20  000B  1621          BUF   RL
2522  1621  888 0 77  1621  2024          ATL
2523  2024  888 0 25  4095  1047          LDA   KON2
```

```
2524   1047  BBB 0 87  1850  2050          TGR  1F
2525   2050  BBB 1 25  9999  2401          LDA2 9999
2526   2401  BBB 0 20  4424  2026          BUF  LIT5
2527   2026  BBB 1 60  9999  1850          STA2 9999      1F
2528   1850  BBB 1 85  9998  0275  1       MUL2 9998
2529   0275  BBB 1 25  9999  2601          LDA2 9999
2530   2601  BBB 0 70  000C  2406          ADD  RX
2531   2406  BBB 1 60  9999  1814          STA2 9999      ANSL
2532                                       HHH
2533   4111  BBB 0 30  1913  4044  SIGN*    LDL            SCAN      B11.ASTERISK
2534   1913  BBB 0 30  1915  2517          LDL  0*
2535   2517  BBB 0 82  1120  2120          TEQ  SGN**     &FNC1
2536   2120  BBB 0 07  1054  4710  &FNC1    IIR  T0004     DIVT2
2537   4112  BBB 0 08  1104  0373  BIN*     LIR1 A0004     ARITH     B12.MULTIPLY
2538   1104  BBB 0 08  1004  0199  A0004    LIR1 Q0004     BINSB
2539   1105  BBB 0 25  2107  0305  A0005    LDA            BINER
2540   2107  BBB 0 11  1310  0905          CON  11131     00905          FLOATING SUBSCRIPT OR I*A ERROR
2541   1106  BBB 0 25  2108  0305  A0006    LDA            BINER
2542   2108  BBB 0 08  0500  0000          CON  08050     00000          A*I ERR
2543   1107  BBB 1 29  0000  2606  A0007    LDA3 0000
2544   2606  BBB 0 30  1051  1853          LDL  CON0
2545   1853  BBB 0 82  0856  1856          TEQ  ANSR      KON*E
2547   4101  BBB 0 05  2103  4428  SIGN%    LDX  OLPRN     -OP3      B15.LEFT PARENTHESIS
2548   4113  BBB 0 07  HHHH  0516  SIGN.    IIR  HHHH
2549   0516  BBB 1 35  0000  000A          ERS2 0000      RA
2550   4114  BBB 1 25  0000  2806  SIGN$    LDA2 0000
2551   2806  BBB 0 35  4724  2226          ERS  XC
2554   2226  BBB 0 37  0400  000A          SHL  0400      RA
2555   4115  BBB 0 08  1108  0373  SIGN/    LIR1 A0008     ARITH     B18.DIVISION
2556   1108  BBB 0 08  1008  0199  A0008    LIR1 Q0008     BINSB
2557   1109  BBB 0 25  0311  0305  A0009    LDA            BINER
2558   0311  BBB 0 16  0500  0000          CON  16050     00000          I/A ERR
2559   1110  BBB 0 25  0312  0305  A0010    LDA            BINER
2560   0312  BBB 0 15  0500  0000          CON  15050     00000          A/I ERR
2561   1111  BBB 0 08  1012  0199  A0011    LIR1 Q0012     BINSB
2562   1120  BBB 0 05  0922  4428  SGN**    LDX  OBN**     -OP3
2563   4116  BBB 0 08  1112  0373  BIN**    LIR1 A0012     ARITH     B20.EXPONENTIATION
2564   1112  BBB 0 08  1016  0199  A0012    LIR1 Q0016     BINSB
2565   1113  BBB 0 25  2115  0305  A0013    LDA            BINER
2566   2115  BBB 0 17  0500  0000          CON  17050     00000          I**A ERR
2567   1114  BBB 0 08  1020  2717  A0014    LIR1 Q0020     1F
- 2568   1115  BBB 0 08  1025  2717  A0015    LIR1 Q0025     1F
2569   2717  BBB 1 29  0000  3006  1        LDA3 0000
2570   3006  BBB 0 30  3009  2411          LDL  CON2
2571   2411  BBB 0 82  2814  0199          TEQ  SQUAR     BINSB
2572   4162  BBB 0 08  1038  0965  BLAND    LIR1 Q0038     1F        B22.AND,OR
- 2573   4163  BBB 0 08  1042  0965  BOR      LIR1 Q0042     1F
2574   0965  BBB 0 05  4756  1610  1        LDX  BIG02
2575   1610  BBB 0 65  0860  0800          STX  OTYPE     BINOP
2576   4107  BBB 0 30  2109  4044  WDIF     LDL            SCAN      B25.WORD IF
```

```
2577  2109  888 0 30  4221  0523          LDL  LPREN
2578  0523  888 0 82  0326  0526          TEQ                MLP
2579  0326  888 0 05  1406  4428          LDX  OIF%          -OP3
2580  4108  888 1 0G  0001  0512  IF%     IIR3  0001                          826.IF-LEFT-PAREN
2581  0512  888 0 30  1051  2053          LDL  CON0
2582  2053  888 1 54  0000  2218          STL3  0000         COLON
2583  2218  888 1 07  0001  2622  COLON    IIR2  0001
2584  2622  888 0 25  2224  2426          LDA  IFMD
2585  2426  888 1 60  0000  1810          STA2  0000         EXPL            827.FINISH IF-STATEMENT
2586  1810  888 0 30  4140  0642  EXPL     LDL  NORMX         EXPL8
2587  0642  888 0 25  0244  1246  EXPL8    LDA  LEXP
2588  1246  888 0 60  4206  000B          STA  LES#          RL
2589  0589  888 0 30  1810  2012  IF.      LDL  EXPL          DOIF
2590  2012  888 1 25  0000  2010  DOIF     LDA2  0000
2591  2010  888 0 70  2212  2015          ADD  BIG40         -IF1
2592  2016  888 0 25  2618  0336  &IF1     LDA                NOMAL
2593  2618  888 0 18  0020  0000          CON  18002         00000                EXTRA COMMA
2594  2015  888 1 60  0000  000B  -IF1     STA2  0000         RL
2595  0195  888 1 25  0000  2410  IF$      LDA2  0000
2596  2410  888 0 70  2212  2215          ADD  BIG40         -IF2
2597  2215  888 0 30  2216  2818  -IF2     LDL  &IF2          MCAL
2598  2818  888 0 25  1820  4514  MCAL     LDA                ALARM
2599  1820  888 0 32  2000  0000          CON  32200         00000                MISSING COMMA
2600  2216  888 1 29  9996  0198  &IF2     LDA3  9996
2601  0198  888 0 37  0900  2610          SHL  0900
2602  2610  888 0 70  000A  2415          ADD  RA            -IF3
2603  2416  888 1 34  0000  3052  &IF3     LDL3  0000                 +50
2604  3052  888 1 29  9998  2250          LDA3  9998                 +50
2605  2250  888 1 64  0000  2253          STA3  0000                 +50
2606  2253  888 1 54  9998  2810          STL3  9998         1F      +02
2607  2415  888 1 29  0000  2810  -IF3     LDA3  0000         1F
2608  2810  888 1 34  9999  2801  1       LDL3  9999
2609  2801  888 0 82  3010  2611          TEQ  5F
2610  2611  888 1 34  9998  1400          LDL3  9998
2611  1400  888 0 82  2811  3011          TEQ  3F
2612  3011  888 1 29  9999  3001          LDA3  9999
2613  3001  888 0 82  2412  2612          TEQ  4F
2614  2612  888 0 05  3014  2616          LDX  C345          1F
2615  2412  888 0 05  1615  2616  4       LDX  C3#4          1F
2616  2811  888 0 05  1613  2616  3       LDX  C3#5          1F
2617  3010  888 0 05  0115  2616  5       LDX  C4#5          1F
2618  2616  888 1 0G  9997  2020  1       IIR3  9997
2619  2020  888 0 30  2822  1617          LDL  D1M$          BINAL
2620  2220  888 0 30  3022  2424  UAS#     LDL  DUA           1F
2621  1821  888 0 30  3022  2424  MISUB    LDL  DUA           1F
2622  2424  888 0 25  2626  1628  1       LDA                PANIC
2623  2626  888 0 32  1300  0000          CON  32130         00000                MISSING SUBSCRIPT
2624  0526  888 0 60  4834  0536  MLP     STA  DSAVE         1F
2625  0536  888 0 30  033B  0340  1       LDL  1F
2626  0340  888 0 25  0942  4514          LDA                ALARM
```

```
2627    0942  888 0 32  2425  0000                CON   32242   50000      MISSING LEFT PARENTHESIS
2628    0938  888 0 07  1066  4698   1            IIR   T0016   DIVRT
2629    1629  888 0 30  1831  1633   MRP          LDL   1F
2630    1633  888 0 25  0635  4514                LDA           ALARM
2631    0635  888 0 32  2200  2500                CON   32220   02500      MISSING RIGHT     PARENTHESIS
2632    1831  888 0 07  1063  4698   1            IIR   T0013   DIVRT
2633                                 BINOP                    889.GENERATE MACHINE OP
2643                                 BINSB                    890.GENERATE LIBRARY REF
```

```
2652  4217  888 0 30  2219  4044   ARRAY   LDL              SCAN       A.  PROCESSING OF ARRAY SUBSCRIPTS
2653  2219  888 0 30  4221  2823           LDL  LPREN
2654  2823  888 0 82  2826  2220           TEQ              UASW
2655  2826  888 0 07  1050  4086           IIR  T0000       DIVT1
2656  4110  888 0 07  HHHH  2113   TARA%   IIR   HHHH                  A1. IS LEFT PAREN NEXT
2657  2113  888 1 39  0000  2812           ERS3  0000
2658  2812  888 1 60  0001  3012           STA2  0001
2659  3012  888 0 25  4016  3018           LDA  LIT1
2660  3018  888 1 60  0002  1813           STA2  0002
2661  1813  888 0 25  1815  2217           LDA  FOR9S
2663  2217  888 1 60  0003  2013           STA2  0003
2664  2013  888 0 30  2615  2417           LDL  ARAMD                  A2. SET ARRAY MODE
2665  2417  888 0 05  2009  4235           LDX  0ARA%       MDOP
2672                                                                  A3. EMIT % 0 +
2678  0478  888 1 29  0000  2213   INDEX   LDA3  0000                  A10.CHECK INDEX.
2679  2213  888 0 30  4431  1833           LDL  BIG21
2680  1833  888 0 82  0636  000C           TEQ              RX
2681  0636  888 1 30  9999  2413           LDL2  9999
2682  2413  888 0 25  2815  2617           LDA#  04997      00000
2683  2617  888 0 87  000C  2420           TGR  RX
2684  2420  888 0 25  3023  2225           LDA  XMC
2685  2225  888 1 35  9996  0398           ERS2  9996
2686  0398  888 0 30  1600  2613           LDL  FCMD
2687  2613  888 0 82  000C  2816           TEQ  RX
2688  2816  888 1 25  9999  2813           LDA2  9999
2689  2813  888 0 20  3015  2817           BUF#  00000      04000
2690  2817  888 1 60  9999  3013           STA2  9999
2691  3013  888 0 25  1051  2453           LDA  CONO
2692  2453  888 1 64  0000  000C           STA3  0000       RX
2693  0493  888 1 25  9999  3016   PNSUB   LDA2  9999                  A11.POTENTIAL NEGATIVITY
2694  3016  888 0 37  0900  1828           SHL   0900
2695  1828  888 0 70  000A  2033           ADD  RA          -PN
2696  2034  888 0 30  1051  2653   &PN     LDL  CONO
2697  2653  888 1 29  0000  3017           LDA3  0000
2698  3017  888 0 82  2620  2820           TEQ  2F
2699  2820  888 0 30  4431  2233           LDL  BIG21
2700  2233  888 0 82  2620  0836           TEQ  2F
2701  0836  888 0 25  4016  0468           LDA  LIT1
2702  0468  888 1 20  9999  2419           BUF2  9999       1F
2703  2620  888 1 25  9999  2419   2       LDA2  9999       1F
2704  2419  888 0 35  2021  2624   1       ERS#  HHHHH      HHHHC
2705  2624  888 1 60  9999  000C           STA2  9999       RX
2706  2033  888 0 00  000C  000C   -PN     JMP  RX
2707  2307  888 0 25  4417  2319   ARA.    LDA  RATOR
2708  2319  888 0 70  2321  000A           ADD              RA
2709  2321  888 0 30  0001  2619           LDL   0001
2710  2619  888 0 25  2009  2819           LDA  0ARA%
2711  2819  888 0 82  2824  3024           TEQ              1F      +02
2712  2824  888 0 05  3024  0478           LDX  1F          INDEX
```

```
2713  3024  888 0 05  3026  0493  1        LDX          PNSUB
2714  3026  888 0 07  0001  1829           IIR   0001                 A12.ADJUST MULTIPLIER
2715  1829  888 1 70  9997  1800           ADD2  9997
2716  1800  888 1 60  9997  0399           STA2  9997
2717  0399  888 0 70  3019  000A           ADD          RA
2718  3019  888 0 25  0001  3020           LDA   0001
2719  3020  888 0 77  3020  2425           ATL
2720  2425  888 0 35  0043  3045           ERS   XM
2721  3045  888 0 82  1848  2048           TEQ   1F
2722  2048  888 0 30  2450  2853           LDL   2F
2723  2853  888 0 25  2055  4514           LDA          ALARM
2724  2055  888 0 18  0013  0000           CON   18001  30000          EXTRA SUBSCRIPT
2725  1848  888 0 20  2650  3053  1        BUF#  01000  05000  A13.EMIT  + N ( 0 +
2726  3053  888 0 60  1058  1260           STA   T0008
2727  1260  888 0 25  0008  0064           LDA   RL
2728  0064  888 0 70  0266  000A           ADD          RA
2729  0266  888 0 30  0001  2221           LDL   0001
2730  2221  888 1 85  9998  0475           MUL2  9998
2731  0475  888 0 30  000C  0279           LDL   RX
2732  0279  888 0 32  0400  2286           SHR   0400
2733  2286  888 1 65  9998  2000           STX2  9998
2734  2000  888 1 25  9999  2621           LDA2  9999
2735  2621  888 0 75  000B  2427           SUB   RL
2736  2427  888 1 60  9999  2450           STA2  9999   2F
2737  2450  888 0 07  1057  4698  2        IIR   T0007  DIVRT
2738  0538  888 0 05  4112  0493  ARA*     LDX   BIN*   PNSUB
2739  1139  888 0 05  0541  0478  ARA*     LDX          INDEX          A20.INDEXING.NEGATIVITY
2740  0541  888 0 05  0143  0493           LDX          PNSUB
2741  0143  888 1 29  0000  2821           LDA3  0000
2742  2821  888 0 35  4740  1242           ERS   X1
2743  1242  888 0 70  4225  0678           ADD   BIG99  -CHFL
- 2744  0678  888 0 30  0679  2081  -CHFL    LDL   &CHFL                 A21.CHECK FIXED POINT
2745  2081  888 0 25  0683  4514           LDA          ALARM
2746  0683  888 0 11  1300  0000           CON   11130  00000          FLOATING SUBSCRIPT
2747  0679  888 0 05  2281  0883  &CHFL    LDX   1F     MAGET          A22.COMPUTE SUBSCRIPT
2748  0883  888 1 29  0000  3021  MAGET    LDA3  0000
2749  3021  888 0 35  2625  2627           ERS#  C0000  00005
2750  2627  888 0 77  2627  0430           ATL
2751  0430  888 0 37  0900  1642           SHL   0900
2752  1642  888 0 20  0008  1646           BUF   RL
2753  1646  888 0 70  0355  0758           ADD   BIG87  -MAG
2754  0759  888 0 30  000C  0363  &MAG      LDL   RX     GET
2755  0758  888 0 00  000C  000C  -MAG      JMP   RX
2756  2281  888 1 25  9996  0598  1        LDA2  9996                   A23.EQUIVALENCE DECL.
2757  0598  888 0 30  2400  2825           LDL   EQUMD
2758  2825  888 0 82  2028  2228           TEQ   AEQU
2759  2228  888 1 29  9999  3025           LDA3  9999
2760  3025  888 0 30  2827  2029           LDL   7F                     A24.WHAT TYPE ARRAY
2761  2029  888 0 05  2031  4744           LDX          ASIGN
2762  2031  888 0 07  HHHH  3434           IIR   HHHH
```

```
2763  0434  888 0 35  0008  0638          ERS  RL
2764  0638  888 1 70  9999  3027          ADD2  9999
2765  3027  888 1 60  9999  2428          STA2  9999
2766  2428  888 0 25  0008  0432          LDA  RL
2767  0432  888 0 35  4740  1842          ERS  X1
2768  1842  888 0 60  4209  0861          STA  TEMP2
2769  0861  888 0 06  0264  0264          CLX
2770  0264  888 0 32  0400  0271          SHR   0400
2771  0271  888 0 70  0273  000A          ADD              RA
2772  0273  888 0 30  4195  0697          LDL  STORE
2773  0697  888 1 25  9999  2628          LDA2  9999
2774  2628  888 0 75  4623  0676          SUB  BIG05
2775  0676  888 0 70  4209  0712          ADD  TEMP2
2776  0712  888 0 87  2315  2515          TGR  6F
2777  2515  888 0 30  4209  0361          LDL  TEMP2
2778  0361  888 0 70  4298  2828          ADD  KON30                  CHECK IF BASE LESS THAN -30
2779  2828  888 0 87  2231  2315          TGR              6F
2780  2231  888 0 37  0900  0444          SHL   0900
2781  0444  888 0 87  2315  1247          TGR  6F
2782  1247  888 1 29  0000  3028          LDA3  0000
2783  3028  888 0 30  1051  0854          LDL  CON0
2784  0854  888 0 82  2257  2457          TEQ  5F
2785  2457  888 1 25  9999  2229          LDA2  9999                  A25.CODE 3SLLLL1000
2786  2229  888 0 35  3023  2429          ERS  XMC
2787  2429  888 0 20  4209  1861          BUF  TEMP2
2788  1861  888 0 20  4247  1899          BUF  BIG30       9F
2789  2315  888 0 25  4209  0561     6    LDA  TEMP2
2790  0561  888 0 06  0164  0164          CLX                         A26.CODE 2B8888S000
2791  0164  888 0 32  0500  0772          SHR   0500
2792  0772  888 0 20  1178  0780          BUF  BIG20       8F
2793  2827  888 0 25  0008  2431     7    LDA  RL
2794  2431  888 0 32  0400  0838          SHR   0400
2795  0838  888 0 35  4724  0876          ERS  XC                     A27.CODE 1B8888PPPP
2796  0876  888 0 20  4974  0780          BUF  BIG10       8F
2797  0780  888 0 77  0780  1183     8    ATL
2798  1183  888 1 25  9999  2629          LDA2  9999
2799  2629  888 0 37  0500  0637          SHL   0500
2800  0637  888 0 35  4740  2042          ERS  X1
2801  2042  888 1 70  9999  2829          ADD2  9999
2802  2829  888 0 35  4741  0644          ERS  XMH
2803  0644  888 0 20  0008  1899          BUF  RL          9F
2804  1899  888 0 06  0502  0502     9    CLX  6F
2805  2257  888 0 07  HHHH  1860     5    IIR   HHHH                  A28.CODE AS SIMPLE VAR.
2806  1860  888 1 35  9999  3029          ERS2  9999
2807  3029  888 0 20  4209  2061          BUF  TEMP2
2808  2061  888 1 64  0000  0830          STA3  0000
2809  0830  888 1 25  9999  0830          LDA2  9999
2810  0830  888 0 37  0200  0835          SHL   0200
2811  0835  888 0 35  1237  0439          ERS  X49
2812  0439  888 0 20  2041  0844          BUF  BIG09
```

```
2813    0844  888 0 05  000A  0502            LDX  RA        6F
2814    0502  888 0 60  4209  0511    6       STA  TEMP4                A29.MOVE SUBSCRIPT
2815    0511  888 0 65  4420  1122            STX  TEMP3
2817    1122  888 0 29  0001  1230            LDA1  0001
2825    1230  888 0 37  0400  1637            SHL   0400
2826    1637  888 0 35  0043  1846            ERS  XM
2827    1846  888 0 70  2248  000A            ADD              RA
2828    2248  888 0 25  0001  1630            LDA   0001
2829    1630  888 1 09  0000  1830            LDX3  0000
2830    1830  888 0 30  0632  0634            LDL              INS2
2831    0632  888 1 0G  0000  1236            IIR3  0000
2832    1236  888 0 30  2243  2046            LDL  ACC
2833    2046  888 0 82  0849  1049            TEQ              1F
2834    0849  888 0 25  0851  1854            LDA  ARAS
2835    1854  888 0 60  2243  1049            STA  ACC         1F
2836    1049  888 0 25  4209  2261    1       LDA  TEMP4
2837    2261  888 0 05  4420  0272            LDX  TEMP3
2838    0272  888 0 30  0074  0634            LDL              INS2
2839    0074  888 0 25  000C  0878            LDA  RX
2840    0878  888 0 70  4301  0504            ADD  BIG90       -AR2
2841    0634  888 0 08  0851  4445    INS2    LIR1 ARAS        INS
2842    0505  888 0 30  4247  0349    &AR2    LDL  BIG30       1F
2843    0504  888 0 31  0349  0349    -AR2    CLL  1F
2844    0349  888 1 0G  9999  0353    1       IIR3  9999
2845    0353  888 1 29  0000  2030            LDA3  0000
2846    2030  888 0 35  4740  2242            ERS  X1
2847    2242  888 0 20  0008  2246            BUF  RL
2848    2246  888 0 20  0851  2054            BUF  ARAS
2849    2054  888 1 64  0000  2230            STA3  0000
2850    2230  888 1 07  9996  4140            IIR2  9996       NORMX
2851                                ARAS      EQU  MRP
```

```
2852                                                                                    U.  UNARY OPERATORS AND SPECIAL GENERATORS
2853   4117  888 0 30  2519  2521   SIGN#    LDL  LDLON     1F
2856   2056  888 0 30  2519  2521   #OFF     LDL  LDLON     1F          U1. EQUALS SIGN
2857   2521  888 0 50  4118  0170   1        STL  BIN!#
2858   0170  888 0 05  0972  4428            LDX  OBIN#     -OP3
2859   4118  888 0 67  4118  4118   BIN!#    HLT            #
2860   2519  888 0 08  1116  0373   LDLON    LIR1 A0016     ARITH
2861   1116  888 0 08  1732  2719   A0016    LIR1 J0032     1F
2862   1118  888 0 05  1920  1922   A0018    LDX  FIXA      2F
2863   1117  888 0 05  2919  1922   A0017    LDX  FLOTA     2F          U2. REPLACEMENT SETUP.
2864   1119  888 0 08  1732  2719   A0019    LIR1 J0032     1F
2865   2719  888 1 29  9999  2430   1        LDA3  9999
2866   2430  888 0 70  4301  2254            ADD  BIG90     -INRA
2867   2254  888 0 07  4092  2657   -INRA    IIR   4092
2868   2657  888 0 30  4417  0269            LDL  RATOR
2869   0269  888 0 82  0472  2255            TEQ            &INRA
2870   0472  888 0 30  1300  0702            LDL  TRCOF
2871   0702  888 0 25  1307  2309            LDA  TRCSW
2872   2309  888 0 82  0912  2255            TEQ            &INRA
2873   0912  888 0 30  1914  0363            LDL            GET
2874   1914  888 1 0G  9999  0318            IIR3  9999
2875   0318  888 0 25  1395  0397            LDA  I0095
- 2876   0397  888 0 30  0599  4350            LDL  7F        ASM2
2877   2255  888 1 09  0000  2630   &INRA    LDX3  0000
2878   2630  888 0 32  0100  0834            SHR   0100
2879   0834  888 0 70  000A  0639            ADD  RA        -RE
2880   0640  888 0 08  1728  1244   &RE      LIR1 J0028
2881   1244  888 0 30  2446  0442            LDL            UNOP3
2882   2446  888 0 30  2448  0319            LDL  3F        ATL
- 2883   1922  888 0 08  1724  0639   2        LIR1 J0024     -RE
2884   0639  888 0 30  2448  0442   -RE      LDL  3F        UNOP3
2885   2448  888 1 0G  9999  2454   3        IIR3  9999     LDLOF
2886   2454  888 1 29  0000  2830   LDLOF    LDA3  0000                 U4. REPLACEMENT OPERATOR
2887   2830  888 0 70  4603  2856            ADD  BIG60     -EEE
2888   2857  888 0 30  2856  4799   &EEE     LDL  -EEE      EEE
2889   2856  888 0 30  0599  3030   -EEE     LDL  7F        ASMTR
2890   0599  888 0 30  2454  2256   7        LDL  LDLOF
2891   2256  888 0 50  4118  0070            STL  BIN!#
2892   0070  888 1 0G  9999  4215            IIR3  9999     OPX
2893   3030  888 0 05  1232  1234   ASMTR    LDX  TRACE
2894   1234  888 0 25  1636  0173            LDA  CTRC      ASM1
2895   4155  888 0 05  1920  2122   FIXF     LDX  FIXA                  U10.UNARY OPERATORS
2896   2122  888 0 31  1325  1325            CLL
2897   1325  888 0 25  4408  0760            LDA  BIG01
2898   0760  888 0 60  0860  1262            STA  OTYPE     2F
2899   4125  888 0 05  1127  0729   EXPF     LDX  EXP       1F
2900   4120  888 0 05  2322  0729   SINF     LDX  SIN       1F
2901   4121  888 0 05  0723  0729   COSF     LDX  COS       1F
2902   4122  888 0 05  0924  0729   TANF     LDX  TAN       1F
```

```
2903    4123  888 0 05  1925  0729    ATANF   LDX  ATAN       1F
2904    4124  888 0 05  0726  0729    LNF     LDX  LN         1F
2905    4119  888 0 05  2721  0729    SQRTF   LDX  SQRT       1F
2906    0729  888 0 31  1332  1332    1       CLL
2907    1332  888 0 50  0860  1262            STL  OTYPE      2F
2908    1262  888 1 29  0000  2631    2       LDA3  0000
2909    2631  888 0 35  4740  2442            ERS  X1
2910    2442  888 0 82  2646  2846            TEQ  1F         2F
2911    4154  888 0 05  2919  2921    FLOTF   LDX  FLOTA
2912    2921  888 0 31  1124  1124            CLL
2913    1124  888 1 29  0000  2831            LDA3  0000
2914    2831  888 0 35  4740  2642            ERS  X1
2915    2642  888 0 82  4140  3046            TEQ  NORMX      5F
2916    4161  888 0 05  0563  1365    BCOMP   LDX  COMPL
2917    1365  888 0 30  4756  3046            LDL  BIG02      5F
2918    3046  888 0 50  0860  2646    5       STL  OTYPE      1F
2919    2646  888 0 08  1724  1841    1       LIR1 J0024      UNOP
2920    2846  888 0 25  2648  0336    2       LDA             NOMAL
2921    2648  888 0 34  0500  0000            CON  34050      00000          F(I) ERR
2922    4126  888 0 08  1736  0929    ABSF    LIR1 J0036      1F
2923    2814  888 1 0G  9999  3031    SQUAR   IIR3  9999
2924    3031  888 0 09  0004  1632            LDX1  0004      2F
2925    4141  888 0 05  0343  0145    WDPOZ   LDX  PAUSF      3F
2926    4142  888 0 05  0744  0145    WDSTP   LDX  STOPF      3F
2927    0145  888 1 07  0001  0549    3       IIR2  0001
2928    0549  888 0 30  0351  0553            LDL  POZMD
2929    0553  888 1 50  0000  1632            STL2  0000      2F
2930    1130  888 1 08  1190  1133    POZ$    LIR3 RAND       BOOL$
2931    1632  888 0 08  1724  0929    2       LIR1 J0024      1F
2932    0929  888 1 29  0000  1832    1       LDA3  0000
2933    1832  888 0 35  4740  2842            ERS  X1
2934    2842  888 0 60  0860  1841            STA  OTYPE      UNOP
2935    4127  888 0 30  1129  0731    OPO     LDL  1F                  THIS OPERATOR IS PERMANENTLY ON THE BOTTOM
2936    0731  888 0 25  1333  4514            LDA             ALARM    OF THE OPERATOR STACK,IS ACTIVE ONLY ON AN
2937    1333  888 0 18  0022  0025            CON  18002      20025    EXTRA RIGHT PARENTHESIS
2938    1129  888 0 05  4093  4428    1       LDX  00PO       -OP3
2939                             NO,     EQU  &IF1
2940                             POZ,    EQU  NO,
2941    0336  888 0 30  4140  4514    NOMAL   LDL  NORMX      ALARM
2942    1133  888 1 07  9999  4114    BOOL$   IIR2  9999     SIGN$
2943    0543  888 0 30  4417  0169    NO$     LDL  RATOR                 U12.END OF STATEMENT
2944    0169  888 0 07  4092  1372            IIR   4092
2945    1372  888 0 82  0575  1629            TEQ  4F         MRP
2946    0575  888 0 25  1051  2654    4       LDA  CON0
2947    2654  888 1 64  0000  2032            STA3  0000
2948    2032  888 1 0G  0000  1836            IIR3  0000
2949    1836  888 0 30  1238  0040            LDL  CRAND
2950    0040  888 0 82  1644  1844            TEQ  1F
2951    1844  888 0 87  1647  1847            TGR  2F
2952    1847  888 1 0G  0001  1851            IIR3  0001
```

used - entries.

```
2953    1851  888 0 25  2854  2456          LDA              5F
2954    2854  888 0 32  2800  0000          CON   32280      00000          MISSING OPERAND
2955    1647  888 1 0G  9999  2051  2       IIR3   9999
2956    2051  888 0 25  3054  2456          LDA              5F
2957    3054  888 0 18  0028  0000          CON   18002      80000          EXTRA OPERAND
2958    2456  888 0 30  0575  4514  5       LDL   4B         ALARM
2959    1644  888 0 05  2047  1249  1       LDX   1F
2960    1249  888 0 08  0851  2455          LIR1  ARAS
2961    2455  888 0 30  0543  4229          LDL   NO$        REM
2962    2047  888 0 60  2243  4140  1       STA   ACC        NORMX
2963    1238  888 0 00  1190  0000  CRAND    JMP   RAND        0000
2964    0363  888 0 50  1819  2232  GET      STL   &SAC                        SUBROUTINE TO BRING OPERAND INTO REGISTER A
2965    2232  888 1 09  0000  2432          LDX3   0000
2966    2432  888 0 32  0100  2036          SHR    0100
2967    2036  888 0 70  000A  3041          ADD   RA         -GET
2968    3042  888 0 08  1728  2247  &GET     LIR1  J0028      1F
2969    3041  888 0 08  1724  2247  -GET     LIR1  J0024      1F
2970    2247  888 0 25  4740  0292  1       LDA   X1
2971    0292  888 1 39  0000  2632          ERS3   0000
2972    2632  888 0 60  0860  1862          STA   OTYPE
2973    1862  888 0 32  0900  0274          SHR    0900
2974    0274  888 0 06  2645  2645          CLX   UNOP2
2975    4131  888 0 30  1933  0642  WDGO     LDL              EXPLB        U13. WORD 'GO'
2976    1933  888 0 30  0335  4044          LDL              SCAN
2977    0335  888 0 30  4221  0573          LDL   LPREN
2978    0573  888 0 82  1176  1776          TEQ   1F
2979    1776  888 0 30  4974  2832          LDL   BIG10
2980    2832  888 0 87  1235  1635          TGR              2F
2981    1235  888 0 30  1837  3089          LDL              LS#
2982    1837  888 0 30  4140  4736          LDL   NORMX      GOTO
2983    1635  888 1 64  0001  3032  2       STA3   0001
2984    3032  888 0 25  1634  2236          LDA   DOTAG
2985    2236  888 0 31  0839  0839          CLL
2986    0839  888 0 82  2044  2244          TEQ              2F
2987    2044  888 0 25  4824  1276          LDA   DOVAR
2988    1276  888 1 64  0002  2433          STA3   0002
2989    2433  888 0 25  1835  2037          LDA              3F
2990    1835  888 0 88  7989  0000          CON   88798      90000          IIR10 STA3 JMP2
2991    2244  888 0 25  2447. 2037  2       LDA              3F
2992    2447  888 0 89  0000  0000          CON   89000      00000          JMP2
2993    2037  888 0 30  1239  0377  3       LDL              ASM11
2994    1239  888 1 0G  0001  2444          IIR3   0001
2995    2444  888 0 26  2647  2647          CLA
2996    2647  888 0 30  4151  4486          LDL   WDDIM      FILUP
2997    1176  888 1 07  0002  0980  1       IIR2   0002
2998    0980  888 0 05  0582  4927          LDX              INCUQ
2999    0582  888 1 50  9999  2633          STL2   9999
3000    2633  888 0 30  2035  0642          LDL              EXPL#
3001    2035  888 0 30  2237  1639          LDL   GOMD
3002    1639  888 0 05  2241  4238          LDX   0G0%       MDOP1
```

```
3003  2833  888 0 30  2235  0642  GO.     LDL  1F        EXPL3
3004  2235  888 0 05  0089  0491  1       LDX  LSW
3005  0491  888 0 30  4140  1142          LDL  NORMX     GOSU3
3006  1142  888 0 50  4926  1778  GOSUB   STL  EXIT3
3007  1778  888 1 0G  9999  0782          IIR3 9999
3008  0782  888 1 29  0001  3033          LDA3 0001
3009  3033  888 0 30  2435  000C          LDL            RX
3010  2435  888 0 35  0043  2847          ERS  XM
3011  2847  888 0 60  4209  2461          STA  TEMP2
3012  2461  888 0 05  0663  4927          LDX            INCUQ
3013  0663  888 0 25  000B  1267          LDA  RL
3014  1267  888 0 30  4756  2308          LDL  BIGO2
3015  2308  888 0 05  4926  4494          LDX  EXIT3     ASM42
3016  4128  888 0 30  1330  4044  GO%     LDL            SCAN
3017  1330  888 0 30  1074  1876          LDL  .
3018  1876  888 0 82  2235  0479          TEQ  1B
3019  0479  888 0 30  2235  2818          LDL  1B        MCAL
3020  1834  888 0 30  2436  0363  GO$     LDL            GET       U14.END COMPUTED GO.
3021  2436  888 0 25  1638  0240          LDA# 78770     60000         ADDOA JMP UZACC
3022  0240  888 0 30  2644  0377          LDL            ASM11
3023  2644  888 1 25  9999  2234          LDA2 9999
3024  2234  888 0 60  4880  0682          STA  NXLOC
3025  0682  888 0 30  0484  4736          LDL            GOTO
3026  0484  888 1 07  9998  0488          IIR2 9998
3027  0488  888 1 0G  9999  4114          IIR3 9999      SIGN$
3028  4130  888 0 30  1932  0642  ASS1    LDL            EXPL3     U17.WORD 'ASSIGN'
3029  1932  888 0 05  1134  4428          LDX            -OP3
3030  1134  888 0 75  0736  0000          SUB  ASS2       0000
3031  0736  888 0 25  4196  0148  ASS2    LDA  UNIQU
3032  0148  888 0 70  0550  0753          ADD  BIG29                U18. ASSIGN OP
3033  0753  888 0 30  0555  4357          LDL            ASM33
3034  0555  888 1 0G  9999  0959          IIR3 9999
3035  0959  888 0 05  0108  0910          LDX  LSWOF
3036  0910  888 0 30  1912  1142          LDL            GOSUB
3037  1912  888 1 0G  0002  0716          IIR3 0002
3038  0716  888 0 30  0518  3030          LDL            ASMTR
3039  0518  888 1 0G  9998  4215          IIR3 9998      OPX
3040  4151  888 0 30  1353  0755  WDDIM   LDL  DIMMD      INSMD     U21.'DIMENSION'
3041  0755  888 1 07  0001  1359  INSMD   IIR2 0001      ISMD1
3042  1359  888 1 50  0000  4140  ISMD1   STL2 0000      NORMX
3043  2844  888 0 07  HHHH  3047  DIM     IIR  HHHH
3044  3047  888 1 39  0000  2434          ERS3 0000
3045  2434  888 1 60  0001  2634          STA2 0001
3046  2634  888 0 20  2636  000A          BUF            RA
3047  2636  888 0 08  0000  2441          LIR1 0000
3048  2441  888 0 07  0002  3044          IIR  0002
3049  3044  888 0 70  4600  2655          ADD  MEML
3050  2655  888 0 60  4600  0902          STA  MEML
3051  0902  888 1 60  0002  2834          STA2 0002
3052  2834  888 0 70  1907  1910          ADD  TWO9S
```

```
3053  1910  BBB 0 77  1910  2313          ATL
3054  2313  BBB 0 29  0000  3034          LDA1  0000
3055  3034  BBB 0 05  000A  1838          LDX   RA
3056  1838  BBB 0 35  4724  2076          ERS   XC
3057  2076  BBB 0 20  0008  0280          BUF   RL
3058  0280  BBB 0 64  0000  2635          STA1  0000
3059  2635  BBB 0 25  000C  1839          LDA   RX
3060  1839  BBB 0 20  4247  1649          BUF   BIG30
3061  1649  BBB 0 35  4201  2855          ERS   XOM
3062  2855  BBB 0 05  000A  2459          LDX   RA
3063  2459  BBB 0 25  0008  0863          LDA   RL
3064  0863  BBB 0 70  0465  000A          ADD           RA
3065  0465  BBB 0 35  0000  2835          ERS   0000                    30 + ERS # STX
3066  2835  BBB 0 07  0001  2038          IIR   0001
3067  2038  BBB 1 60  0003  3035          STA2  0003
3068  3035  BBB 0 30  2437  2039          LDL   DIMMD
3069  2039  BBB 0 05  2641  4235          LDX   0DIM%     MDOP
3070                            DIM$      EQU   MRP
3071  0471  BBB 0 07  HHHH  0474  DIM.     IIR   HHHH
3072  0474  BBB 1 39  0000  2836          ERS3  0000
3073  2836  BBB 0 05  000A  0440          LDX   RA
3074  0440  BBB 0 70  2848  000A          ADD           RA
3075  2848  BBB 0 30  0001  3036          LDL   0001
3076  3036  BBB 0 07  0001  2239          IIR   0001
3077  2239  BBB 0 70  4600  3055          ADD   MEML
3078  3055  BBB 0 60  4600  1902          STA   MEML
3079  1902  BBB 0 70  0704  000A          ADD           RA
3080  0704  BBB 0 65  0000  2637          STX   0000
3081  2637  BBB 1 85  9999  2276          MUL2  9999
3082  2276  BBB 0 32  0400  1283          SHR   0400
3083  1283  BBB 1 65  9999  2837          STX2  9999      DIM.
3084  4139  BBB 0 07  HHHH  1342  DIM%     IIR   HHHH
3085  1342  BBB 1 39  0000  3037          ERS3  0000
3086  3037  BBB 0 70  2439  000A          ADD           RA
3087  2439  BBB 0 30  0001  2238          LDL   0001
3088  2238  BBB 1 85  9999  2476          MUL2  9999
3089  2476  BBB 0 32  0800  0687          SHR   0800
3090  0687  BBB 1 25  9997  0799          LDA2  9997
3091  0799  BBB 0 37  0200  2438          SHL   0200
3092  2438  BBB 0 32  0600  3048          SHR   0600
3093  3048  BBB 0 77  3048  2251          ATL
3094  2251  BBB 1 25  9998  2600          LDA2  9998
3095  2600  BBB 0 70  2638  000A          ADD           RA
3096  2638  BBB 0 50  0000  2838          STL   0000
3097  2838  BBB 1 07  9996  1849          IIR2  9996
3098  1849  BBB 0 07  FFFF  2656          IIR   FFFF
3099  2656  BBB 0 87  2837  2659          TGR   DIM.
3100  2659  BBB 0 30  2837  2639          LDL   DIM.
3101  2639  BBB 0 25  2841  4514          LDA           ALARM
3102  2841  BBB 0 03  3500  0000          CON   03350     00000         BAD DIMENSION
```

```
- 3103  2837  888 1 0G  9999  4140  D1M*    IIR3  9999      NORMX
  3104  2822  888 1 0G  9999  1133  D1M$    IIR3  9999      BOOL$
  3105  4152  888 J 25  0754  0756  WDCOM   LDA   1F                    U27.'COMMON'
  3106  0756  888 J 60  2220  3038        STA   UASW
  3107  3038  888 J 30  0840  0755        LDL   COMMD     INSMD
  3108  2508  888 J 07  0001  0711  COM*    IIR    0001   2F
  3109  0754  888 J 07  HHHH  0557  1       IIR    HHHH
  3110  0557  888 1 39  0000  2839        ERS3  0000
  3111  2839  888 J 70  2049  000A        ADD             RA
  3112  2049  888 J 25  0001  3039        LDA    0001
  3113  3039  888 J 35  0043  0711        ERS   XM        2F
  3114  0711  888 J 30  4198  0750  2     LDL   COMON
  3115  0750  888 J 50  4631  1783        STL   TEMP1
  3116  1783  888 J 70  0008  0388        ADD   RL
  3117  0388  888 J 60  4198  2800        STA   COMON
  3118  2800  888 J 30  1240  4833        LDL             BR2
  3119  1240  888 J 20  4631  1883        BUF   TEMP1
  3120  1883  888 J 64  0000  1640        STA1   0000
  3121  1640  888 1 0G  9999  2249        IIR3  9999
  3122  2249  888 J 25  4030  1882        LDA   LAST
  3123  1882  888 J 30  1064  0466        LDL   $
  3124  0466  888 J 82  0469  4140        TEQ   EQ1$      NORMX
  3125  0469  888 J 25  1821  1840  EQ1$    LDA   MISUB
  3126  1840  888 J 60  2220  1133        STA   UASW      BOOL$
  3127                      COM$    EQU   COM*
  3128  0528  888 J 25  1930  4514  BED     LDA             ALARM
  3129  1930  888 J 03  2300  0000        CON   03230     00000          BAD EQUIV
  3130  4132  888 J 25  4277  0579  WDNO    LDA   BIG50
  3131  0579  888 J 60  4804  4050        STA   NOTAG     SCAN1     U29.CONTROL WORDS
  3132  4136  888 J 70  000A  1741  WDTRC   ADD   RA        -TRC
  3133  1742  888 J 60  4804  1356  &TRC    STA   NOTAG
  3134  1356  888 J 25  1300  2102        LDA   TRCOF     1F
  3135  1741  888 J 25  1855  2102  -TRC    LDA   TRCON     1F
  3136  2102  888 J 60  1307  4050  1       STA   TRCSW     SCAN1
  3137  4133  888 J 70  000A  1338  WDLIS   ADD   RA        -LIS
  3138  1339  888 J 60  4804  1756  &LIS    STA   NOTAG
  3139  1756  888 J 25  4735  0587        LDA   PROF      1F
  3140  1338  888 J 25  4975  0587  -LIS    LDA   PRON      1F
  3141  0587  888 J 60  4883  4050  1       STA   PRTSW     SCAN1
  3142  4137  888 J 70  000A  1942  WDCOR   ADD   RA        -COR
  3143  1943  888 J 60  4804  1956  &COR    STA   NOTAG
  3144  1956  888 J 07  0057  1759        IIR    0057   1F
  3145  1942  888 J 07  0007  1759  -COR    IIR    0007   1F
  3146  1759  888 J 60  4336  4050  1       STA   INCRE     SCAN1
  3147  4166  888 J 70  000A  1771  WDPRG   ADD   RA        -PRG
  3148  1772  888 J 60  4804  2040  &PRG    STA   NOTAG
  3149  2040  888 J 25  4758  2060        LDA   PCHOF     1F
  3150  1771  888 J 25  4651  2060  -PRG    LDA   PCHON     1F
  3151  2060  888 J 60  4981  4050  1       STA   PCHSW     SCAN1
```

```
3152  4100  888 0 05  4740  2142  WDDO    LDX  X1      1F        D.  DO LOOP CONTROL
3153  4138  888 0 06  2142  2142  WDTRU   CLX  1F
3154  2142  888 0 25  0944  0546  1       LDA  3F
3155  0546  888 0 60  4206  0358          STA  LESW    WDD01     D1. SET UP FOR LABEL
3156  0358  888 1 65  0001  2240  WDD01   STX2  0001
3157  2240  888 1 07  0002  2449          IIR2  0002
3158  2449  888 0 30  2451  3056          LDL  1F      2F
3159  3056  888 0 50  4117  0669  2       STL  SIGN#
3160  0669  888 0 30  0671  1359          LDL  DOMD    ISMD1
3162  2451  888 1 25  0000  2440  1       LDA2  0000             D3. ZERO COMMA COUNT
3163  2440  888 0 35  3023  2640          ERS  XMC
3164  2640  888 1 60  0000  2840          STA2  0000
3165  2840  888 0 30  2056  3056          LDL  #OFF    2B
3166  0944  888 0 30  4402  0954  3       LDL  LEOFF
3167  0954  888 0 50  4206  0008          STL  LESW    RL
3168  0168  888 0 30  0970  2012  DO.     LDL          DOIF
3169  0970  888 0 05  4140  0883          LDX  NORMX   MAGET
3170  1370  888 0 30  1972  0374  DOS     LDL  DOO     DO$SB     D5. CHECK COMMAS
3171  0374  888 0 50  1976  4164  DO$SB   STL  EXIT6   DO$1
3172  4164  888 1 25  0000  3040  DO$1    LDA2  0000
3173  3040  888 0 70  2212  2849          ADD  BIG40   -D02
3174  2849  888 0 07  1074  4086  -D02    IIR  T0024   DIVT1
3175  2850  888 1 07  9998  3057  &D02    IIR2  9998             D6. STORE EXP IN TEMP
3176  3057  888 0 05  2859  0283          LDX          CLACC
3177  2859  888 0 30  4745  1097          LDL  TROFF
3178  1097  888 0 50  4789  0741          STL  TRSW
3179  0741  888 0 07  HHHH  1144          IIR   HHHH
3180  1144  888 1 39  9996  0798          ERS3  9996
3181  0798  888 0 70  3000  000A          ADD          RA
3182  3000  888 0 25  0001  2649          LDA   0001
3183  2649  888 0 60  2651  0858          STA  DON
3184  0858  888 1 29  9997  0999          LDA3  9997
3185  0999  888 0 60  1079  2481          STA  T0029             D7. DO OR DONT
3186  2481  888 1 35  0001  3049          ERS2  0001
3187  3049  888 0 35  1634  3050          ERS  DOTAG
3188  3050  888 0 31  1858  1858          CLL
3189  1858  888 0 82  2661  2861          TEQ  DONT
3190  2861  888 1 29  0000  2851          LDA3  0000
3191  2851  888 0 35  4723  0675          ERS  KON.5
3192  0675  888 1 39  9998  3051          ERS3  9998
3193  3051  888 0 82  2661  2058          TEQ  DONT
3194  2058  888 0 50  1634  2258          STL  DOTAG
3195  2258  888 0 25  0509  1911          LDA  LSWON             D8. BEGIN DOO
3196  1911  888 0 60  0089  0691          STA  LSW
3197  0691  888 1 06  9995  0095          IIR3  9995
3198  0095  888 0 07  HHHH  0098          IIR   HHHH
3199  0098  888 1 39  0005  2458          ERS3  0005
3200  2458  888 0 70  2260  000A          ADD          RA
3201  2260  888 0 25  0001  2658          LDA   0001
```

```
3202  2658  888 J 20  1388  0590            BUF  10086
3203  0590  888 J 60  1375  2577            STA  10075
3204  2577  888 J 07  HHHH  1180            IIR  HHHH
3205  1180  888 1 39  0003  2858            ERS3 0003
3206  2858  888 J 70  2460  000A            ADD            RA
3207  2460  888 J 25  0001  3058            LDA  0001
3208  3058  888 J 20  2660  2062            BUF# 0R000     09999
3209  2062  888 J 30  0464  4350            LDL            ASM2
3210  0464  888 J 07  HHHH  1867            IIR  HHHH
3211  1867  888 1 39  0002  3059            ERS3 0002
3212  3059  888 J 60  4824  2676            STA  DOVAR
3213  2676  888 J 25  1278  0480            LDA            7F
3214  1278  888 J 19  7574  2021            CON  19757     42021        3F2H IIR1N LDL5 TGR9F MK9F
3215  2661  888 1 34  9998  2860  DONT      LDL3 9998                   D10•LDA INIT 3F
3216  2860  888 1 0G  0001  0664            IIR3 0001
3217  0664  888 1 54  0000  3060            STL3 0000
3218  3060  888 J 30  2262  0363            LDL            GET
3219  2262  888 1 0G  9999  0666            IIR3 9999
3220  0666  888 J 25  0668  0270            LDA# 06190     00000        UZACC 3F2H
3221  0270  888 J 30  0672  0377            LDL            ASM11        D11•   V + INC
3222  0672  888 J 07  1078  4698            IIR  T0028     DIVRT
3223  4157  888 1 0G  9995  0761  DONT1     IIR3 9995
3224  0761  888 J 25  0763  0480            LDA            7F
3225  0763  888 J 74  2079  0600            CON  74207     90600        LDL5 TGR9F STA3 UZACC
3226  0460  888 J 30  2082  0377  7         LDL            ASM11
3227  2082  888 J 25  4989  0891            LDA  TRON                   D12•LDL• TGR
3228  0891  888 J 60  4789  1976            STA  T•SW      EXIT8
3229  1972  888 J 25  2651  3061  DOO       LDA  DON                    D20•LABEL IN TABLE
3230  3061  888 J 20  0544  0746            BUF  NINEF
3231  0746  888 J 05  0531  2133            LDX  TWO8
3232  2133  888 J 08  0537  1136            LIR1 DOOST
3233  1136  888 J 30  0543  4449            LDL  NO$       INS
```

```
3234  4226  888 1 25  0000  2462  FUNCT  LDA2  0000                    F.  FUNCTION CALLS
3235  2462  888 0 30  1353  0955         LDL   D1MMD
3236  0955  888 0 82  2844  0558         TEQ   DIM
3237  0558  888 0 30  0960  0362         LDL                FASIN
3238  0960  888 0 05  3022  2662         LDX   DUA                  F1. ASSIGN F
3239  2662  888 0 65  2220  2862         STX   UAS#
3240  2862  888 0 05  0864  0866         LDX   OFC%
3241  0866  888 0 30  1600  4234         LDL   FCMD         MDOP2
3242  3062  888 0 30  1264  1266  FC.    LDL                PARSB    F2. SET FUNC MODE
3243  1264  888 1 25  0000  1863         LDA2  0000
3244  1863  888 0 70  4408  2111         ADD   BIG01
3245  2111  888 1 60  0000  4140         STA2  0000         NORMX
3246                      FC$    EQU   MRP
3247  4158  888 0 30  1360  1266  FC%    LDL                PARSB
3251  1360  888 0 30  0562  0364         LDL   DOWN         NAMEC    F4. BEGIN REVERSE PASS
3252  0364  888 0 50  0166  0368  NAMEC  STL   EXIT9
3253  0368  888 1 25  0000  2063         LDA2  0000
3254  2063  888 0 32  0400  0470         SHR   0400
3255  0470  888 0 35  0406  2263         ERS   X45
3256  2263  888 0 70  4095  0298         ADD   KON2
3257  0298  888 0 30  4196  0348         LDL   UNIQU
3258  0348  888 0 70  0008  1953         ADD   RL
3259  1953  888 0 60  4196  1798         STA   UNIQU         9F
3260  1798  888 0 75  4097  2463  9      SUB   KON1
3261  2463  888 1 60  0001  2663         STA2  0001
3262  2663  888 1 29  0000  2863         LDA3  0000
3263  2863  888 0 06  1866  1866         CLX
3264  1866  888 0 32  0900  1878         SHR   0900
3265  1878  888 0 70  0680  000A         ADD                RA
3266  0680  888 1 29  0000  4029         LDA3  0000         F0005
3267  4029  888 0 30  3063  4025  F0005  LDL   1F           F0001
3268  4025  888 0 05  0417  4744  F0001  LDX   FCEX         ASIGN
3269  3063  888 0 50  4191  0693  1      STL   TEMP5
3270  0693  888 0 25  0295  1297         LDA#  07HHH        H0000
3271  1297  888 0 30  2099  4556         LDL                ASM32
3272  2099  888 0 07  HHHH  2302         IIR   HHHH
3273  2302  888 0 35  4191  0743         ERS   TEMP5
3274  0743  888 0 20  0345  0547         BUF#  35000        00000
3275  0547  888 0 30  0749  4357         LDL   8F           ASM33
3276  4024  888 0 30  1864  0108  F0000  LDL                LSWOF
3277  1864  888 0 77  1864  2067         ATL                1F
3278  0417  888 0 25  0008  2067  FCEX   LDA   RL           1F
3279  4027  888 0 30  4623  2067  F0003  LDL   BIG05        1F
3280  2067  888 0 35  0043  2064  1      ERS   XM           2F
3281  2064  888 0 60  4209  2311  2      STA   TEMP2
3282  2311  888 1 25  0001  2264         LDA2  0001
3283  2264  888 0 05  2066  4494         LDX   7F           ASM42
3284  1266  888 0 50  1976  1978  PARSB  STL   EXIT8
3285  1978  888 1 29  0000  2464         LDA3  0000
```

```
3286  2464  888 0 77  2464  2267                ATL
3287  2267  888 0 37  0900  0879                SHL   0900
3288  0879  888 0 70  000A  0684                ADD   RA          -PAR1
3289  0685  888 0 30  1287  0363  &PAR1         LDL   1F          GET
3290  0684  888 0 25  4431  2333  -PAR1         LDA   BIG21
3291  2333  888 0 82  0685  1287                TEQ   &PAR1       1F
3292  1287  888 0 05  1976  0283  1             LDX   EXIT8       CLACC
3293  3022  888 0 07  1068  4710  DUA           IIR   T0018       DIVT2
3294  4026  888 0 25  2664  2266  F0002         LDA#  07990       19999
- 3295  2266  888 0 30  0749  4350              LDL   8F          ASM2
3296  0749  888 1 25  0001  2864  8             LDA2  0001
3297  2864  888 0 20  2212  3064                BUF   BIG40
3298  3064  888 1 64  0000  0665                STA3  0000
3299  0665  888 0 25  1395  0597                LDA   I0095
3300  0597  888 0 30  2066  4350                LDL   7F          ASM2
3301  2066  888 1 0G  9999  0670  7             IIR3  9999
3302  0670  888 1 25  0000  0865                LDA2  0000
3303  0865  888 0 70  4225  2078                ADD   BIG99       -PAR4
3304  2079  888 1 60  0000  1865  &PAR4         STA2  0000
3305  1865  888 1 25  0001  1798                LDA2  0001        9B
3306  2078  888 0 30  0880  2282  -PAR4         LDL               4F
3307  0880  888 1 25  0001  2065                LDA2  0001
3308  2065  888 0 75  4097  0500                SUB   KON1
3309  0500  888 0 30  0166  0932                LDL   EXIT9       FILNX
3310  2282  888 1 29  0000  2265  4             LDA3  0000
- 3311  2265  888 0 32  0400  4970              SHR   0400        ASM36
3312  0962  888 0 05  1821  2465  DOWN          LDX   MISUB                   FS. LIR3
3313  2465  888 0 65  2220  2665                STX   UASW
3314  2665  888 1 07  9999  0869                IIR2  9999
3315  0869  888 1 29  0000  2865                LDA3  0000
3316  2865  888 0 35  4740  0492                ERS   X1
3317  0492  888 0 30  4140  2342                LDL   NORMX
3318  2342  888 0 50  1819  0463                STL   &SAC        SACC
3319                                  CAL*      EQU   NO*
3320  2320  888 1 29  0000  3065  CAL$          LDA3  0000
3321  3065  888 0 35  0645  2466                ERS   H1
3322  2466  888 0 30  4974  2876                LDL   BIG10
3323  2876  888 0 82  2822  1279                TEQ   D1M$
3324  1279  888 0 30  2681  0362                LDL               FASIN
3325  2681  888 0 30  2083  2282                LDL               4B
3326  2083  888 0 05  0485  4084                LDX               FARNL
3327  0485  888 0 30  2822  0932                LDL   D1M$        FILNX
3328  4160  888 0 30  0762  0755  WDCAL         LDL   CALMD       INSMD
3329  0362  888 0 50  0201  2666  FASIN         STL   EXIT4
3330  2666  888 0 30  0868  4833                LDL               BR2
3331  0868  888 0 77  0868  0871                ATL
3332  0871  888 0 70  2212  2866                ADD   BIG40       -FUNC
3333  2866  888 0 70  1268  2119  -FUNC         ADD               -FNC1
3334  1268  888 0 59  9999  0000                CON   59999       90000
3335  2119  888 0 07  0100  2522  -FNC1         IIR   0100
```

```
3336  2522  888 0 70  1924  1327           ADD  FS
3337  1327  888 0 60  1924  1126           STA  FS
3338  1126  888 0 32  0200  1131           SHR   0200
3339  1131  888 0 34  0001  3066           LDL1  0001
3340  3066  888 0 05  1868  0204           LDX                SUBDF
3341  1868  888 0 30  0870  4833           LDL                BR2
3342  0870  888 0 20  1924  1326           BUF  FS
3343  1326  888 0 77  1326  1329           ATL
3344  1329  888 0 64  0000  2867           STA1  0000         &FUNC
3345  2867  888 1 29  0000  2467  &FUNC    LDA3  0000
3346  2467  888 0 35  4740  0692           ERS  X1
3347  0692  888 0 20  0008  0496           BUF  RL
3348  0496  888 1 64  0000  0201           STA3  0000         EXIT4
3349  0204  888 0 65  4926  2667  SUBDF    STX  EXIT3
3350  2667  888 0 50  4209  2511           STL  TEMP2
3351  2511  888 0 32  0200  1916           SHR   0200
3352  1916  888 0 35  0718  2520           ERS#  00000        0HH00
3353  2520  888 0 20  4603  1355           BUF  BIG60
3354  1355  888 0 30  0757  4700           LDL                ASM41
3355  0757  888 0 05  4209  1361           LDX  TEMP2         1F
3356  2156  888 0 50  4926  1361  SHEAD    STL  EXIT3         1F
3357  1361  888 0 25  1363  1765  1        LDA  HEAD
3358  1765  888 0 75  4097  3067           SUB  KON1          2F
3359  3067  888 0 60  1363  1965  2        STA  HEAD
3360  1965  888 0 31  0568  0568           CLL
3361  0568  888 0 82  0171  0371           TEO                1F
3362  0171  888 0 50  0775  0775           STL  WARN
3363  0775  888 0 07  0050  3067           IIR   0050         2B
3364  0371  888 0 70  1373  000A  1        ADD                RA
3365  1373  888 0 65  1549  4926           STX  00000         EXIT3
```

```
3366  4129  888 0 25  1331  2533   LABL    LDA  LEXP1                    D.  D40. CLOSE OF DO RANGE.
3367  2533  888 0 60  4206  1358           STA  LESW
3368  1358  888 0 30  1760  4044           LDL                SCAN
3369  1760  888 0 30  0522  0089           LDL  LABLX         LSW
3370  0522  888 0 29  0000  2002   LABLX   LDA1  0000        LBLX1
3371  2002  888 0 35  4741  2068   LBLX1   ERS  XMH
3372  2068  888 0 60  4191  0893           STA  TEMP5
3373  0893  888 0 30  0495  4736           LDL                GOTO
3374  0495  888 0 05  4191  1143           LDX  TEMP5
3375  1143  888 0 65  4880  4140           STX  NXLOC         NORMX
3376  1331  888 0 77  1331  1334   LEXP1   ATL
3377  1334  888 0 25  0537  1939           LDA  DOOST
3378  1939  888 0 70  1141  000A           ADD                RA
3379  1141  888 0 25  0001  2268           LDA   0001
3380  2268  888 0 35  0043  2468           ERS  XM
3381  2468  888 0 82  1271  1871           TEQ                1F
3382  1271  888 0 25  0473  0875           LDA  DOEON
3383  0875  888 0 60  4170  1871           STA  DOESW         1F
3384  1871  888 0 50  4209  2711   1       STL  TEMP2         2F
3385  0244  888 0 60  4209  2711   LEXP    STA  TEMP2         2F
3386  2711  888 0 05  4277  1929   2       LDX  BIG50
3387  1929  888 0 65  4412  0564           STX  TYPE
3388  0564  888 0 25  0366  0768           LDA  LIT99
3389  0768  888 0 30  4410  4729           LDL  SEND          SRCH
3390  0473  888 0 08  0537  3076   DOEON   LIR1 DOOST                    D40. GO TO 2B
3391  3076  888 0 30  2278  4229           LDL                REM
3392  2278  888 0 29  0001  2668           LDA1  0001
3393  2668  888 0 60  4191  1293           STA  TEMP5
3394  1293  888 0 35  0043  2868           ERS  XM
3395  2868  888 0 60  0024  3068           STA  TEMP4                   041.DO OR DONT
3396  3068  888 0 25  0008  1272           LDA  RL
3397  1272  888 0 35  4741  1893           ERS  XMH
3398  1893  888 0 30  0695  4736           LDL                GOTO
3399  0695  888 0 25  4191  1343           LDA  TEMP5
3400  1343  888 0 37  0400  0950           SHL   0400
3401  0950  888 0 35  0043  1269           ERS  XM
3402  1269  888 0 20  4756  2708           BUF  BIG02
3403  2708  888 1 64  0003  1869           STA3  0003
3404  1869  888 0 25  4191  2093           LDA  TEMP5
3405  2093  888 0 35  4740  2542           ERS  X1
3406  2542  888 0 31  0545  0545           CLL
3407  0545  888 0 82  0548  0748           TEQ  8F
3408  0748  888 0 60  1634  2069           STA  DOTAG
3409  2069  888 0 25  0108  2110           LDA  LSWOF
3410  2110  888 0 60  0089  1291           STA  LSW
3411  1291  888 0 25  4824  1926           LDA  DOVAR
3412  1926  888 1 64  0002  2269           STA3  0002         7F
3413  2269  888 0 05  2071  0673   7       LDX  9F                      042.EMPTY LLIST
3414  0673  888 0 08  0415  0277           LIR1 LLIST
```

```
3415  0277  888 0 30  1879  4229          LDL          REM
3416  1879  888 0 50  4631  2283          STL  TEMP1
3417  2283  888 0 29  0001  2469          LDA1  0001
3418  2469  888 0 35  4741  2293          ERS  XMH
3419  2293  888 0 05  000A  1897          LDX  RA
3420  1897  888 0 29  0001  2669          LDA1  0001
3421  2669  888 0 37  0400  0477          SHL  0400
3422  0477  888 0 35  0043  2869          ERS  XM
3423  2869  888 0 20  4277  2279          BUF  BIG50
3424  2279  888 1 64  0001  3069          STA3  0001
3425  3069  888 0 30  2271  4303          LDL          BR1
3426  2271  888 0 35  0435  1270          ERS  XCO
3427  1270  888 0 20  000C  0674          BUF  RX
3428  0674  888 0 64  0000  1870          STA1  0000
3429  1870  888 0 30  000C  0874          LDL  RX
3430  0874  888 0 25  4631  2483          LDA  TEMP1
3431  2483  888 0 35  4741  2493          ERS  XMH
3432  2493  888 0 82  2269  0696          TEQ  7B
3433  0696  888 0 60  4880  2132          STA  NXLOC
3434  2132  888 0 25  1934  1336          LDA#  88790      00000          IIR10 STA3
3435  1336  888 0 30  0738  0377          LDL          ASM11
3436  0738  888 1 29  0001  2070          LDA3  0001
3437  2070  888 0 30  1872  0089          LDL          LSW
3438  1872  888 0 30  2269  4686          LDL  7B          FILUP
3439  2071  888 0 60  4824  0548     9    STA  DOVAR       8F
3440  0548  888 1 29  0003  2270     8    LDA3  0003                    DSO. ANY MORE
3441  2270  888 0 60  4880  2482          STA  NXLOC
3442  2482  888 0 25  0537  2139          LDA  DOOST
3443  2139  888 0 70  1341  000A          ADD          RA
3444  1341  888 0 25  0001  2470          LDA  0001
3445  2470  888 0 35  0043  2670          ERS  XM
3446  2670  888 0 30  0024  2870          LDL  TEMP6
3447  2870  888 0 82  0473  0873          TEQ  DOEON
3448  0873  888 0 25  4376  2478          LDA  DOEOF
3449  2478  888 0 60  4170  000A          STA  DOESW       RA
```

```
3450                                                                    X.  PROCESSING FORMAT STRING
3451                                                                    X1. COMPILE 02
3452  4149  888 0 25  4196  1998   WDFMT   LDA  UNIQU
3453  1998  888 0 70  4408  3070           ADD  BIG01
3454  3070  888 0 30  2072  4357           LDL  RESET     ASM33
3462  2072  888 0 25  1274  0677   RESET   LDA  FSWOF                  X2. RESET OP.N.W.D
3463  0677  888 0 60  2479  2881           STA  FSW                        N#TEMP5  OP#TEMP6  D#TEMP7  W#TEMP8
3464  2881  888 0 30  2683  0885           LDL                CLD
3465  2683  888 0 60  4191  2693           STA  TEMP5
3466  2693  888 0 60  0024  2471           STA  TEMP6
3467  2471  888 0 60  4750  1150           STA  TEMP8     X0000
3468  1150  888 0 30  1352  4202   X0000   LDL                NXTCH       X3. NEXT CHARACTER
3469  1352  888 0 08  1150  4205           LIR1 X0000         KIND
3470  1152  888 0 25  4194  0196   X0002   LDA  TEMP7
3471  0196  888 0 37  0100  2671           SHL   0100
3472  2671  888 0 20  000C  1275           BUF  RX
3473  1275  888 0 60  4194  1150           STA  TEMP7     X0000
3474  1154  888 0 25  2356  1758   X0004   LDA  FSWON
3475  1758  888 0 60  2479  3081           STA  FSW       CYCLE
3476  1153  888 0 26  2556  2556   X0003   CLA  1F
3477  1151  888 0 26  2556  2556   X0001   CLA  1F
3478  2556  888 0 32  0500  0764   1       SHR   0500
3479  0764  888 0 37  0400  0571           SHL   0400
3480  0571  888 0 32  0900  1983           SHR   0900
3481  1983  888 0 77  1983  0586           ATL
3482  0586  888 0 60  4394  0396           STA  TEMP9
3483  0396  888 0 20  2198  2871           BUF  3F
3484  2871  888 0 60  1155  0957           STA  X0005
3485  0957  888 0 08  1173  1960           LIR1 X0023     2F
3486  1960  888 0 29  0000  3071   2       LDA1  0000
3487  3071  888 0 35  1273  1875           ERS  X89
3488  1875  888 0 82  2678  2878           TEQ  1F
3489  2878  888 0 06  9999  1960           IIR1  9999     2B
3490  2678  888 0 29  0000  2272   1       LDA1  0000
3491  2272  888 0 32  0200  1277           SHR   0200
3492  1277  888 0 35  1273  0054           ERS  X89       BIG04
3493  2198  888 0 00  2472  0000   3       JMP                0000
3494  2472  888 0 25  4394  0896           LDA  TEMP9     VAR
3495  1173  888 0 00  0975  003A   X0023   JMP  FORCE      003A          ,
3496  1172  888 0 00  0574  0038   X0022   JMP  LEFT       0038          %
3497  1171  888 0 00  0975  0118   X0021   JMP  FORCE      0118          :
3498  1170  888 0 00  0975  1031   X0020   JMP  FORCE      1031          /
3499  1169  888 0 00  0896  0415   X0019   JMP  VAR        0415          E
3500  1168  888 0 00  0896  0516   X0018   JMP  VAR        0516          F
3501  1167  888 0 00  0896  0319   X0017   JMP  VAR        0319          I
3502  1166  888 0 00  1368  0637   X0016   JMP  POP        0637          X
3503  1165  888 0 00  0896  0711   X0015   JMP  VAR        0711          A
3504  1164  888 0 00  0896  0924   X0014   JMP  VAR        0924          M
3505  1163  888 0 00  2165  0818   X0013   JMP  HOL        0818          H
```

```
3506  1162  888 0 00  0964  990H  X0012  JMP  ONWRD   990H        *
3507  1161  888 0 00  1368  0227  X0011  JMP  POP     0227        P
3508  1160  888 0 00  0962  010A  X0010  JMP  FSIGN   010A        -
3509  1159  888 0 00  0962  001C  X0009  JMP  FSIGN   001C        &
3510  1158  888 0 00  0962  0030  X0008  JMP  FSIGN   0030        +
3511  1157  888 0 00  0975  010C  X0007  JMP  FORCE   010C        )
3512  1156  888 0 00  0574  000F  X0006  JMP  LFFT    000F        (
3513  0896  888 0 60  0024  3081  VAR    STA  TEMP6   CYCLE     X4. SET OP+CYCLE.
3516  0962  888 0 60  4750  1150  FSIGN  STA  TEMP8   X0000     X5. SET SIGN INTO W
3518  1368  888 0 05  2072  1874  POP    LDX  RESET   ASMF1     X6. ASSEMBLE THIS OP
3521  0574  888 0 05  2176  1874  LEFT   LDX         ASMF1     X7. ASSEMBLE 2 LINES
3522  2176  888 0 26  0779  0779        CLA
3523  0779  888 0 05  2072  4289        LDX  RESET   ASM43
3526  0975  888 0 60  4394  0596  FORCE  STA  TEMP9              X8. ASSEMBLE TWO OPS
3527  0596  888 0 05  2398  2479        LDX          FSW
3528  2398  888 0 25  4394  2672        LDA  TEMP9
3529  2672  888 0 05  2072  2074        LDX  RESET   ASMF3
3532  2165  888 0 05  0567  1874  HOL    LDX  1F      ASMF1     X9. ASSEMBLE H OP
3533  0567  888 0 25  4191  0193  1     LDA  TEMP5
3534  0193  888 0 30  0395  0797        LDL# 99999   99995     X10.INSERT LITERAL
3535  0797  888 0 70  0008  2872        ADD  RL      -HOT
3536  2873  888 0 60  4191  2893  &HOT  STA  TEMP5
3537  2893  888 0 25  4424  2126        LDA  LIT5
3538  2126  888 0 30  0567  0369        LDL  18      FHSUB
3539  2872  888 0 82  2072  2075  -HOT  TEQ  RESET
3540  2075  888 0 75  0008  1880        SUB  RL
3541  1880  888 0 30  2072  0369        LDL  RESET   FHSUB
3542  2479  888 0 30  2356  1958  FSW    LDL  FSWON   CYC1
3543  1274  888 0 30  2356  1958  FSWOF  LDL  FSWON   CYC1
3544  3081  888 0 30  1150  1958  CYCLE  LDL  X0000   CYC1
3545  1958  888 0 25  4750  3072  CYC1   LDA  TEMP8
3546  3072  888 0 60  4191  3093        STA  TEMP5
3547  3093  888 0 25  4194  1146        LDA  TEMP7
3548  1146  888 0 60  4750  0885        STA  TEMP8   CLD
3549  0885  888 0 26  0688  0688  CLD    CLA
3550  0688  888 0 60  4194  0008        STA  TEMP7   RL
3551  2356  888 0 25  0024  2074  FSWON  LDA  TEMP6   ASMF3
3552  2074  888 0 31  1877  1877  ASMF3  CLL
3553  1877  888 0 82  000C  2080        TEQ  RX      ASMF2
3554  1874  888 0 30  4194  1296  ASMF1  LDL  TEMP7
3555  1296  888 0 50  4191  2080        STL  TEMP5   ASMF2
3556  2080  888 0 37  0300  2486  ASMF2  SHL  0300
3557  2486  888 0 20  4191  0894        BUF  TEMP5
3558  0894  888 0 37  0300  0700        SHL  0300
3559  0700  888 0 20  4750  1952        BUF  TEMP6
3560  1952  888 0 37  0200  1357        SHL  0200
3561  1357  888 0 20  4194  0796        BUF  TEMP7
3562  0796  888 0 31  1799  1799        CLL
3563  1799  888 0 50  4750  4289        STL  TEMP8   ASM43
3564  0369  888 0 50  4568  1873  FHSUB  STL  EXIT2
```

```
  3565    1873  888 J 60  4209  2911            STA  TEMP4
  3566    2911  888 J 30  2513  4674            LDL                HOLSB
- 3567    2913  888 J 25  4420  4921            LDA  TEMP3         ASM44
  3568    0964  888 J 05  4135  2080  ONWRD     LDX  SIGN'         ASMF2      X11.ASSEMBLE 99 OP
```

```
3571                                          N78     NEW  78000     00000      W.  INPUT-OUTPUT (READ,PUNCH,PRINT)
3572  4146  888 0 05  1148  1350              WDRED   LDX                1F
3573  1148  888 0 78  1348  0405                      N78  IN           0405
3574  4159  888 0 05  1761  1350              WDPCH   LDX                1F
3575  1761  888 0 78  1961  0406                      N78  OUT          0406
3576  4147  888 0 05  0949  1350              WDPRT   LDX                1F
3577  0949  888 0 78  1961  0407                      N78  OUT          0407
3578  1350  888 0 65  2152  1354              1       STX  IOOP                  W1. SET TWO OPERANDS
3579  1354  888 1 0G  0002  2158                      IIR3  0002
3580  2158  888 0 32  0600  0767                      SHR   0600
3581  0767  888 0 35  0043  2073                      ERS  XM
3582  2073  888 0 20  1178  1780                      BUF  BIG20
3583  1780  888 1 64  0000  2273                      STA3  0000
3584  2273  888 0 32  0200  3078                      SHR   0200
3585  3078  888 0 30  2280  0188                      LDL              CALPK
3586  2280  888 0 30  2682  0642                      LDL              EXPLB
3587  2682  888 0 25  0884  2686                      LDA  IO#
3588  2686  888 0 60  4117  2720                      STA  SIGN#
3589  2720  888 0 25  2722  2124                      LDA# 00040       00000
3590  2124  888 1 64  9999  2473                      STA3  9999
3591  2473  888 0 30  2275  0755                      LDL  IO1MD       INSMD
3592  0792  888 0 30  0394  2818              IO1$    LDL  IO2$        MCAL              MISSING COMMA
3593  0393  888 0 30  0595  0364              IO1.    LDL              NAMEC     W2. CALL FUNCTION
3594  0595  888 0 25  0997  1999                      LDA  IOARA
3595  1999  888 0 60  2220  2673                      STA  UASW
3596  2673  888 0 25  2475  2077                      LDA  IO2MD
3597  2077  888 1 60  0000  3073                      STA2  0000       IO2.
3598  0997  888 0 30  2199  4833              IOARA   LDL              BR2
3601  2199  888 0 29  0001  2274                      LDA1  0001                 W5. UNDIM ARRAY
3602  2274  888 0 35  0043  2474                      ERS  XM
3603  2474  888 0 30  2277  4260                      LDL              CONST
3604  2277  888 0 0G  0000  2882                      IIR1  0000
3605  2882  888 0 20  1884  2886                      BUF# 01000       05000
3606  2886  888 0 60  1093  0895                      STA  T0043
3607  0895  888 0 30  2097  4426                      LDL              REMRT
3608  2097  888 0 07  1082  4710                      IIR  T0032       DIVT2
3609  3073  888 0 30  2675  4044              IO2.    LDL              SCAN      W10.SCAN FOR (
3610  2675  888 0 30  1064  2674                      LDL  $
3611  2674  888 0 82  0394  2477                      TEQ  IO2$
3612  2477  888 0 30  4221  1123                      LDL  LPREN
3613  1123  888 0 82  4165  2326                      TEQ  IO2.1
3614  2326  888 0 65  4209  2161                      STX  TEMP2
3615  2161  888 0 25  2152  1954                      LDA  IOOP
3616  1954  888 0 30  2756  4242                      LDL              INSRT
3617  2756  888 0 05  4209  2361                      LDX  TEMP2       RESCN
3618  4165  888 0 25  0967  0569              IO2.1   LDA# 19000       00000          3F2H
3619  0569  888 0 30  0771  0173                      LDL              ASM1      W12.INTERRUPT SEQUENCE
3620  0771  888 0 25  1773  1175                      LDA  0I0%
3621  1175  888 0 30  2777  4242                      LDL              INSRT
```

```
3622  2777  888 1 07  0003  0381          IIR2  0003
3623  0381  888 0 25  2183  0985          LDA   IO3MD
3624  0985  888 1 60  0000  2874          STA2  0000
3625  2874  888 0 25  0323  2125          LDA   THREF
3626  2125  888 1 60  9999  3074          STA2  9999
3627  3074  888 0 25  0531  2733          LDA   TWO8
3628  2733  888 1 60  9998  3073          STA2  9998      IO2.
3629  1348  888 0 30  1950  2352  IN      LDL             ENTER     W14.IN
3630  1950  888 0 30  1814  3030          LDL   ANSL      ASMTR
3631  1961  888 0 30  1763  0363  OUT     LDL             GET       W15.OUT
3632  1763  888 0 30  1814  2352          LDL   ANSL      ENTER
3633  2352  888 1 29  0000  2875  ENTER   LDA3  0000
3634  2875  888 0 32  0200  2480          SHR   0200
3635  2480  888 0 35  3082  2084          ERS   X3
3636  2084  888 0 70  3086  0889          ADD#  04010     00000
3637  0889  888 0 05  000A  1294          LDX   RA
3638  1294  888 0 25  1896  0173          LDA   BIG13     ASM1          LIR5
3639  0884  888 0 30  1887  4426  IO#     LDL             REMRT     W17.EQUALS SIGN
3640  1887  888 0 30  1289  1891          LDL             IMPDO
3641  1289  888 0 06  0358  0358          CLX   #DDO1
3642  3075  888 1 25  0000  2677  IO%     LDA2  0000
3643  2677  888 0 35  3023  2877          ERS   XMC
3644  2877  888 0 30  0671  3077          LDL   DOMD                  W20.   (LIST)
3645  3077  888 0 82  2680  2880          TEQ             1F
3646  2680  888 0 05  0742  1344          LDX   TOBIO
3647  1344  888 0 65  0927  2129          STX   TOBSW
3648  2129  888 0 30  1931  0374          LDL             DO$SB
3649  1931  888 0 05  0140  2742          LDX   TOB
3650  2742  888 0 65  0927  2329          STX   TOBSW
3651  2329  888 1 0G  0001  2933          IIR3  0001
3652  2933  888 0 25  0884  2087          LDA   IO#
3653  2087  888 0 60  4117  2920          STA   SIGN#     2F
3654  2880  888 0 30  2920  1891  1       LDL   2F        IMPDO
3655  2920  888 1 25  9998  2679  2       LDA2  9998
3656  2679  888 0 30  2883  4736          LDL             GOTO
3657  2883  888 0 25  0544  1346          LDA   NINEF
3658  1346  888 0 37  0400  2153          SHL   0400
3659  2153  888 0 20  4756  2358          BUF   BIG02
3660  2358  888 0 60  4880  0982          STA   NXLOC
3661  0982  888 1 07  9997  4140          IIR2  9997      NORMX
3662  1891  888 0 50  4195  2297  IMPDO   STL   EXIT6
3663  2297  888 0 05  2299  4084          LDX             FARNL
3664  2299  888 0 60  0544  1746          STA   NINEF
3665  1746  888 0 30  1748  4686          LDL             FILUP
3666  1748  888 1 25  9999  2879          LDA2  9999
3667  2879  888 0 60  4880  4195          STA   NXLOC     EXIT6
3668  0394  888 0 05  1796  2598  I02$    LDX#  04040     00000
3669  2598  888 0 25  1896  0498          LDA   BIG13                 #30.END
3670  0498  888 0 30  0900  0173          LDL             ASM1
3671  0900  888 1 0G  9999  0904          IIR3  9999
```

```
3672    0904   BBB 0 25  2056   3079                LDA   #0FF
3673    3079   BBB 0 60  4117   0469                STA   SIGN#      EQ1$
3674                                      I03$      EQU   NO$
3675                                      I03.      EQU   I02.
```

```
3676  4144  888 0 05  1946  1948   WDFUN   LDX                1F        P.  FUNCTION AND SUBROUTINE DECLARATIONS
3677  1946  888 0 88  2223  9915           CON   88222        39915         IIR10 BUF1F LIR10 LDA1 ATL
3678  4145  888 0 05  0747  1948   WDSUB   LDX                1F
3679  0747  888 0 88  2223  0000           CON   88222        30000         IIR10 BUF1F LIR10
3680  1948  888 0 65  2651  3080   1       STX   DON                      P1. COMPILE PREAMBLE
3681  3080  888 0 05  0231  3083           LDX   BAND
3682  3083  888 0 65  4880  2332           STX   NXLOC
3683  2332  888 0 05  1419  2284           LDX   ONE15
3684  2284  888 0 65  2287  1889           STX   XLINE
3685  1889  888 0 30  2091  4044           LDL                      SCAN
3686  2091  888 1 64  0001  2484           STA3  0001
3687  2484  888 0 35  0043  2684           ERS   XM
3688  2684  888 0 70  2487  000A           ADD                      RA
3689  2487  888 0 30  0001  2884           LDL   0001
3690  2884  888 0 05  2687  2089           LDX   1F           NAME
3691  2089  888 0 65  4464  2116   NAME    STX   EXIT1
3692  2116  888 1 0G  0001  2922           IIR3  0001
3693  2922  888 0 25  2324  2526           LDA   HEAD1
3694  2526  888 0 70  0728  000A           ADD                      RA
3695  0728  888 0 50  1549  0551           STL   00000
3696  0551  888 0 25  0008  1755           LDA   RL
3697  1755  888 0 05  4974  2376           LDX   BIG10
3698  2376  888 0 32  0500  0984           SHR    0500
3699  0984  888 0 37  0500  0992           SHL    0500
3700                                       OFF    9000
3708                                       ON     9000
3709                                       ON     9001
3710                                       ON     9002
3711  0992  888 0 65  0908  2310           STX   R0108
3712  2310  888 0 60  0913  2715           STA   R0113
3713  2715  888 0 50  0948  4464           STL   R0148        EXIT1
3714                                       ON     8001
3715                                       ON     8002
3716  2687  888 0 25  2289  2291   1       LDA   BIGOG                    P2. SET UP CARD
3717  2291  888 0 30  1894  4521           LDL                      ASM37
3718  1894  888 0 25  2096  0698           LDA#  01000        20000
3719  0698  888 0 60  4196  2148           STA   UNIQU
3720  2148  888 0 25  4603  1955           LDA   BIG60
3721  1955  888 0 30  1757  4357           LDL                      ASM33
3722  1757  888 0 25  2651  3084           LDA   DON
3723  3084  888 0 30  2887  0377           LDL                      ASM11
3724  2887  888 0 25  4408  2510           LDA   BIG01
3725  2510  888 0 30  2112  4486           LDL                      FILUP
3726  2112  888 0 25  0323  2325           LDA   THREF
3727  2325  888 0 60  4860  2532           STA   NXLOC
3728  2532  888 0 25  2134  1936           LDA#  60000        10000
3729  1936  888 0 30  1138  4357           LDL                      ASM33
3730  1138  888 0 25  0540  2942           LDA#  70200        00000
3731  2942  888 0 06  0745  0745           CLX
```

```
3732  0745  888 0 30  0947  4535          LDL              ASM4
3733  0947  888 0 30  1149  0751          LDL# 34000       20000
3734  0751  888 0 50  2651  1885          STL  DON                      P3. SCAN PARAMETERS
3735  1885  888 0 30  3087  0755          LDL  PARMD       INSMD
3736  2136  888 0 07  0001  2339  PAR.    IIR   0001
3737  2339  888 0 70  2651  2085          ADD  DON
3738  2085  888 0 60  2651  4140          STA  DON         NORMX
3739  2539  888 0 30  1941  4044  PAR$    LDL              SCAN         P4. SCAN AHEAD
3740  1941  888 0 30  1743  0945          LDL  OWDIM
3741  0945  888 0 82  4042  2348          TEQ  NORM
3742  2348  888 0 30  1064  2285          LDL  $
3743  2285  888 0 82  2539  0888          TEQ  PAR$        8F           P5. GENERATE THUNKS
3746  0888  888 1 0G  9999  1292  8       IIR3  9999
3747  1292  888 0 30  1238  2485          LDL  CRAND
3748  2485  888 0 82  1288  1888          TEQ  1F
3749  1868  888 0 25  2651  2685          LDA  DON
3750  2685  888 0 75  4097  1900          SUB  KON1
3751  1900  888 0 60  2651  2885          STA  DON
3752  2885  888 0 30  2088  4521          LDL              ASM37
3753  2088  888 1 29  0001  3085          LDA3  0001
3754  3085  888 0 30  2288  4303          LDL              BR1
3755  2288  888 0 70  4392  2295          ADD  BIG70       -F8
3756  1288  888 1 07  9999  2361  1       IIR2  9999       RESCN
3757  2361  888 0 25  4030  4042  RESCN   LDA  LAST         NORM
3758  2295  888 0 30  2497  2499  -FB     LDL              FBSB1
3759  2497  888 0 25  4196  2548          LDA  UNIQU
3760  2548  888 0 60  0288  0490          STA  TMP13
3761  0490  888 0 70  0613  2488          ADD  KON3
3762  2488  888 0 60  4196  0898          STA  UNIQU
3763  0898  888 0 25  4604  2507          LDA  BIG25
3764  2507  888 0 30  2509  2312          LDL              FBSUB
3765  2509  888 0 25  4247  1349          LDA  BIG30
3766  1349  888 0 30  1351  2312          LDL              FBSUB
3767  1351  888 0 25  4277  0979          LDA  BIG50
3768  0979  888 0 30  0888  2312          LDL  88          FBSUB
3769  2296  888 0 30  1098  4303  &FB     LDL              BR1
3770  1098  888 0 30  2100  2499          LDL              FBSB1
3771  2100  888 0 05  2502  4927          LDX              INCUQ
3772  2502  888 0 70  1904  2707          ADD# 48999       90000
3773  2707  888 0 30  0888  4357          LDL  88          ASM33
3774  2499  888 0 25  4196  2748  FBSB1   LDA  UNIQU
3775  2748  888 0 70  2150  2353          ADD  BIG03
3776  2353  888 0 24  0000  2688          BUF1  0000
3777  2688  888 0 64  0000  0008          STA1  0000       RL
3778  2312  888 0 50  0379  0581  FBSUB   STL  EXIT7
3779  0581  888 0 20  0022  2888          BUF  X9
3780  2888  888 0 30  0690  4260          LDL              CONST
3781  0690  888 0 05  1892  0072          LDX              CASIN
3782  1892  888 0 25  0008  2496          LDA  RL
3783  2496  888 0 70  1298  0101          ADD  BIG24
```

```
3784  0101  888 J 30  2303  4357            LDL             ASM33
3785  2303  888 J 25  1380  1182            LDA   10080
3786  1182  888 J 30  1184  4350            LDL             ASM2
3787  1184  888 J 25  0288  0890            LDA   TMP13
3788  0890  888 J 70  4097  2300            ADD   KON1
3789  2300  888 J 60  0288  1290            STA   TMP13
3790  1290  888 J 70  2092  1295            ADD#  58999     90000
3791  1295  888 J 30  0379  4357            LDL   EXIT7     ASM33
3792  4150  888 J 30  4140  1792  WDRTN     LDL   NORMX     RETRN
3793  1792  888 J 25  2287  4736  RETRN     LDA   XLINE     GOTO
```

```
3794  0594  888 0 30  4095  3088      INIT    LDL  KON2                    2.  INITIALIZATION AND TERMINATION
3795  3088  888 0 25  1363  2365              LDA  HEAD
3796  2365  888 0 87  1768  1968              TGR  1F
3797  1968  888 0 50  0773  1775              STL  WARN                    21. SET UP HEADER TABLE
3798  1775  888 0 07  0050  1768              IIR   0050      1F
3799  1768  888 0 60  2324  2726      1       STA  HEAD1
3800  2726  888 0 75  0008  2131              SUB  RL
3801  2131  888 0 60  1363  2565              STA  HEAD
3802  2565  888 0 30  1367  0769              LDL  2F
3803  0769  888 0 05  1371  2089              LDX            NAME
3804  1371  888 0 07  4038  0774              IIR  N0008
3805  0774  888 0 60  4427  1179              STA  NWORD     INITT
3806  1367  888 0 21  1224  1958      2       ALF  MAIN*
3807  1179  888 0 07  3099  1782      INITT   IIR  MEML1                   22. CLEAR SYMBOL TABLE
3808  1782  888 0 60  4600  2489              STA  MEML
3809  2489  888 0 05  2491  2094              LDX  MEMU1
3810  2094  888 0 65  4292  1744              STX  MEMU
3811  1744  888 0 07  0099  1147              IIR   0099      1F
3812  1147  888 0 60  4420  2172      1       STA  TEMP3     2F
3813  2172  888 0 70  0974  000A      2       ADD            RA
3814  0974  888 0 08  1420  1980              LIR1 Z0000
3815  1980  888 0 34  0000  2689              LDL1  0000
3816  2689  888 0 25  2491  2294              LDA  MEMU1
3817  2294  888 0 87  2697  2699              TGR            2F     +02
3818  2697  888 0 05  2699  0301              LDX  2F
3819  0301  888 0 30  2503  4229              LDL            REM
3820  2503  888 0 25  4420  2172              LDA  TEMP3     2B
3821  2699  888 0 25  4420  1923      2       LDA  TEMP3
3822  1923  888 0 31  2926  2926              CLL
3823  2926  888 0 82  2529  2729              TEQ  1F
3824  2729  888 0 75  4097  1147              SUB  KON1      1B
3825  2529  888 0 50  0027  2889      1       STL  LEVEL
3826  2889  888 0 50  4635  0737              STL  AVAIL
3827  0737  888 0 50  4928  2180              STL  RWORD          STL  DOVAR
3828  2180  888 0 50  4579  3089              STL  IWORD
3829  3089  888 0 50  4088  0740              STL  DUMMY
3830  0740  888 0 05  2143  1145              LDX* 60090     00000
3831  1145  888 0 65  1924  1927              STX  FS
3832  1927  888 0 05  4577  1779              LDX  B10                     23. INITIALIZE COUNTERS
3833  1779  888 0 65  0503  0705              STX  P0103
3834  0705  888 0 65  0508  2710              STX  P0108
3835  2710  888 0 08  0004  2713              LIR1  0004
3836  2713  888 0 31  2316  2316              CLL  1F
3837  2316  888 0 26  2123  2123      1       CLA
3838  2123  888 0 24  1750  2552              BUF1 W0000
3839  2552  888 0 64  1750  2752              STA1 W0000
3840  2752  888 0 06  9999  2956              IIR1  9999
3841  2956  888 0 82  1959  2316              TEQ            1B
3842  1959  888 0 25  4408  1890              LDA  BIG01
```

```
3843   1890  888 J 60  4196  1898          STA  UNIQU
3844   1898  888 J 70  4408  2512          ADD  BIG01
3845   2512  888 0 60  0231  2090          STA  BAND
3846   2090  888 J 70  4408  2712          ADD  BIG01
3847   2712  888 0 60  4198  2350          STA  COMON
3848   2350  888 0 05  4277  1979          LDX  BIG50
3849   1979  888 0 65  4456  2290          STX  NZONS
3850   2290  888 0 05  4623  2525          LDX  BIG05
3851   2525  888 0 65  4094  2146          STX   4094
- 3852   2146  888 0 65  4096  2798          STX   4096
- 3853   2798  888 0 65  4098  2490          STX   4098
3854   2490  888 0 50  4374  2127          STL  OLDLC
3855   2127  888 0 50  4701  2553          STL  TEMPS
3856   2553  888 0 07  0004  1957          IIR   0004
3857   1957  888 0 60  4880  1982          STA  NXLOC
3858   1982  888 0 07  0010  1785          IIR   0010
3859   1785  888 0 60  2287  2690          STA  XLINE
3860   2690  888 0 07  4183  2494          IIR  50003
3861   2494  888 0 60  4980  2732          STA  ASMST
3862                                       OFF   9000
3866                                       ON    9000
3867                                       ON    9001
3868                                       ON    9002
3869                                       OFF   8001
3870                                       OFF   8002
3871   2732  888 0 50  0928  2130          STL  R0128
3872                                       ON    8001
3873                                       ON    8002
3874   2130  888 1 02  1520  2334          LIR2 MODE
3875   2334  888 1 08  1190  4140          LIR3 RAND      NORMX
3876   4143  888 J 30  1345  1792  WDEND   LDL            RETRN     250.END IS SENSED
3877   1345  888 0 30  1347  1627          LDL            ADDNX
3878   1347  888 0 30  1749  1951          LDL            ASMSD
3879   1749  888 J 25  0908  2910          LDA  RWD1
3880   2910  888 J 35  0009  2890          ERS  H5
3881   2890  888 J 60  0908  2912          STA  RWD1
3882   2912  888 J 25  2114  2516          LDA  1F
3883   2516  888 J 20  2324  000A          BUF  HEAD1     RA
3884   2114  888 1 02  0000  2917  1       LIR2  0000                 251.PUNCH HEADERS
3885   2917  888 0 25  0231  3090          LDA  BAND
- 3886   3090  888 J 70  4541  1944          ADD  KN200
3887   1944  888 0 05  4198  2550          LDX  COMON
3888   2550  888 J 32  0400  2157          SHR   0400
3889   2157  888 J 35  4724  2576          ERS  XC
3890   2576  888 J 20  2178  2380          BUF# 71000     10000
3891   2380  888 1 60  1547  1949          STA2 09998
3892   1949  888 J 25  4196  2998          LDA  UNIQU
3893   2998  888 J 37  0200  2691          SHL   0200
3894   2691  888 J 32  0600  2500          SHR   0600
3895   2500  888 J 35  3023  2891          ERS  XMC
```

```
3896  2891  888 0 20  2212  3091          BUF  BIG40
3897  3091  888 1 60  1548  2750          STA2 09999
3898  2750  888 0 06  2753  2753          CLX
3899  2753  888 0 30  2155  2156          LDL            SHEAD
3900  2155  888 0 25  2357  2159          LDA  1F
3901  2159  888 0 05  2561  1963          LDX  2F
3902  1963  888 0 60  0503  0905          STA  P0103
3903  0905  888 0 65  0508  2913          STX  P0108     3F
3904                                      OFF   9000
3911                                      ON    9000
3912  2357  888 0 64  A7FA  27G0     1    CON  64A7F     A27G0
3913  2561  888 0 31  0200  1110     2    CON  31020     01110
3914                                      ON    9001
3915                                      ON    9002
3916                                      ON    8001
3917                                      ON    8002
3918  2913  888 1 25  1549  2151     3    LDA2 00000
3919  2151  888 0 31  2154  2154          CLL
3920  2154  888 0 82  2557  2757          TEQ  3F
3921  2757  888 0 05  4577  2179          LDX  B10
3922  2179  888 0 30  0781  4533          LDL            PRNT
3923  0781  888 1 25  1549  2351          LDA2 00000
3924  2351  888 0 30  2953  4337          LDL            ASM5
3925  2953  888 1 07  9999  2957          IIR2 9999
3926  2957  888 0 31  2160  2160          CLL
3927  2160  888 0 82  2163  2913          TEQ            3B
3928  2163  888 1 02  0050  2913          LIR2 0050      3B
3929  2557  888 0 30  2359  1951     3    LDL            ASM5D      252•READ NEXT CARD
3930  2359  888 0 25  2761  2363          LDA  1F
3931  2363  888 0 05  2765  0337          LDX            3U
3932  2765  888 0 30  0135  0937          LDL  CHALT     POUT
3933  2761  888 0 25  0011  2292     1    LDA  HWD1
3934  2292  888 0 30  2694  2696          LDL  *LOAD
3935  2696  888 0 82  2899  0594          TEQ  PASS2     INIT
3936  2694  888 0 82  6638  3801  *LOAD   NUM  *ROOT      L 01
3937  2899  888 0 30  0501  0937  PASS2   LDL  HALT      POUT
3938  0937  888 0 50  1976  2378  POUT    STL  EXIT8
3939  2378  888 0 30  0050  2492          LDL  LC                  SUBROUTINE TO EJECT CARDS AND PAPER
3940  2492  888 0 85  2894  1971          MUL  1F
3941  1971  888 0 70  1973  000A          ADD            RA
3942  1973  888 0 16  0049  2580          PFD   0049     -POT
3943  2581  888 0 67  3333  000A  &POT    HLT   3333     RA
3944  2580  888 0 30  2182  1784  -POT    LDL            ASM5C
3945  2182  888 0 30  1984  1784          LDL            ASM5C
3946  1984  888 0 30  0786  1784          LDL            ASM5C
3947  0786  888 0 16  0017  0790          PFD   0017     -POT1
3948  0791  888 0 67  3333  000A  &POT1   HLT   3333     RA
3949  0790  888 0 16  0086  0794  -POT1   PFD   0086     -POT2
3950  0795  888 0 67  3333  000A  &POT2   HLT   3333     RA
3951  0794  888 0 30  1976  1784  -POT2   LDL   EXIT8    ASM5C
```

```
3952  2894  888 1 00  0050  0000   1          CON1 00005     00000
3953  0501  888 0 25  0773  1975   HALT       LDA  WARN
3954  1975  888 0 70  000A  2780              ADD  RA        -PAS2
3955  2781  888 0 05  2383  1985   &PAS2      LDX  1F        2F
3956  1985  888 0 72  000C  000C   2          HCC  RX        RX
- 3957  2383  888 0 42  0787  1985   1          HBT                    2B
3958  0787  888 0 96  0000  2692              HBU  HDW2
3959  2692  888 0 72  000A  1895              HCC  RA
3960  1895  888 0 96  0000  2892              HBU  HDW2      3F
3961  2892  888 0 07  2896  2095   3          IIR  2F
3962  2095  888 0 60  2892  2781              STA  3B        &PAS2
3963  2896  888 1 07  1548  2700   2          IIR2 09999
3964  2700  888 0 08  0000  0021              LIR1  0000     HDW3
3965  2780  888 0 67  0A2A  0A2A   -PAS2      HLT   0A2A      0A2A
3966  1784  888 0 50  4568  3092   ASM5C      STL  EXIT2     1F
3967  3092  888 0 26  2495  2495   1          CLA
3968  2495  888 0 30  2897  4337              LDL  2F        ASM5
3969  1951  888 0 50  4568  2897   ASM5D      STL  EXIT2     2F
3970  2897  888 0 07  4181  2900   2          IIR  50001
3971  2900  888 0 30  4980  2932              LDL  ASM5T
3972  2932  888 0 82  4568  3092              TEQ  EXIT2     1B
3973  2491  888 0 00  4000  0000   MEMU1      JMP  MEMU2      0000
3974  4514  888 0 05  2780  2382   ALARM      LDX  -PAS2                 ERROR PRINTOUT SUBROUTINE
3975  2382  888 0 65  0501  1628              STX  HALT      PANIC
3976                                          OFF   8001
3977                                          OFF   9000
3984                                          ON    9000
3985                                          ON    9001
3986                                          ON    8001
```

```
   3987   4012  888 0 07  0001  3094      C0002    IIR   0001                        E.  EQUIVALENCE DECLARATIONS.
   3988   3094  888 0 60  4209  2314               STA   TEMP2
   3989   2314  888 0 26  1918  1918               CLA
   3990   1918  888 0 60  4420  2323               STA   TEMP3
   3991   2323  888 0 25  4631  2534               LDA   TEMP1     2F
   3992   2534  888 0 05  000A  1938      2        LDX   RA
   3993   1938  888 0 70  4974  2977               ADD   BIG10     -ASN2
   3994   2978  888 0 35  4741  0593      &ASN2    ERS   XMH
   3995   0593  888 0 75  4623  2695               SUB   BIG05
   3996   2695  888 0 60  4624  2327               STA   TEMP4
   3997   2327  888 0 70  4209  1362               ADD   TEMP2
   3998   1362  888 0 31  2965  2965               CLL                               E1. SEARCH THROUGH CHAIN
41 3999   2965  808 0 87  3096  2168               TGR   1F    +03
   4000   2168  888 0 07  0001  3096               IIR    0001     1F
   4001   3096  888 0 60  4209  2514      1        STA   TEMP2     3F
   4002   2514  888 0 25  4420  2523      3        LDA   TEMP3
 - 4003   2523  888 0 75  4624  2578               SUB   TEMP4
   4004   2578  888 0 87  1181  1781               TGR   1F
   4005   1781  888 0 50  4420  2895               STL   TEMP3     6F
   4006   1181  888 0 60  4420  2895      1        STA   TEMP3     6F
   4007   2977  888 0 70  4603  3097      -ASN2    ADD   BIG60     -ASN3
   4008   3098  888 0 37  0400  1705      &ASN3    SHL    0400
   4009   1705  888 0 35  0043  2098               ERS   XM
   4010   2098  888 0 30  4209  2714               LDL   TEMP2
   4011   2714  888 0 87  2118  2171               TGR             1F      +54
   4012   2118  888 0 60  4209  2171               STA   TEMP2     1F
   4013   2171  888 0 77  2171  1174      1        ATL
   4014   1174  888 0 07  HHHH  2778               IIR    HHHH
   4015   2778  888 0 39  0001  2298               ERS1   0001
   4016   2298  888 0 75  0008  2703               SUB   RL
   4017   2703  888 0 30  4420  2723               LDL   TEMP3
   4018   2723  888 0 87  2527  2980               TGR             1F      +54
   4019   2527  888 0 60  4420  2980               STA   TEMP3     1F
   4020   2980  888 0 25  000C  3097      1        LDA   RX        -ASN3
   4021   2895  888 0 32  0600  3097      6        SHR    0600     -ASN3
   4022   3097  888 0 30  3099  4303      -ASN3    LDL             BR1
   4023   3099  888 0 30  4631  2734               LDL   TEMP1
   4024   2734  888 0 82  1137  2534               TEQ             2B
   4025   1137  888 0 25  4196  2948               LDA   UNIQU
   4026   2948  888 0 70  4209  1762               ADD   TEMP2
   4027   1762  888 0 77  1762  0566               ATL
   4028   0566  888 0 70  4420  2173               ADD   TEMP3
   4029   2173  888 0 60  4196  2399               STA   UNIQU
   4030   2399  888 0 25  4545  2498               LDA   ASGN1     EQASN
   4031   2498  888 0 50  4631  2934      EQASN    STL   TEMP1                       E2. ASSIGN CHAIN
   4032   2934  888 0 60  4464  0766               STA   EXIT1
   4033   0766  888 0 25  4740  1992               LDA   X1
   4034   1992  888 0 35  0008  1996               ERS   RL
   4035   1996  888 0 60  4420  2698               STA   TEMP3
```

```
4036  2698  888 0 06  0000  2702          IIR1  0000
4037  2702  888 0 60  4209  2914          STA   TEMP4
4038  2914  888 0 29  0000  2898          LDA1  0000
4039  2898  888 0 70  4392  2345          ADD   BIG70      -EQV3
4040  2346  888 0 37  0400  2354  &EQV3    SHL   0400
4041  2354  888 0 35  0043  0701          ERS   XM
4042  0701  888 0 70  4631  0535          ADD   TEMP1
4043  0535  888 0 60  4631  2345          STA   TEMP1      -EQV3
4044  2345  888 0 29  0000  1901  -EQV3    LDA1  0000     2F
4045  1901  888 0 05  000A  1905  2        LDX   RA
4046  1905  888 0 70  4974  2727          ADD   BIG10      -EQV1
4047  2728  888 0 35  4741  2343  &EQV1    ERS   XMH
4048  2343  888 0 70  4631  2184          ADD   TEMP1
4049  2184  888 0 75  4623  2101          SUB   BIG05
4050  2101  888 0 60  4631  0735          STA   TEMP1
4051  0735  888 0 32  0600  2144          SHR   0600       3F
4052  2727  888 0 70  4603  2558  -EQV1    ADD   BIG60      -EQV2
4053  2559  888 0 37  0400  1366  &EQV2    SHL   0400
4054  1366  888 0 35  0043  2301          ERS   XM         1F
4055  2558  888 0 07  0001  2301  -EQV2    IIR   0001       1F
4056  2301  888 0 75  4631  0935  1        SUB   TEMP1
4057  0935  888 0 77  0935  2138          ATL
4058  2138  888 0 25  000C  2543          LDA   RX
4059  2543  888 0 70  4392  2195          ADD   BIG70      -EQV4
4060  2196  888 0 25  4247  2501  &EQV4    LDA   BIG30      1F
4061  2195  888 0 35  4724  2501  -EQV4    ERS   XC         1F
4062  2501  888 0 20  000B  2105  1        BUF   RL
4063  2105  888 0 64  0000  2701          STA1  0000
4064  2701  888 0 35  4740  2743          ERS   X1
4065  2743  888 0 30  4420  2372          LDL   TEMP3
4066  2372  888 0 82  2175  2375          TEQ   1F
4067  2375  888 0 30  4464  0528          LDL   EXIT1      8ED
4068  2175  888 0 25  000C  2144  1        LDA   RX         3F
4069  2144  888 0 35  0043  2901  3        ERS   XM
4070  2901  888 0 30  4209  2915          LDL   TEMP2
4071  2915  888 0 82  4464  2318          TEQ   EXIT1
4072  2318  888 0 70  2923  000A          ADD               RA
4073  2923  888 0 08  0000  2345          LIR1  0000       -EQV3
4074  4153  888 0 30  2355  2758  WDEQU     LDL   EQ1MD
4075  2758  888 1 50  0001  2902          STL2  0001
4076  2902  888 0 25  3022  2903          LDA   DUA
4077  2903  888 0 60  2220  2104          STA   UASW
4078  2104  888 1 07  0001  2908          IIR2  0001       EQ1*
4079  2908  888 0 30  2716  4044  EQ1*      LDL               SCAN
4080  2716  888 0 30  4221  2524          LDL   LPREN
4081  2524  888 0 82  2927  0526          TEQ               MLP
4082  2927  888 0 31  2330  2330          CLL
4083  2330  888 1 50  0001  2304          STL2  0001
4084  2304  888 0 50  2907  2709          STL   RRRR
4085  2709  888 0 50  2916  2518          STL   ZLINK
```

```
4086  2518  BBB 1 50  0003  2504                STL2  0003
4087  2504  BBB 0 30  2400  2704                LDL   EQUMD
4088  2704  BBB 0 05  2909  4235                LDX   0EQU&      MDOP
4089  2904  BBB 0 30  4140  2943  EQU.          LDL   NORMX      EQSVB
4090  2943  BBB 0 50  4464  1766  EQSVB         STL   EXIT1                 E3. 'EQUIVALENCE'
4091  1766  BBB 1 29  0000  2305                LDA3  0000
4092  2305  BBB 0 70  4301  2554                ADD   BIG90      -EQ.
4093  2555  BBB 0 30  2958  0528  &EQ.          LDL   8F         8ED
4094  2554  BBB 0 30  2759  4833  -EQ.          LDL              8R2
4095  2759  BBB 0 35  4741  0793                ERS   XMH
4096  0793  BBB 0 05  000A  1797                LDX   RA
4097  1797  BBB 0 31  2505  2505                CLL
4098  2505  BBB 0 82  2718  2918                TEQ   1F
4099  2918  BBB 0 35  4740  2344                ERS   X1
4100  2344  BBB 0 30  4756  2959                LDL   BIG02
4101  2959  BBB 0 82  1962  2162                TEQ   2F
4102  2162  BBB 1 25  9999  2705                LDA2  9999
4103  2705  BBB 0 31  2724  2724                CLL
4104  2724  BBB 0 82  1128  2555                TEQ              &EQ.
4105  1128  BBB 1 65  9999  2905                STX2  9999
4106  2905  BBB 0 0G  0000  2924                IIR1  0000
4107  2924  BBB 1 60  9998  2725                STA2  9998       3F
4108  2718  BBB 0 0G  0000  2725  1             IIR1  0000       3F
4109  2725  BBB 1 30  9997  2599  3             LDL2  9997       4F
4110  2599  BBB 1 60  9997  2799  4             STA2  9997
4111  2799  BBB 0 25  2907  2925                LDA   RRRR
4112  2925  BBB 0 32  0400  1135                SHR   0400
4113  1135  BBB 0 35  4724  2776                ERS   XC
4114  2776  BBB 0 05  000A  1981                LDX   RA
4115  1981  BBB 0 26  2384  2384                CLA
4116  2384  BBB 0 82  0987  1787                TEQ              1F
4117  0987  BBB 0 0G  0000  0391                IIR1  0000
4118  0391  BBB 0 60  2916  1787                STA   ZLINK      1F
4119  1787  BBB 0 29  0000  1328  1             LDA1  0000
4120  1328  BBB 0 35  0435  1928                ERS   XC0
4121  1928  BBB 0 20  000B  1335                BUF   RL
4122  1335  BBB 0 20  4756  2360                BUF   BIG02
4123  2360  BBB 0 20  000C  1364                BUF   RX
4124  1364  BBB 0 64  0000  2958                STA1  0000       8F
4125  1962  BBB 0 29  0000  2128  2             LDA1  0000
4126  2128  BBB 0 70  4392  2545                ADD   BIG70      -EQ1.
4127  2545  BBB 0 07  HHHH  2149  -EQ1.         IIR   HHHH
4128  2149  BBB 0 39  0000  2725                ERS1  0000       3B
4129  2546  BBB 0 37  0400  2754  &EQ1.         SHL   0400
4130  2754  BBB 0 35  0043  2328                ERS   XM
4131  2328  BBB 0 77  2328  2331                ATL
4132  2331  BBB 0 07  HHHH  1935                IIR   HHHH
4133  1935  BBB 0 35  2907  2528                ERS   RRRR
4134  2528  BBB 0 82  2545  2531                TEQ   -EQ1.
4135  2531  BBB 0 75  000B  2336                SUB   RL
```

```
4136  2336  888 0 60  4209  2961          STA  TEMP2
4137  2961  888 0 70  4623  2976          ADD  BIG05
4138  2976  888 0 20  4301  2928          BUF  BIG90
4139  2928  888 0 60  4631  2135          STA  TEMP1
4140  2135  888 1 25  9997  2999          LDA2  9997
4141  2999  888 0 31  2929  2929          CLL
4142  2929  888 0 50  2907  2530          STL  RRRR
4143  2530  888 0 82  2335  2535          TEQ                 1F
4144  2335  888 0 07  0001  2338          IIR   0001
4145  2338  888 0 70  4600  2954          ADD  MEML
4146  2954  888 0 60  2916  2730          STA  ZLINK
4147  2730  888 0 26  2535  2535          CLA  1F
4148  2535  888 0 06  2538  2538     1    CLX
4149  2538  888 0 32  0400  1745          SHR   0400
4150  1745  888 0 20  4631  2583          BUF  TEMP1
4151  2563  888 0 77  2583  1786          ATL
4152  1786  888 0 07  0001  0789          IIR   0001
4153  0789  888 0 70  4600  2930          ADD  MEML
4154  2930  888 0 60  4420  2572          STA  TEMP3
4155  2572  888 0 70  1774  000A          ADD                 RA
4156  1774  888 0 50  0000  2731          STL   0000
4157  2731  888 0 25  4623  2575          LDA  BIG05
4158  2575  888 0 75  4209  2931          SUB  TEMP2
4159  2931  888 0 20  4301  2755          BUF  BIG90
4160  2755  888 0 60  4631  2783          STA  TEMP1
4161  2783  888 0 07  HHHH  1986          IIR   HHHH
4162  1986  888 0 39  0000  2735          ERS1  0000
4163  2735  888 0 32  0400  2544          SHR   0400
4164  2544  888 0 20  4631  2983          BUF  TEMP1
4165  2983  888 0 77  2983  2186          ATL
4166  2186  888 0 07  0002  0989          IIR   0002
4167  0989  888 0 70  4600  2935          ADD  MEML
4168  2935  888 0 60  4600  2952          STA  MEML
4169  2952  888 0 70  2955  000A          ADD                 RA
4170  2955  888 0 50  0000  2536          STL   0000
4171  2536  888 0 25  4600  2560          LDA  MEML
4172  2560  888 0 30  4420  2599          LDL  TEMP3          4B
4173  2958  888 1 0G  9999  4464     8    IIR3  9999          EXIT1
4174  2028  888 1 29  0000  2736  AEQU    LDA3  0000                    CHECK THAT SUBSCRIPT WAS CONSTANT
4175  2736  888 0 30  1051  2936          LDL  CON0
4176  2936  888 0 82  2739  2939          TEQ  1F             3F
4177  2939  888 0 30  2141  0528     3    LDL  2F             8E0
4178  2739  888 1 25  9999  1337     1    LDA2  9999
4179  1337  888 0 70  4097  2950          ADD  KON1
4180  2950  888 0 30  1815  1937          LDL  FOR9S
4181  1937  888 0 87  0940  2939          TGR                 3B
4182  0940  888 0 60  2907  2141          STA  RRRR           2F
4183  2141  888 1 07  9996  1945     2    IIR2  9996
4184  1945  888 1 0G  9999  2349          IIR3  9999
4185  2349  888 0 07  HHHH  2760          IIR   HHHH
```

```
4186  2760  888 1 39  0000  2137          ERS3  0000
4187  2137  888 1 64  0000  4140          STA3  0000      NORMX
4188  4156  888 0 30  2960  2943  EQU%    LDL             EQSVB
4189  2960  888 0 25  2916  2337          LDA   ZLINK
4190  2337  888 0 31  1140  1140          CLL
4191  1140  888 0 82  2744  2944          TEQ   4F        1F
4192  2744  888 0 30  2746  0528  4       LDL   8F        8ED
4193  2944  888 0 30  2946  4641  1       LDL             8R
4194  2946  888 0 70  000A  2562          ADD   RA        -EQU%
4195  2563  888 1 25  9997  2537  &EQU%   LDA2  9997
4196  2537  888 0 06  1340  1340          CLX
4197  1340  888 0 32  0400  1747          SHR   0400      1F
4198  2562  888 1 25  9997  1747  -EQU%   LDA2  9997      1F
4199  1747  888 0 24  0000  2737  1       BUF1  0000
4200  2737  888 0 64  0000  2937          STA1  0000
4201  2937  888 1 30  9999  2738          LDL2  9999
4202  2738  888 0 26  2341  2341          CLA
4203  2341  888 0 82  2746  2145          TEQ   8F
4204  2145  888 0 25  0054  2938          LDA   BIG04
4205  2938  888 0 87  2541  2744          TGR             4B
4206  2541  888 1 25  9998  1740          LDA2  9998
4207  1740  888 0 20  2745  000A          BUF             RA
4208  2745  888 0 08  0000  2551          LIR1  0000
4209  2551  888 0 25  2746  2498          LDA   8F        EQASN
4210  2746  888 1 07  9996  4140  8       IIR2  9996      NORMX
4211                      EQU%  KON*E     EQU   MRP
4212  1856  888 1 09  9999  1940  KON*E   LDX3  9999      ROUTINE FOR N*() WHERE N IS A COSTANT
4213  1940  888 0 32  0100  2945          SHR   0100
4214  2945  888 0 70  000A  2762          ADD   RA        -MUL
4215  2762  888 0 32  0300  2368  -MUL    SHR   0300
4216  2368  888 0 70  000A  2373          ADD   RA        -MUL1
4217  2374  888 0 07  HHHH  2379  &MUL1   IIR   HHHH
4218  2379  888 1 39  9999  2140          ERS3  9999
4219  2140  888 0 70  1947  000A          ADD             RA
4220  1947  888 0 25  0001  2340          LDA   0001
4221  2340  888 0 31  2147  2147          CLL
4222  2147  888 0 82  1814  2751          TEQ   ANSL
4223  2751  888 0 06  2362  2362          CLX
4224  2362  888 0 32  0500  1770          SHR   0500
4225  1770  888 0 82  2573  2773          TEQ   1F
4226  2773  888 0 32  0100  2579          SHR   0100
4227  2579  888 0 82  2582  2782          TEQ   2F
4228  2782  888 0 32  0100  2386          SHR   0100
4229  2386  888 0 82  1789  1989          TEQ   3F
4230  1969  888 0 32  0100  1793          SHR   0100
4231  1793  888 0 82  2396  2763          TEQ   4F        &MUL
4232  2582  888 0 07  0100  2573  2       IIR   0100      1F
4233  1789  888 0 07  0200  2573  3       IIR   0200      1F
4234  2396  888 0 07  0300  2573  4       IIR   0300      1F
4235  2573  888 0 60  2775  2779  1       STA   PAR3
```

```
4236  2779  888 0 30  000C  2584          LDL  RX
4237  2584  888 0 25  4974  2540          LDA  BIG10
4238  2540  888 0 82  2347  2547          TEQ  1F
4239  2547  888 0 70  000A  2962          ADD  RA
4240  2962  888 0 82  2347  1966          TEQ  1F
4241  1966  888 0 31  0969  0969          CLL
4242  0969  888 0 25  4305  2740          LDA  LITA      2F
4243  2740  888 0 32  0900  2963    2     SHR   0900
4244  2963  888 0 82  2166  2366          TEQ  2F
4245  2366  888 0 32  0F00  2740          SHR   0F00     2B
4246  2166  888 0 25  000C  1970    2     LDA  RX
4247  1970  888 0 30  2772  4260          LDL            CONST
4248  2772  888 0 0G  0000  2979          IIR1  0000
4249  2979  888 0 20  4723  2940          BUF  KON.5
4250  2940  888 1 64  9999  2741          STA3  9999
4251  2741  888 0 06  2747  2747          CLX
4252  2747  888 0 0B  1716  2951          LIR1 J0016     3F
4253  2347  888 0 0B  1720  2951    1     LIR1 J0020     3F
4254  2951  888 1 0G  9999  1764    3     IIR3  9999
4255  1764  888 1 29  0001  2941          LDA3  0001
4256  2941  888 0 30  4215  2004          LDL  OPX       UNOP1
4257  2763  888 0 0B  1034  0199  &MUL    LIR1 Q0034     BINSB
4258  2373  888 0 0B  1034  0199  -MUL1   LIR1 Q0034     BINSB
4259  1316  888 0 07  0100  2947  I0016   IIR   0100     1F
4260  2947  888 0 70  2775  2181    1     ADD  PAR3
4261  2181  888 0 70  2784  0930          ADD  BIG37     TAS32
4262  1317  888 0 25  0104  2549  I0017   LDA  PAR1
4263  2549  888 0 30  1178  2381          LDL  BIG20
4264  2381  888 0 82  2984  2185          TEQ            2F
4265  2984  888 0 25  2586  0588          LDA# 70000     A0000
4266  0588  888 0 30  2185  4556          LDL  2F        ASM32
4267  2165  888 0 30  2775  2981    2     LDL  PAR3
4268  2981  888 0 26  2385  2385          CLA
4269  2365  888 0 82  0130  2947          TEQ  IX        1B
4270  1628  888 0 50  2566  2568  PANIC   STL  -ALRM
4271  2568  888 0 0B  1250  2371          LIR1 10000     5F
4272  2371  888 0 06  1974  1974    5     CLX
4273  1974  888 0 32  0800  2585          SHR   0800
4274  2585  888 0 65  1987  2189          STX  WDS
4275  2189  888 0 37  0400  2596          SHL   0400     4F
4276  2596  888 0 60  2749  1964    4     STA  WD
4277  1964  888 0 70  2766  000A          ADD            RA
4278  2706  888 0 25  1650  2949          LDA  30000
4279  2949  888 0 60  2164  2966          STA  ALF
4280  2966  888 0 06  1369  1369          CLX
4281  1369  888 0 32  0500  2982          SHR   0500
4282  2982  888 0 37  0500  0990          SHL   0500
4283  0990  888 0 04  0000  0000          JMP1  0000
4284  1256  888 0 60  0533  2364  10006   STA  THETA      1F
4285  1254  888 0 60  0533  2364  10004   STA  THETA      1F
```

```
4286  1252  888 0 60  0933  2364   10002   STA  THETA     1F
4287  1250  888 0 60  0533  2364   10000   STA  THETA     1F
4288  2364  888 0 65  0139  2564   1       STX  CHI       3F
4289  1257  888 0 32  0500  2764   10007   SHR   0500     2F
4290  1255  888 0 32  0500  2764   10005   SHR   0500     2F
4291  1253  888 0 32  0500  2764   10003   SHR   0500     2F
4292  1251  888 0 32  0500  2764   10001   SHR   0500     2F
4293  2764  888 0 20  0533  2964   2       BUF  THETA
4294  2964  888 0 32  0F00  2785           SHR   0F00
4295  2785  888 0 20  0139  1767           BUF  CHI
4296  1767  888 0 04  0008  0008           JMP1  0008
4297  1265  888 0 60  0650  1967   10015   STA  20050
4298  1967  888 0 65  0655  2564           STX  20055     3F
4299  1263  888 0 60  0765  2167   10013   STA  20165
4300  2167  888 0 65  0770  2564           STX  20170     3F
4301  1261  888 0 60  0681  2367   10011   STA  20081
4302  2367  888 0 65  0686  2564           STX  20086     3F
4303  1259  888 0 60  0600  2767   10009   STA  20000
4304  2767  888 0 65  0605  2564           STX  20005     3F
4305  2564  888 0 0G  0001  2768   3       IIR1  0001
4306  2768  888 0 25  2164  2967           LDA  ALF
4307  2967  888 0 70  0015  2968           ADD  H10       -AL2
4308  2969  888 0 07  0001  2972   &AL2    IIR   0001
4309  2972  888 0 70  2749  2596           ADD  WD        4B
4310  2968  888 0 25  1987  2371   -AL2    LDA  WDS       5B
4311  1258  888 0 25  0050  1769   10008   LDA  LC
4312  1769  888 0 70  0054  2169           ADD  BIG04     -AL1
4313  2170  888 0 60  0050  1969   &AL1    STA  LC
4314  1969  888 0 11  0618  2566           PRN  20018     -ALRM
4315  2169  888 0 60  0050  2369   -AL1    STA  LC
4316  2369  888 0 11  0602  2566           PRN  20002     -ALRM
4317  2567  888 0 00  0190  0190   &ALRM   JMP  &CRD3
4318  0739  888 0 00  0000  0000   20139   ZON
4319  0623  888 0 00  0000  0000   20023   ZON
4320  0708  888 0 00  0000  0000   20108   ZON
4321  0646  888 0 00  0000  0000   20046   ZON
4322  0730  888 0 00  0000  0000   20130   ZON
4323  0614  888 0 00  0000  0000   20014   ZON
4324  0699  888 0 00  0000  0000   20099   ZON
4325  0783  888 0 00  0000  0000   20183   ZON
4326  0667  888 0 00  0000  0000   20067   ZON
4327                                       OFF   9000
4376                                       ON    9000
4377  1650  888 1 00  0000  0000   30000   CON1  00000     00000
4378  1651  888 1 03  0009  C600   30001   CON1  03000     9C600
4379  1652  888 1 31  2202  6110   30002   CON1  31220     26110
4380  1653  888 1 02  0007  7F00   30003   CON1  02000     77F00
4381  1654  888 1 00  1106  A770   30004   CON1  00110     6A770
4382  1655  888 1 01  101A  2282   30005   CON1  01101     A2282
4383  1656  888 1 23  0007  7900   30006   CON1  23000     77900
```

```
4384  1657  BBB 1 03  2009  7700  30007  CON1 03200  97700
4385  1658  BBB 1 20  0007  3900  30008  CON1 20000  73900
4386  1659  BBB 1 00  2009  3700  30009  CON1 00200  93700
4387  1660  BBB 1 01  0008  2000  30010  CON1 01000  82000
4388  1661  BBB 0 32  0232  1874  30011  CON  32023  21874
4389  1662  BBB 1 02  1009  6500  30012  CON1 02100  96500
4390  1663  BBB 0 11  0117  6771  30013  CON  11011  76771
4391  1664  BBB 1 10  1302  9840  30014  CON1 10130  29840
4392  1665  BBB 1 23  0007  9900  30015  CON1 23000  79900
4393  1666  BBB 1 03  2009  9700  30016  CON1 03200  99700
4394  1667  BBB 1 00  0209  3370  30017  CON1 00020  93370
4395  1668  BBB 1 03  312A  1427  30018  CON1 03312  A1427
4396  1669  BBB 1 22  0021  77A1  30019  CON1 22002  177A1
4397  1670  BBB 1 10  0021  8667  30020  CON1 10002  18667
4398  1671  BBB 1 03  101A  1808  30021  CON1 03101  A1808
4399  1672  BBB 1 10  1132  9544  30022  CON1 10113  29544
4400  1673  BBB 1 01  102A  969A  30023  CON1 01102  A969A
4401  1674  BBB 1 20  3301  A240  30024  CON1 20330  1A240
4402  1675  BBB 0 12  102B  72A6  30025  CON  12102  B72A6
4403  1676  BBB 0 31  0104  4A79  30026  CON  31010  44A79
4404  1677  BBB 1 10  0007  0000  30027  CON1 10000  70000
4405  1678  BBB 0 01  0128  8A27  30028  CON  01012  88A27
4406  1679  BBB 1 20  0006  F000  30029  CON1 20000  6F000
4407  1680  BBB 0 10  2131  8674  30030  CON  10213  18674
4408  1681  BBB 1 22  3007  6400  30031  CON1 22300  76400
4409  1682  BBB 0 00  1106  9779  30032  CON  00110  69779
4410  1683  BBB 1 21  0006  5000  30033  CON1 21000  65000
4411  1684  BBB 1 33  0102  69G0  30034  CON1 33010  269G0
4412  1685  BBB 0 00  002F  96A6  30035  CON  00002  F96A6
4413  1686  BBB 1 10  0207  9860  30036  CON1 10020  79860
4414  0734  BBB 0 00  0000  0000  20134  ZON
4415  0618  BBB 0 00  0000  0000  20018  ZON
4416  0703  BBB 0 00  0000  0000  20103  ZON
4417  0641  BBB 0 00  0000  0000  20041  ZON
4418  0725  BBB 0 00  0000  0000  20125  ZON
4419  0609  BBB 0 00  0000  0000  20009  ZON
4420  0694  BBB 0 00  0000  0000  20094  ZON
4421  0778  BBB 0 00  0000  0000  20178  ZON
4422  0662  BBB 0 00  0000  0000  20062  ZON
4423                                     ON    8001
4424                                     ON    9001
4425                                     ON    9002
4426                                     ON    8002
```

0000000000	0000000000	0000000000	0000000000	0000000000
0000000000	0000000000	0000010000	0000000000	0000000000
0000000000	0000000000	0000020000	0000000000	0000000000
0000000000	0000000000	0000030000	0000000000	0000000000
0000000000	0000000000	0000040000	0000000000	0000000000
0000000000	0000000000	0000050000	0000000000	0000000000
0000000000	0000000000	0000060000	0000000000	0000000000
0000000000	0000000000	0000070000	0000000000	0000000000
0000000000	0000000000	0000080000	0000000000	0000000000
0000000000	0000000000	0000090000	0000000000	0000000000
0000000000	0000000000	0000100000	0000000000	0000000000
0000000000	0000000000	0000110000	0000000000	0000000000
0000000000	0000000000	0000120000	0000000000	0000000000
0000000000	0000000000	0000130000	0000000000	0000000000
0000000000	0000000000	0000140000	0000000000	0000000000
0000000000	0000000000	0000150000	0000000000	0000000000
0000000000	0000000000	0000160000	0000000000	0000000000
0000000000	0000000000	0000170000	0000000000	0000000000
0000000000	0000000000	0000180000	0000000000	0000000000
0000000000	0000000000	0000190000	0000000000	0044000000
0000000000	0000000000	0000200000	0000000000	0444400000
0000000000	0000000000	0000210000	0000000000	0044400000
0000000000	0000000000	0000220000	0000000000	0000000000
0000000000	0000000000	0000230000	0000000000	0000400000
0000000000	0000000000	0000240000	0000000000	4044400000
0000000000	0000000000	0000250000	0000000000	0000400000
0000000000	0000000000	0000260000	0000000000	0000000000
0000000000	0000000000	0000270000	0000000000	0000000000
0000000000	0000000000	0000280000	0000000000	0000000000
0000000000	0000000000	0000290000	0000000000	0000000000
0000000000	0000000000	0000300000	0000000000	0000000000
0000000000	0000000000	0000310000	0000000000	0000000000
0000000000	0000000000	0000320000	0000000000	0000000000
0000000000	0000000000	0000330000	0000000000	0000000000
0000000000	0000000000	0000340000	0000000000	0000000000
0000000000	0000000000	0000350000	0000000000	0000400000
0000000000	0000000000	0000360000	0000000000	0004400000
0000000000	0000000000	0000370000	0000000000	4444400000
0000000000	0000000000	0000380000	0000000000	4449400055
0000000000	0000000000	0000390000	0000000000	0444400000
0000000000	0000000000	0000400000	0000000000	4444400055
0000000000	0000000000	0000410000	0000000000	4494400055
0000000000	0000000000	0000420000	0000000000	4444400000
0000000000	0000000000	0000430000	0000000000	4444400005
0000000000	0000000000	0000440000	0000000000	4444900055
0000000000	0000000000	0000450000	0000000000	0444900055
0000000000	0000000000	0000460000	0000000000	0004400000
0000000000	0000000000	0000470000	0000000000	4444400005
0000000000	0000000000	0000480000	0000000000	0000000000
0000000000	0000000000	0000490000	0000000000	0000000000

```
4428                                                    BLA  MEMLL     MEML2
4429                                                    BLR  WDFOR
4430                                                    BLR  MEMLL
4431                                                    BLR   2201      2211
4432   3100  888 0 25  2491  3293   MEMLL   LDA  MEMU1                      ROUTINE FOR INSERTING RESERVED WORDS
4433   3293  888 0 60  4292  3144           STA  MEMU
4434   3144  888 0 20  3146  000A           BUF                RA
4435   3146  888 0 08  0000  3151           LIR1  0000
4436   3151  888 0 31  3154  3154           CLL
4437   3154  888 0 54  9994  2796           STL1  9994
4438   2796  888 0 06  9994  3200           IIR1  9994
4439   3200  888 0 60  4635  3237           STA  AVAIL
4440   3237  888 0 25  3239  4264           LDA                SCAN9
4441   3239  888 0 90  3241  0000           SML  LCARD          0000
4442   3241  888 0 07  HHHH  3244   LCARD   IIR   HHHH
4443   3244  888 1 39  9999  3201           ERS3  9999
4444   3201  888 0 20  3203  000A           BUF                RA
4445   3203  888 0 08  0000  3208           LIR1  0000
4446   3208  888 0 07  HHHH  3211           IIR   HHHH
4447   3211  888 1 39  0000  3202           ERS3  0000
4448   3202  888 0 77  3202  3205           ATL
4449   3205  888 0 70  3207  000A           ADD                RA
4450   3207  888 0 25  0001  3204           LDA   0001
4451   3204  888 0 24  0000  3206           BUF1  0000
4452   3206  888 0 64  0000  3209           STA1  0000
4453   3209  888 0 25  2491  3294           LDA  MEMU1
- 4454   3294  888 0 75  4095  3148           SUB  KON2
4455   3148  888 0 60  2491  3295           STA  MEMU1
4456   3295  888 0 08  1519  3298           LIR1 Z0099         1F
4457   3298  888 0 29  0000  3210   1       LDA1  0000
4458   3210  888 0 82  3213  3214           TEQ  1F
4459   3214  888 0 06  9999  3298           IIR1  9999         1B
4460   3213  888 1 06  9998  3217   1       IIR3  9998
- 4461   3217  888 0 30  1179  4229           LDL  INITT         REM
4462   3262  888 0 11  0200  2389   PRIME   PRN  K0000          -GOD          FIRST TIME INITIALIZATION,SET UP TEMP STORES
4463   2390  888 0 67  3333  000A   &GOD    HLT   3333          RA
4464   2389  888 0 30  0591  1993   -GOD    LDL                ZZONS
4465   0591  888 0 72  000A  0994           HCC  RA            -GOD1
4466   0995  888 0 67  2222  2389   &GOD1   HLT   2222         -GOD
4467   0994  888 0 31  1997  1997   -GOD1   CLL  1F
4468   1997  888 0 50  0050  3252   1       STL  LC
4469   3252  888 0 50  0415  3218           STL  LLIST
4470   3218  888 0 50  2243  3245           STL  ACC
4471   3245  888 0 50  0851  3253           STL  ARAS
4472   3253  888 0 50  0537  3139           STL  DOOST
4473   3139  888 0 50  4701  3153           STL  TEMPS
4474   3153  888 0 50  4824  3176           STL  DOVAR
4475   3176  888 0 50  4834  2786           STL  DSAVE
4476   2786  888 0 07  0057  2589           IIR  INCR1
```

```
4477   2589  888 0 60  4336  3238                STA  INCRE
4478   3238  888 0 07  0050  3242                IIR   0050
4479   3242  888 0 60  1363  3165                STA  HEAD
4480   3165  888 0 50  4804  3212                STL  NOTAG
4481   3212  888 0 05  4376  3228                LDX  DOEOF
4482   3228  888 0 65  4170  3272                STX  DOESW
4483   3272  888 0 05  4402  3104                LDX  LEOFF
4484   3104  888 0 65  4206  3108                STX  LESW
4485   3108  888 0 05  4405  3157                LDX  805
4486   3157  888 0 65  4770  3172                STX  COMT
4487   3172  888 0 05  0154  3156                LDX  CRDC
4488   3156  888 0 65  0141  3143                STX  CRDSW
4489   3143  888 0 05  4408  3160                LDX  BIG01
4490   3160  888 0 65  1634  3236                STX  DOTAG
4491   3236  888 0 05  1821  3223                LDX  MISUB
4492   3223  888 0 65  2220  3222                STX  UASW
4493   3222  888 0 05  4735  3240                LDX  PROF
4494   3240  888 0 65  4883  3285                STX  PRTSW
4495   3285  888 0 05  4050  3102                LDX  SCAN1
4496   3102  888 0 65  4248  3150                STX  SCANX
4497   3150  888 0 05  0108  3110                LDX  LSWOF
4498   3110  888 0 65  0089  3291                STX  LSW
4499   3291  888 0 05  4989  3141                LDX  TRON
4500   3141  888 0 65  4789  1791                STX  TRSW
4501   1791  888 0 05  1300  3103                LDX  TRCOF
4502   3103  888 0 65  1307  3109                STX  TRCSW
4503   3109  888 0 08  0000  3112                LIR1  0000      -ISIS
4504   3112  888 0 0G  0001  3116  -ISIS        IIR1  0001
4505   3116  888 0 70  3118  3112                ADD           -ISIS
4506   3118  888 0 99  9980  0000                CON  99998    00000
4507   3113  888 0 47  0100  3117  &ISIS        HSS   0100
4508   3117  888 0 30  0594  4613                LDL  INIT     NXTW
4509                           LDCN4             EQU   1521
4510   3111  888 0 0G  0010  1525  LDCN3        IIR1  0010     1525
4511   3114  888 0 23  2120  0000  LDCN2        ZON  *TRAN    40000
4512   3115  888 0 83  9154  0000  LDCN1        NUM  *TRAN    40000
4513   2200  888 0 07  4181  3215  WDFOR        IIR  50001
4514   3215  888 0 60  4980  3232                STA  ASM5T                ROUTINE IN 2200 IS TO PUNCH OUT THE TRANSLATN
4515   3232  888 0 30  3234  1993                LDL           ZZON5
4516   3234  888 0 25  3115  3119                LDA  LDCN1
4517   3119  888 0 05  3114  3120                LDX  LDCN2
4518                                             OFF   9000
4537                                             ON    9000
4538                                             ON    9001
4539                                             ON    9002
4540   3120  888 0 60  0908  3121                STA  R0108
4541   3121  888 0 65  0913  3122                STX  R0113
4542   3122  888 1 02  9999  3125                L1R2  9999
4543   3125  888 0 25  3127  3129                LDA#  ABABA   00000
4544   3129  888 0 20  3131  3133                BUF#  00000   BABAB
```

```
4545  3133  888 0 60  3135  3137                STA  FGFG
4546  3137  888 0 60  0011  3216                STA  H0011
4547  3216  888 0 60  0031  3233                STA  H0031
4548  3233  888 0 60  0051  3254                STA  H0051
4549  3254  888 0 60  0071  3273                STA  H0071
4550  3273  888 0 60  0112  3123                STA  H0112
4551  3123  888 0 60  0132  3134                STA  H0132
4552  3134  888 0 60  0152  3155                STA  H0152
4553  3155  888 0 60  0172  2174                STA  H0172      4F
4554                                            ON    8001
4555                                            ON    8002
4556  2174  888 1 07  0001  3178  4             IIR2  0001
4557  3178  888 1 25  2201  3219               LDA2  90000
4558  3219  888 0 30  3221  3224               LDL#  CCCCC     CCCCC
4559  3224  888 0 87  3227  000A               TGR             RA
4560  3227  888 0 37  0400  3235               SHL   0400
4561  3235  888 0 35  0043  3246               ERS   XM
4562  3246  888 0 60  4420  3274               STA   TEMP3
4563  3274  888 0 20  3276  3278               BUF#  08000     0000C
4564  3278  888 0 30  3280  3282               LDL             ASM5E
4565  3280  888 0 25  3283  3286               LDA   1F
4566  3286  888 0 20  4420  000A               BUF   TEMP3     RA
4567  3283  888 1 08  0000  3287  1            LIR3  0000      1F
4568  3168  888 1 0G  0000  2973  7            IIR3  0000
4569  2973  888 1 30  2201  3220               LDL2  90000
4570  3220  888 0 87  3225  3226               TGR             5F
4571  3225  888 0 30  2174  3177               LDL   4B        ASM5F
4572  3226  888 1 0G  0001  3287  5            IIR3  0001      1F
4573  3173  888 1 0G  0010  3287  PRM5         IIR3  0010      1F
4574  3287  888 1 29  0000  3229  1            LDA3  0000
4575  3229  888 0 36  3243  3243               CAA
4576  3243  888 0 31  3247  3247               CLL
4577  3247  888 0 82  3250  3251               TEQ   3F
4578  3251  888 0 25  4980  3284               LDA   ASM5T
4579  3284  888 0 70  3288  000A               ADD             RA
4580  3288  888 0 25  0000  3230               LDA   0000
4581  3230  888 0 35  4201  3255               ERS   XOM
4582  3255  888 0 70  3257  3260               ADD   2F
4583  3260  888 0 77  3260  3263               ATL
4584  3263  888 0 25  4016  0008               LDA   LIT1      RL
4585  3257  888 0 00  0005  3231  2            JMP   0005      1F
4586  3231  888 0 26  3248  3248  1            CLA
4587  3248  888 1 24  0000  3249               BUF3  0000      2F
4588  3250  888 1 29  0000  3249  3            LDA3  0000      2F
4589  3249  888 0 30  3256  4337  2            LDL             ASM5
4590  3256  888 0 07  4181  3259               IIR   50001
4591  3259  888 0 30  4980  3289               LDL   ASM5T
4592  3289  888 0 82  3292  3168               TEQ             7B
4593  3292  888 0 30  3168  3177               LDL   7B        ASM5F
4594  3262  888 0 05  0908  3124  ASM5E        LDX   RWD1
```

```
4595    3124  888 0 32  0F00  3138                SHR   0F00
4596    3138  888 0 20  3140  3142                BUF# 00000      50000
4597    3142  888 0 32  0F00  3158                SHR   0F00
4598    3158  888 0 65  0908  4337                STX   RWD1        ASM5
4599    3177  888 0 50  4568  3258  ASM5F         STL   EXIT2       1F
4600    3258  888 0 07  4181  3261  1             IIR   50001
4601    3261  888 0 30  4980  3290                LDL   ASM5T
4602    3290  888 0 82  3296  3297                TEQ   1F
4603    3297  888 0 25  3135  3145                LDA   FGFG
4604    3145  888 0 30  3258  4337                LDL   1B          ASM5
4605    3296  888 0 25  0908  3126  1             LDA   RWD1
4606    3126  888 0 35  3128  3130                ERS#  HHHHH       CHHHH
4607    3130  888 0 60  0908  3132                STA   RWD1
4608    3132  888 0 30  4568  1993                LDL   EXIT2       ZZONS
4609    1993  888 0 26  2996  2996  ZZONS         CLA
4610                                              OFF   9000
4621                                              ON    9000
4622                                              ON    9001
4623                                              ON    9002
4624    2996  888 0 60  0923  3136                STA   R0123
4625    3136  888 0 60  0933  3147                STA   R0133
4626    3147  888 0 60  0943  3149                STA   R0143
4627    3149  888 0 60  0953  3159                STA   R0153
4628    3159  888 0 60  0963  3166                STA   R0163
4629    3166  888 0 60  0973  0008                STA   R0173      RL
4630                                              ON    8002
4631                                              OFF   9000
4649                                              ON    9000
4650                                              ON    9001
4651                                              ON    8001
4652    2201  888 0 00  1190  0000  90000         JMP   1190        0000
4653    2202  888 0 00  1519  1230  90001         JMP   1519        1230
4654    2203  888 0 00  3298  1600  90002         JMP   3298        1600
4655    2204  888 0 00  4998  3800  90003         JMP   4998        3800
- 4656  2205  888 1 77  2205  3264  90004         ATL2
4657    3264  888 0 67  HHHH  3264                HLT   HHHH        *
4658                                              ON    8002
4659                                              ON    9002
```

0000000000 0000000000 0000000000 0000000000 0000000000
0000000000 0000000000 0000000000 0000000000 0000000000
0000000000 0000000000 0000000000 0000000000 0000000000

```
4661    4417  BBB 0 00  4092  0000    RATOR   CON  00409  20000
4662    1420  BBB 0 00  4098  0000    Z0000   CON  00409  80000    CON ZERO
4663    1421  BBB 0 00  4096  0000    Z0001   CON  00409  60000    CON 1
4664    1422  BBB 0 00  4094  0000    Z0002   CON  00409  40000    CON 2
4665    1423  BBB 0 00  0000  0000    Z0003   CON  00000  00000
4666    1424  BBB 0 00  0000  0000    Z0004   CON  00000  00000
4667    1425  BBB 0 00  0000  0000    Z0005   CON  00000  00000
4668    1426  BBB 0 00  0000  0000    Z0006   CON  00000  00000
4669    1427  BBB 0 00  0000  0000    Z0007   CON  00000  00000
4670    1428  BBB 0 00  0000  0000    Z0008   CON  00000  00000
4671    1429  BBB 0 00  4090  0000    Z0009   CON  00409  00000    APOSTROPHE
4672    1430  BBB 0 00  0000  0000    Z0010   CON  00000  00000
4673    1431  BBB 0 00  0000  0000    Z0011   CON  00000  00000
4674    1432  BBB 0 00  0000  0000    Z0012   CON  00000  00000
4675    1433  BBB 0 00  0000  0000    Z0013   CON  00000  00000
4676    1434  BBB 0 00  0000  0000    Z0014   CON  00000  00000
4677    1435  BBB 0 00  0000  0000    Z0015   CON  00000  00000
4678    1436  BBB 0 00  0000  0000    Z0016   CON  00000  00000
4679    1437  BBB 0 00  0000  0000    Z0017   CON  00000  00000
4680    1438  BBB 0 00  0000  0000    Z0018   CON  00000  00000
4681    1439  BBB 0 00  0000  0000    Z0019   CON  00000  00000
4682    1440  BBB 0 00  0000  0000    Z0020   CON  00000  00000
4683    1441  BBB 0 00  0000  0000    Z0021   CON  00000  00000
4684    1442  BBB 0 00  0000  0000    Z0022   CON  00000  00000
4685    1443  BBB 0 00  0000  0000    Z0023   CON  00000  00000
4686    1444  BBB 0 00  0000  0000    Z0024   CON  00000  00000
4687    1445  BBB 0 00  0000  0000    Z0025   CON  00000  00000
4688    1446  BBB 0 00  0000  0000    Z0026   CON  00000  00000
4689    1447  BBB 0 00  0000  0000    Z0027   CON  00000  00000
4690    1448  BBB 0 00  0000  0000    Z0028   CON  00000  00000
4691    1449  BBB 0 00  0000  0000    Z0029   CON  00000  00000
4692    1450  BBB 0 00  0000  0000    Z0030   CON  00000  00000
4693    1451  BBB 0 00  0000  0000    Z0031   CON  00000  00000
4694    1452  BBB 0 00  0000  0000    Z0032   CON  00000  00000
4695    1453  BBB 0 00  0000  0000    Z0033   CON  00000  00000
4696    1454  BBB 0 00  0000  0000    Z0034   CON  00000  00000
4697    1455  BBB 0 00  0000  0000    Z0035   CON  00000  00000
4698    1456  BBB 0 00  0000  0000    Z0036   CON  00000  00000
4699    1457  BBB 0 00  0000  0000    Z0037   CON  00000  00000
4700    1458  BBB 0 00  0000  0000    Z0038   CON  00000  00000
4701    1459  BBB 0 00  0000  0000    Z0039   CON  00000  00000
4702    1460  BBB 0 00  0000  0000    Z0040   CON  00000  00000
4703    1461  BBB 0 00  0000  0000    Z0041   CON  00000  00000
4704    1462  BBB 0 00  0000  0000    Z0042   CON  00000  00000
4705    1463  BBB 0 00  0000  0000    Z0043   CON  00000  00000
4706    1464  BBB 0 00  0000  0000    Z0044   CON  00000  00000
4707    1465  BBB 0 00  0000  0000    Z0045   CON  00000  00000
4708    1466  BBB 0 00  0000  0000    Z0046   CON  00000  00000
4709    1467  BBB 0 00  0000  0000    Z0047   CON  00000  00000
```

```
4710    1468    888 0 00    0000    0000    Z0048    CON    00000    00000
4711    1469    888 0 00    0000    0000    Z0049    CON    00000    00000
4712    1470    888 0 00    0000    0000    Z0050    CON    00000    00000
4713    1471    888 0 00    0000    0000    Z0051    CON    00000    00000
4714    1472    888 0 00    0000    0000    Z0052    CON    00000    00000
4715    1473    888 0 00    0000    0000    Z0053    CON    00000    00000
4716    1474    888 0 00    0000    0000    Z0054    CON    00000    00000
4717    1475    888 0 00    0000    0000    Z0055    CON    00000    00000
4718    1476    888 0 00    0000    0000    Z0056    CON    00000    00000
4719    1477    888 0 00    0000    0000    Z0057    CON    00000    00000
4720    1478    888 0 00    0000    0000    Z0058    CON    00000    00000
4721    1479    888 0 00    0000    0000    Z0059    CON    00000    00000
4722    1480    888 0 00    0000    0000    Z0060    CON    00000    00000
4723    1481    888 0 00    0000    0000    Z0061    CON    00000    00000
4724    1482    888 0 00    0000    0000    Z0062    CON    00000    00000
4725    1483    888 0 00    0000    0000    Z0063    CON    00000    00000
4726    1484    888 0 00    0000    0000    Z0064    CON    00000    00000
4727    1485    888 0 00    0000    0000    Z0065    CON    00000    00000
4728    1486    888 0 00    0000    0000    Z0066    CON    00000    00000
4729    1487    888 0 00    0000    0000    Z0067    CON    00000    00000
4730    1488    888 0 00    0000    0000    Z0068    CON    00000    00000
4731    1489    888 0 00    0000    0000    Z0069    CON    00000    00000
4732    1490    888 0 00    0000    0000    Z0070    CON    00000    00000
4733    1491    888 0 00    0000    0000    Z0071    CON    00000    00000
4734    1492    888 0 00    0000    0000    Z0072    CON    00000    00000
4735    1493    888 0 00    0000    0000    Z0073    CON    00000    00000
4736    1494    888 0 00    0000    0000    Z0074    CON    00000    00000
4737    1495    888 0 00    0000    0000    Z0075    CON    00000    00000
4738    1496    888 0 00    0000    0000    Z0076    CON    00000    00000
4739    1497    888 0 00    0000    0000    Z0077    CON    00000    00000
4740    1498    888 0 00    0000    0000    Z0078    CON    00000    00000
4741    1499    888 0 00    0000    0000    Z0079    CON    00000    00000
4742    1500    888 0 00    0000    0000    Z0080    CON    00000    00000
4743    1501    888 0 00    0000    0000    Z0081    CON    00000    00000
4744    1502    888 0 00    0000    0000    Z0082    CON    00000    00000
4745    1503    888 0 00    0000    0000    Z0083    CON    00000    00000
4746    1504    888 0 00    0000    0000    Z0084    CON    00000    00000
4747    1505    888 0 00    0000    0000    Z0085    CON    00000    00000
4748    1506    888 0 00    0000    0000    Z0086    CON    00000    00000
4749    1507    888 0 00    0000    0000    Z0087    CON    00000    00000
4750    1508    888 0 00    0000    0000    Z0088    CON    00000    00000
4751    1509    888 0 00    0000    0000    Z0089    CON    00000    00000
4752    1510    888 0 00    0000    0000    Z0090    CON    00000    00000
4753    1511    888 0 00    0000    0000    Z0091    CON    00000    00000
4754    1512    888 0 00    0000    0000    Z0092    CON    00000    00000
4755    1513    888 0 00    0000    0000    Z0093    CON    00000    00000
4756    1514    888 0 00    0000    0000    Z0094    CON    00000    00000
4757    1515    888 0 00    0000    0000    Z0095    CON    00000    00000
4758    1516    888 0 00    0000    0000    Z0096    CON    00000    00000
4759    1517    888 0 00    0000    0000    Z0097    CON    00000    00000
```

```
4760    1518  BBB 0 00  0000  0000    Z0098   CON  00000    00000
4761    1519  BBB 0 00  0000  0000    Z0099   CON  00000    00000
4762    0405  BBB 0 00  0000  0000    P0005   ZON
4763    0486  BBB 0 00  0000  0000    P0086   ZON
4764    0570  BBB 0 00  0000  0000    P0170   ZON
4765    0455  BBB 0 00  0000  0000    P0055   ZON
4766    0539  BBB 0 00  0000  0000    P0139   ZON
4767    0423  BBB 0 00  0000  0000    P0023   ZON
4768    0508  BBB 0 00  0000  0000    P0108   ZON
4769    0446  BBB 0 00  0000  0000    P0046   ZON
4770    0530  BBB 0 00  0000  0000    P0130   ZON
4771    0414  BBB 0 00  0000  0000    P0014   ZON
4772    0499  BBB 0 00  0000  0000    P0099   ZON
4773    0583  BBB 0 00  0000  0000    P0183   ZON
4774    0467  BBB 0 00  0000  0000    P0067   ZON
4775    0339  BBB 0 00  0000  0000    K0139   ZON
4776    0223  BBB 0 00  0000  0000    K0023   ZON
4777    0308  BBB 0 00  0000  0000    K0108   ZON
4778    0246  BBB 0 00  0000  0000    K0046   ZON
4779    0330  BBB 0 00  0000  0000    K0130   ZON
4780    0214  BBB 0 00  0000  0000    K0014   ZON
4781    0299  BBB 0 00  0000  0000    K0099   ZON
4782    0383  BBB 0 00  0000  0000    K0183   ZON
4783    0267  BBB 0 00  0000  0000    K0067   ZON
4784                                    OFF   9000
4807                                    ON    8001
4810                                    ON    9001
4813                                    ON    9002
4815                                    ON    9001
4816                                    ON    8001
4817                                    ON    8002
4828                                    ON    9000
4829                                    OFF   9001
4830                                    OFF   9002
4831                                    OFF   8001
4832                                    OFF   8002
4833    0400  BBB 0 00  0000  0000    P0000   ZON
4834    0481  BBB 0 00  0000  0000    P0081   ZON
4835    0450  BBB 0 00  0000  0000    P0050   ZON
4836    0418  BBB 0 00  0000  0000    P0018   ZON
4837    0503  BBB 0 00  0000  0000    P0103   ZON
4838    0441  BBB 0 00  0000  0000    P0041   ZON
4839    0525  BBB 0 00  0000  0000    P0125   ZON
4840    0409  BBB 0 00  0000  0000    P0009   ZON
4841    0494  BBB 0 00  0000  0000    P0094   ZON
4842    0578  BBB 0 00  0000  0000    P0178   ZON
4843    0462  BBB 0 00  0000  0000    P0062   ZON
4844    0200  BBB 0 67  7028  2427    K0000   CON  67702    82427    USS FORTRA
4845    0205  BBB 0 11  1030  1312    K0005   CON  11103    01312
4846    0281  BBB 0 60  9900  3330    K0081   CON  60990    03330    N II  ***
```

```
4847   0286  BBB 0 20  0000  0000   K0086  CON  20000  00000
4848   0365  BBB 0 0A  A279  B608   K0165  CON  0AA27  9B608      VERSION #
4849   0370  BBB 0 02  0110  0201   K0170  CON  02011  00201
4850   0250  BBB 0 01  11F1  0F52   K0050  CON  0111F  10F52      9000-MONTH-YEAR
4851   0255  BBB 0 20  0010  3122   K0055  CON  20001  03122
4852   0334  BBB 0 00  0000  0000   K0134  ZON
4853   0218  BBB 0 00  0000  0000   K0018  ZON
4854   0303  BBB 0 00  0000  0000   K0103  ZON
4855   0241  BBB 0 00  0000  0000   K0041  ZON
4856   0325  BBB 0 00  0000  0000   K0125  ZON
4857   0209  BBB 0 00  0000  0000   K0009  ZON
4858   0294  BBB 0 00  0000  0000   K0094  ZON
4859   0378  BBB 0 00  0000  0000   K0178  ZON
4860   0262  BBB 0 00  0000  0000   K0062  ZON
4861                                       ON   9002
4862                                       ON   9001
4863   0988  BBB 0 00  0000  0000   R0188  CON  00000  00000
4864   0993  BBB 0 00  0000  0000   R0193  CON  00000  00000
4865   0998  BBB 0 00  0000  0000   R0198  CON  00000  00000
4866   0903  BBB 0 00  0000  0000   R0103  CON  00000  00000
4867   0983  BBB 0 00  0000  0000   R0183  CON  00000  00000
4868                                       OFF  9000
4871                                       ON   8001
4872                                       ON   8002
4874                                       ON   9000
4875                                       ON   9001
4876                                       ON   9002
4877
4878
4879
4880
4881
4882   1700  BBB 0 05  0199  0300   J0000  CON  05019  90800
4883   1701  BBB 0 06  0900  0000   J0001  CON  06090  00000
4884   1702  BBB 0 05  8809  0000   J0002  CON  05880  90000
4885   1703  BBB 0 02  9699  1000   J0003  CON  02969  91000
4886   1704  BBB 0 06  0800  0000   J0004  CON  06080  00000
4887
4888   1706  BBB 0 06  1588  1100   J0006  CON  06158  81100
4889   1707  BBB 0 06  1598  1100   J0007  CON  06159  81100
4890   1708  BBB 0 05  8808  0000   J0008  CON  05880  80000
4891   1709  BBB 0 06  1588  1000   J0009  CON  06158  81000
4892   1710  BBB 0 05  8815  1000   J0010  CON  05881  51000
4893   1711  BBB 0 96  8810  0000   J0011  CON  96881  00000
4894   1712  BBB 0 03  9908  0000   J0012  CON  03990  80000
4895   1713  BBB 0 06  1599  1000   J0013  CON  06159  91000
4896   1714  BBB 0 97  8811  0000   J0014  CON  97881  10000
4897   1715  BBB 0 04  9699  1000   J0015  CON  04969  91000
4898
4899   1716  BBB 0 05  9687  1600   J0016  CON  05968  71600
```

INTERPRETIVE CODES FOR BINARY OPERATION
V1 OP V2 OR V2 PO V1.
KEY: S#SIMPLE VARIABLE,CONSTANT,OR TEMP STORE
A#REGISTER A I # INDEX REGISTER 1
D#SUBSCRIPTED VARIABLE
SS CLACC CHG1 LDA1 OP2
SA UZACC PO1
SI CLACC IIR10 PO1
SD CHG2 LDL2 LDA1 OPRL
AS UZACC OP2
AA IMPOSIBLE CASE
AI UZACC ATL IIR10 PORL
AD UZACC ATL LDA2 PORL
IS CLACC IIR10 OP2
IA UZACC ATL IIR10 OPRL
II CLACC IIR10 ATL OPRL
ID LDL2 IIR10 OPRL
DS CHG3 LDA1 OP2
DA UZACC ATL LDA1 OPRL
DI LDL1 IIR10 PORL
DD CHG4 LDL2 LDA1
INTERPRETIVE CODES FOR VARIOUS UNARY OPS
MUL S CLACC LDL2 MUL1 SHL

```
4900    1717  BBB 0 06  1587  1600    J0017   CON  06158  71600    MUL  A UZACC ATL MUL1 SHL
4901    1718  BBB 0 05  8815  8716    J0018   CON  05881  58716    MUL  I CLACC IIR10 ATL MUL1 SHL
4902    1719  BBB 0 96  8716  0000    J0019   CON  96871  60000    MUL  D LDL2 MUL1 SHL
4903    1720  BBB 0 05  9817  0000    J0020   CON  05981  70000    MULL S CLACC LDA2 ADSHL
4904    1721  BBB 0 06  1700  0000    J0021   CON  06170  00000    MULL A UZACC ADSHL
4905    1722  BBB 0 05  8817  0000    J0022   CON  05881  70000    MULL I CLACC IIR10 ADSHL
4906    1723  BBB 0 98  1700  0000    J0023   CON  98170  00000    MULL D LDA2 ADSHL
4907    1724  BBB 0 05  9918  0000    J0024   CON  05991  80000    GET+ S CLACC LDA1 UNARY
4908    1725  BBB 0 06  1800  0000    J0025   CON  06180  00000    GET+ A UZACC UNARY
4909    1726  BBB 0 05  8818  0000    J0026   CON  05881  80000    GET+ I CLACC IIR10 UNARY
4910    1727  BBB 0 99  1800  0000    J0027   CON  99180  00000    GET+ D LDA1 UNARY
4911    1728  BBB 0 05  8685  0000    J0028   CON  05868  50000    GET- S CLACC CLA SUB1
4912    1729  BBB 0 06  1586  8400    J0029   CON  06158  68400    GET- A UZACC ATL CLA SUBRL
4913    1730  BBB 0 05  8815  8684    J0030   CON  05881  58684    GET- I CLACC IIR10 ATL CLA SUBRL
4914    1731  BBB 0 97  8684  0000    J0031   CON  97868  40000    GET- D LDL1 CLA SUBRL
4915    1732  BBB 0 97  0000  0000    J0032   CON  97000  00000    LDL  S LDL1      NOTE:CLACC NOT USED HERE.
4916    1733  BBB 0 06  1500  0000    J0033   CON  06150  00000    LDL  A UZACC ATL
4917    1734  BBB 0 05  8815  0000    J0034   CON  05881  50000    LDL  I CLACC IIR10 ATL
4918    1735  BBB 0 97  0000  0000    J0035   CON  97000  00000    LDL  D LDL1
4919    1736  BBB 0 05  8681  2400    J0036   CON  05868  12400    ABS  S CLACC CLA BUF1 XIT
4920    1737  BBB 0 06  1586  8024    J0037   CON  06158  68024    ABS  A UZACC ATL CLA BUFRL XIT
4921    1738  BBB 0 05  8824  0000    J0038   CON  05882  40000    ABS  I CLACC IIR10 XIT
4922    1739  BBB 0 97  8680  2400    J0039   CON  97868  02400    ABS  D LDL1 CLA BUFRL XIT
4923    1636  BBB 0 94  0713  0000    CTRC    CON  94071  30000    STL1 TRACE LIR3
4924    0801  BBB 0 13  0001  3000    CSUB    CON  13000  13000    LIR3 - LIR3  LEFT SIDE IS OP:RIGHT SIDE IS PO
4925    3014  BBB 0 93  9109  2900    C345    CON  93910  92900    TGR5 TEQ43 - TGR 3 TEQ45
4926    0115  BBB 0 93  9108  2000    C4#5    CON  93910  82000    TGR5 TEQ43 - TGR34
4927    1615  BBB 0 83  0009  2900    C3#4    CON  83000  92900    TGR54 - TGR3 TEQ45
4928    1613  BBB 0 91  0009  1000    C3#5    CON  91000  91000    TEQ43 - TEQ43
4929    1908  BBB 0 12  0001  2000    COP     CON  12000  12000    OPRLX - OPRLX
4930                                                               SUBROUTINE ENTRANCES.LEFT:OP  RIGHT:PO
4931    1000  BBB 0 01  0600  1060    00000   CON  01060  01060    && FAD   FAD
4932    1001  BBB 0 01  0700  1080    00001   CON  01070  01080    -& RFSUB FSUB
4933    1002  BBB 0 01  0800  1070    00002   CON  01080  01070    &- FSUB  RFSUB
4934    1003  BBB 0 01  0650  1065    00003   CON  01065  01065    -- FAD-  FAD-
4935    1004  BBB 0 01  0900  1090    00004   CON  01090  01090    && FMUL  FMUL
4936    1005  BBB 0 01  1000  1100    00005   CON  01100  01100    -& NFMUL NFMUL
4937    1006  BBB 0 01  1000  1100    00006   CON  01100  01100    &- NFMUL NFMUL
4938    1007  BBB 0 01  0900  1090    00007   CON  01090  01090    -- FMUL  FMUL
4939    1008  BBB 0 01  1100  1130    00008   CON  01110  01130    && FDIV  RFDIV
4940    1009  BBB 0 01  1200  1140    00009   CON  01120  01140    -& NFDIV NRFDV
4941    1010  BBB 0 01  1200  1140    00010   CON  01120  01140    &- NFDIV NRFDV
4942    1011  BBB 0 01  1100  1130    00011   CON  01110  01130    -- FDIV  RFDIV
4943    1012  BBB 0 01  0200  1040    00012   CON  01020  01040    && DIV   RDIV
4944    1013  BBB 0 01  0300  1050    00013   CON  01030  01050    -& NDIV  NRDIV
4945    1014  BBB 0 01  0300  1050    00014   CON  01030  01050    &- NDIV  NRDIV
4946    1015  BBB 0 01  0200  1040    00015   CON  01020  01040    -- DIV   RDIV
4947    1016  BBB 0 02  0600  2100    00016   CON  02060  02100    && PLL   RPLL
4948    1017  BBB 0 02  0700  2120    00017   CON  02070  02120    -& PLL2  PLL7
4949    1018  BBB 0 02  0800  2110    00018   CON  02080  02110    &- PLL3  PLL6
```

```
4950  1019  BBB 0 02  0900  2130  Q0019  CON  02090  02130        --  PLL4  PLL8
4951  1020  BBB 0 02  1400  2180  Q0020  CON  02140  02180        &&  PLX   RPLX
4952  1021  BBB 0 02  1500  2200  Q0021  CON  02150  02200        -&  PLX2  PLX7
4953  1022  BBB 0 02  1600  2190  Q0022  CON  02160  02190        &-  PLX3  PLX6
4954  1023  BBB 0 02  1700  2210  Q0023  CON  02170  02210        --  PLX4  PLX8
4955  1024  BBB 0 01  2500  1250  Q0024  CON  01250  01250            FLSQ  FLSQ
4956  1025  BBB 0 02  2200  2260  Q0025  CON  02220  02260        &&  PXX   RPXX
4957  1026  BBB 0 02  2300  2280  Q0026  CON  02230  02280        -&  PXX2  PXX7
4958  1027  BBB 0 02  2400  2270  Q0027  CON  02240  02270        &-  PXX3  PXX6
4959  1028  BBB 0 02  2500  2290  Q0028  CON  02250  02290        --  PXX4  PXX8
4960  1029  BBB 0 01  2400  1240  Q0029  CON  01240  01240            FXSQ  FXSQ
4961  1030  BBB 0 70  0007  0000  Q0030  CON  70000  70000        &&  ADD   ADD
4962  1031  BBB 0 75  0057  5000  Q0031  CON  75005  75000        -&  SUB-  SUB
4963  1032  BBB 0 75  0007  5005  Q0032  CON  75000  75005        &-  SUB   SUB-
4964  1033  BBB 0 70  0057  0005  Q0033  CON  70005  70005        --  ADD-  ADD-
4965  1034  BBB 0 01  0000  1000  Q0034  CON  01000  01000        &&  MUL   MUL
4966  1035  BBB 0 01  0100  1010  Q0035  CON  01010  01010        -&  NMUL  NMUL
4967  1036  BBB 0 01  0100  1010  Q0036  CON  01010  01010        &-  NMUL  NMUL
4968  1037  BBB 0 01  0000  1000  Q0037  CON  01000  01000        --  MUL   MUL
4969  1038  BBB 0 35  0003  5000  Q0038  CON  35000  35000            ERS   ERS
4970  1039  BBB 0 35  0003  5000  Q0039  CON  35000  35000            ERS   ERS
4971  1040  BBB 0 35  0003  5000  Q0040  CON  35000  35000            ERS   ERS
4972  1041  BBB 0 35  0003  5000  Q0041  CON  35000  35000            ERS   ERS
4973  1042  BBB 0 20  0002  0000  Q0042  CON  20000  20000            BUF   BUF
4974  1043  BBB 0 20  0002  0000  Q0043  CON  20000  20000            BUF   BUF
4975  1044  BBB 0 20  0002  0000  Q0044  CON  20000  20000            BUF   BUF
4976  1045  BBB 0 20  0002  0000  Q0045  CON  20000  20000            BUF   BUF
4977  1127  BBB 0 02  0300  2020  EXP    CON  02030  02020            EXP   NEXP   LEFT SIDE IS F(X)
4978  0726  BBB 0 02  0500  2040  LN     CON  02050  02040            LN    NLN    RIGHT SIDE IS F(-X)
4979  1925  BBB 0 03  0300  3035  ATAN   CON  03030  03035            ATAN  ATAN-
4980  0924  BBB 0 03  0200  3025  TAN    CON  03020  03025            TAN   TAN-
4981  2721  BBB 0 02  0000  2010  SQRT   CON  02000  02010            SQRT  NSQRT
4982  0723  BBB 0 03  0100  3010  COS    CON  03010  03010            COS   COS
4983  2322  BBB 0 03  0000  3005  SIN    CON  03000  03005            SIN   SIN-
4984  2919  BBB 0 01  1600  1170  FLOTA  CON  01160  01170            FLT   NFLT
4985  1920  BBB 0 01  2000  1210  FIXA   CON  01200  01210            FIX   NFIX
4986  0563  BBB 0 01  1500  1150  COMPL  CON  01150  01150            COMP  COMP
4987  1232  BBB 0 04  1200  4120  TRACE  CON  04120  04120          TRACE TRACE
4988  0343  BBB 0 01  2700  1270  PAUSF  CON  01270  01270         PAUSE  PAUSE
4989  0744  BBB 0 01  2800  1280  STOPF  CON  01280  01280         STOP   STOP
4990  1750  BBB 0 31  2203  5478  W0000  ALF  TEMP
4991  1751  BBB 0 12  2226  3728  W0001  ALF  FLPK*                 NAMES OF LIBRARY PCKAGES
4992  1752  BBB 0 13  2225  7728  W0002  ALF  EXPK*
4993  1753  BBB 0 32  1123  9978  W0003  ALF  TRIG*
4994  1754  BBB 0 11  2225  4728  W0004  ALF  EDPK*
4995  3009  BBB 0 01  4094  5000  CON2   CON  01409  45000
4996  1363  BBB 0 00  0050  0000  HEAD   CON  00005  00000
4997  0773  BBB 0 FF  FFFF  FFFF  WARN   CON  FFFFF  FFFFF
4998  1050  BBB 0 99  4110  0000  T0000  CON  99411  00000          99 TARA*
4999  1051  BBB 0 02  4098  5000  T0001  CON  02409  85000          CON ZERO
```

```
5000  1052  BBB 0 82  4106  0000   T0002  CON  82410  60000   82 BIN&
5001  1053  BBB 0 00  0000  0000   T0003  CON  00000  00000   SENTINEL
5002  1054  BBB 0 84  4112  0000   T0004  CON  84411  20000   84 BIN*
5003  1055  BBB 0 00  0000  0000   T0005  CON  00000  00000   SENTINEL
5004  1057  BBB 0 82  4106  0000   T0007  CON  82410  60000   82 BIN&
5005  1058  BBB 0 02  4098  5000   T0008  CON  02409  85000   FILLED IN
5006  1059  BBB 0 99  4109  0000   T0009  CON  99410  90000   99 TARA*
5007  1060  BBB 0 02  4098  5000   T0010  CON  02409  85000   CON ZERO
5008  1061  BBB 0 82  4106  0000   T0011  CON  82410  60000   82 BIN&
5009  1062  BBB 0 00  0000  0000   T0012  CON  00000  00000   SENTINEL
5010  1063  BBB 0 70  0000  0000   T0013  CON  70000  00000   RIGHT PAREN
5011  1064  BBB 0 73  4114  0000   T0014  CON  73411  40000   73 SIGN$
5012  1065  BBB 0 00  0000  0000   T0015  CON  00000  00000   SENTINEL
5013  1066  BBB 0 99  4101  0000   T0016  CON  99410  10000   99 SIGN%
5014  1067  BBB 0 00  0000  0000   T0017  CON  00000  00000   SENTINEL
5015  1068  BBB 0 99  4110  0000   T0018  CON  99411  00000   99 TARA%
5016  1069  BBB 0 02  4098  5000   T0019  CON  02409  85000   CON ZERO
5017  1070  BBB 0 82  4106  0000   T0020  CON  82410  60000   82 BIN&
5018  1071  BBB 0 01  4096  5000   T0021  CON  01409  65000   CON 1
5019  1072  BBB 0 70  0000  0000   T0022  CON  70000  00000   RIGHT PARENTHESIS
5020  1073  BBB 0 00  0000  0000   T0023  CON  00000  00000   SENTINEL
5021  1074  BBB 0 78  4113  0000   T0024  CON  78411  30000   78 SIGN'
5022  1075  BBB 0 01  4096  5000   T0025  CON  01409  65000   CONSTANT 1
5023  1076  BBB 0 99  4164  0000   T0026  CON  99416  40000   99 DO$1
5024  1077  BBB 0 00  0000  0000   T0027  CON  00000  00000   SENTINEL
5025  1078  BBB 0 82  4106  0000   T0028  CON  82410  60000   82 BIN&
5026  1079  BBB 0 31  2005  1988   T0029  ALF  VAR             FILLED IN
5027  1080  BBB 0 73  4157  0000   T0030  CON  73415  70000   73 DONT1
5028  1081  BBB 0 00  0000  0000   T0031  CON  00000  00000   SENTINEL
5029  1082  BBB 0 99  4165  0000   T0032  CON  99416  50000   99 I02.1
5030  1083  BBB 0 99  4110  0000   T0033  CON  99411  00000   99 TARA%
5031  1084  BBB 0 02  4098  5000   T0034  CON  02409  85000   CON ZERO
5032  1085  BBB 0 82  4106  0000   T0035  CON  82410  60000   82 BIN&
5033  1086  BBB 0 01  4088  0000   T0036  CON  01408  80000      *I*
5034  1087  BBB 0 70  0000  0000   T0037  CON  70000  00000   RIGHT PAREN
5035  1088  BBB 0 78  4113  0000   T0038  CON  78411  30000   78 SIGN'
5036  1089  BBB 0 01  4088  0000   T0039  CON  01408  80000     *I*
5037  1090  BBB 0 99  4117  0000   T0040  CON  99411  70000   99 SIGN#
5038  1091  BBB 0 01  4096  5000   T0041  CON  01409  65000   CONSTANT 1
5039  1092  BBB 0 78  4113  0000   T0042  CON  78411  30000   78 SIGN'
5040  1093  BBB 0 21  2313  5538   T0043  ALF  LENTH           FILLED IN
5041  1094  BBB 0 78  4113  0000   T0044  CON  78411  30000   78 SIGN'
5042  1095  BBB 0 01  4096  5000   T0045  CON  01409  65000   CON 1
5043  1096  BBB 0 70  0000  0000   T0046  CON  70000  00000   RIGHT PAREN
5044  4221  BBB 0 99  4101  0000   LPREN  CON  99410  10000   99 SIGN%
5045  4370  BBB 0 99  4129  0000   LABEL  CON  99412  90000   99 LABL
5046  0316  BBB 0 82  4103  0000   0BIN-  CON  82410  30000   82 BIN-
5047  0972  BBB 0 75  4118  0000   0BIN#  CON  75411  80000   75 BIN1#
5048  0922  BBB 0 87  4116  0000   0BN**  CON  87411  60000   87 BIN**
5049  2641  BBB 0 70  4139  0000   0DIM%  CON  70413  90000   70 DIM%
```

```
5050  2909  888 0 70  4156  0000  0EQU*  CON  70415  60000      70 EQU%
5051  1406  888 0 70  4108  0000  0IF%   CON  70410  80000      70 IF%
5052  1743  888 0 99  4151  0000  0WDIM  CON  99415  10000      99 WDIM
5053  1915  888 0 99  4111  0000  0*     CON  99411  10000      99 SIGN*
5054  4093  888 0 70  4127  0000  0OPO   CON  70412  70000      70 OPO
5055  2317  888 0 84  4102  0000  0UN-   CON  84410  20000      84 UN-
5056  2241  888 0 70  4128  0000  0GO%   CON  70412  80000      70 GO%
5057  0864  888 0 70  4158  0000  0FC%   CON  70415  80000      70 FC%
5058  2103  888 0 70  4140  0000  0LPRN  ADD  NORMX   0000
5059  1816  888 0 70  0538  0000  0ARA*  ADD  ARA*    0000
5060  2009  888 0 70  1139  0000  0ARA%  ADD  ARA%    0000
5061  4109  888 0 05  1816  4428  TARA*  LDX  0ARA*   -0P3
5062  1773  888 0 70  3075  0000  0IO%   ADD  IO%     0000
5063  2615  888 0 00  2307  1629  ARAMD  JMP  ARA.    ARA$
5064  0840  888 0 00  2508  2508  COMMD  JMP  COM.    COM$
5065  1353  888 0 00  2837  2822  DIMMD  JMP  DIM.    DIM$
5066  2437  888 0 00  0471  1629  DIMMD  JMP  DIM.    DIM$
5067  0671  888 0 00  0168  1370  DOMD   JMP  DO.     DO$
5068  2355  888 0 00  2908  0469  EQ1MD  JMP  EQ1.    EQ1$
5069  2400  888 0 00  2904  1629  EQUMD  JMP  EQU.    EQU$
5070  1600  888 0 00  3062  1629  FCMD   JMP  FC.     FC$
5071  2237  888 0 00  2833  1834  GOMD   JMP  GO.     GO$
5072  2224  888 0 00  0589  0195  IFMD   JMP  IF.     IF$
5073  1520  888 0 00  2016  0543  MODE   JMP  NO.     NO$
5074  0351  888 0 00  2016  1130  POZMD  JMP  POZ.    POZ$
5075  3087  888 0 00  2136  2539  PARMD  JMP  PAR.    PAR$
5076  0762  888 0 00  2016  2320  CALMD  JMP  CAL.    CAL$
5077                             NO1    NEW  01000   00000
- 5078  2275  888 0 01  0393  0792  IO1MD  NO1  IO1.    IO1$
5079  2475  888 0 00  3073  0394  IO2MD  JMP  IO2.    IO2$
5080  2163  888 0 00  3073  0543  IO3MD  JMP  IO3.    IO3$
5081  4408  888 0 01  0000  0000  BIG01  CON  01000   00000
5082  4756  888 0 02  0000  0000  BIG02  CON  02000   00000
5083  2150  888 0 03  0000  0000  BIG03  CON  03000   00000
5084  0054  888 0 04  0000  0000  BIG04  CON  04000   00000
5085  4623  888 0 05  0000  0000  BIG05  CON  05000   00000
5086  0805  888 0 07  0000  0000  BIG07  CON  07000   00000
5087  2041  888 0 09  0000  0000  BIG09  CON  09000   00000
5088  2289  888 0 0G  0000  0000  BIG0G  CON  0G000   00000
5089  4974  888 0 10  0000  0000  BIG10  CON  10000   00000
5090  1896  888 0 13  0000  0000  BIG13  CON  13000   00000
5091  1178  888 0 20  0000  0000  BIG20  CON  20000   00000
5092  4431  888 0 21  0000  0000  BIG21  CON  21000   00000
5093  1298  888 0 24  0000  0000  BIG24  CON  24000   00000
5094  4604  888 0 25  0000  0000  BIG25  CON  25000   00000
5095  0550  888 0 29  0000  0000  BIG29  CON  29000   00000
5096  4247  888 0 30  0000  0000  BIG30  CON  30000   00000
5097  2784  888 0 37  0000  0000  BIG37  CON  37000   00000
5098  2212  888 0 40  0000  0000  BIG40  CON  40000   00000
5099  4277  888 0 50  0000  0000  BIG50  CON  50000   00000
```

```
5100  4603  BBB 0 60  0000  0000  BIG60  CON  60000  00000
5101  0461  BBB 0 69  0000  0000  BIG69  CON  69000  00000
5102  4392  BBB 0 70  0000  0000  BIG70  CON  70000  00000
5103  4203  BBB 0 71  0000  0000  BIG71  CON  71000  00000
5104  0121  BBB 0 77  0000  0000  BIG77  CON  77000  00000
5105  0355  BBB 0 87  0000  0000  BIG87  CON  87000  00000
5106  4301  BBB 0 90  0000  0000  BIG90  CON  90000  00000
5107  4225  BBB 0 99  0000  0000  BIG99  CON  99000  00000
5108  4617  BBB 0 HH  0000  0000  XO     CON  HH000  00000
5109  0043  BBB 0 00  HHHH  0000  XM     CON  00HHH  H0000
5110  4724  BBB 0 00  0000  HHHH  XC     CON  00000  0HHHH
5111  3023  BBB 0 00  HHHH  HHHH  XMC    CON  00HHH  HHHHH
5112  4201  BBB 0 HH  HHHH  0000  XOM    CON  HHHHH  H0000
5113  4667  BBB 0 HH  0000  HHHH  XOC    CON  HH000  0HHHH
5114  4267  BBB 0 01  HHHH  0000  XM1    CON  01HHH  H0000
5115  4741  BBB 0 0H  HHHH  0000  XMH    CON  0HHHH  H0000
5116  0435  BBB 0 H0  0000  HHHH  XCO    CON  H0000  0HHHH
5117  4740  BBB 0 0H  0000  0000  X1     CON  0H000  00000
5118  3062  BBB 0 00  0H00  0000  X3     CON  000H0  00000
5119  0022  BBB 0 00  0000  000H  X9     CON  00000  0000H
5120  0037  BBB 0 H0  000H  0000  X05    CON  H0000  H0000
5121  1237  BBB 0 00  00H0  000H  X49    CON  0000H  0000H
5122  0012  BBB 0 00  000H  0000  X5     CON  00000  H0000
5123  0406  BBB 0 00  00HH  0000  X45    CON  0000H  H0000
5124  1273  BBB 0 00  0000  00HH  X89    CON  00000  000HH
5125  0645  BBB 0 H0  0000  0000  H1     CON  H0000  00000
5126  0009  BBB 0 HH  HHH0  0000  H5     CON  HHHHH  00000
5127  0015  BBB 0 HH  HHHH  HHHH  H10    CON  HHHHH  HHHHH
5128  4733  BBB 0 BB  BBB0  0000  B5     CON  BBBBB  00000
5129  4405  BBB 0 00  0008  BBBB  B05    CON  00000  BBBBB
5130  4577  BBB 0 BB  BBBB  BBBB  B10    CON  BBBBB  BBBBB
5131  1419  BBB 0 01  0001  0000  ONE15  CON  01000  10000
5132  4628  BBB 1 00  0000  0000  MZERO  CON1 00000  00000
5133  4723  BBB 0 00  0000  5000  KON.5  CON  00000  05000
5134  4097  BBB 0 00  0001  0000  KON1   CON  00000  10000
5135  4095  BBB 0 00  0002  0000  KON2   CON  00000  20000
5136  0613  BBB 0 00  0003  0000  KON3   CON  00000  30000
5137  4298  BBB 0 00  0030  0000  KON30  CON  00003  00000
5138  4541  BBB 0 00  0200  0000  KN200  CON  00020  00000
5139  4016  BBB 0 00  0000  0001  LIT1   CON  00000  00001
5140  4720  BBB 0 00  0000  0004  LIT4   CON  00000  00004
5141  4424  BBB 0 00  0000  0005  LIT5   CON  00000  00005
5142  4413  BBB 0 00  0000  0008  LIT8   CON  00000  00008
5143  0633  BBB 0 00  0000  0010  LIT10  CON  00000  00010
5144  0063  BBB 0 00  0000  0011  LIT11  CON  00000  00011
5145  0366  BBB 0 00  0000  0099  LIT99  CON  00000  00099
5146  4305  BBB 0 00  0000  000A  LITA   CON  00000  0000A
5147  4362  BBB 0 00  0000  000B  LITB   CON  00000  0000B
5148  1907  BBB 0 29  9999  0000  TW09S  CON  29999  90000
5149  1815  BBB 0 04  9999  0000  FOR9S  CON  04999  90000
```

```
- 5150                                    END   PRIME
```

```
*    1.  FORTRAN II COMPILER  PASS 1
*        THE TRANSLATOR IS DIVIDED INTO TWO MAJOR
*        CO-ROUTINES, 'SCAN' AND 'GEN'.
*        SCAN HAS THE DUTY OF READING CARDS, CONDEN-
*        SING IDENTIFIERS AND CONSTANTS INTO SINGLE
*        ENTITIES AND TO FEED ITEMS, IN A CONVENIENT
*        INTERNAL CODE, ONE AT A TIME TO GEN.
*        GEN HAS THE DUTY OF PRODUCING OBJECT
*        CODE FROM THESE ITEMS.  CONTROL IS
*        PASSED BETWEEN GEN AND SCAN IN A FASHION
*        SUCH THAT EACH ROUTINE LOOKS LIKE A
*        SUBROUTINE OF THE OTHER.
*        THE PROGRAM BEGINS BY PRINTING THE TITLE LINE
*        FEEDING A CARD, AND GOING TO THE
*        INITIALIZATION ROUTINE, STEP 21.
*    TABLE OF CONTENTS
*        A. ARRAY SUBSCRIPTING
*        B. BINARY AND ARITHMETIC OPERATORS
*        C. CONSTANT SCANNER
*        D. DO LOOP CONTROL
*        E. EQUIVALENCE PROCESSING
*        F. FUNCTION CALLS
*        G. GENERATOR CONTROL
*        I. ASSEMBLER STRUCTURE
*        L. LINKED MEMORY SUBROUTINES
*        N. 'GET NEXT CHARACTER' ROUTINE
*        P. FUNCTION AND SUBROUTINE DECLARATIONS
*        Q. SPECIAL SCANNING ROUTINES
*        S. SCANNER CONTROL
*        T. SYMBOL TABLE SEARCH
*        U. UNARY OPERATORS AND SPECIAL GENERATORS
*        W. INPUT OUTPUT (READ PUNCH PRINT)
*        X. PROCESSING FORMAT STRING
*        Z. INITIALIZATION AND TERMINATION
*        FRANKLY, IT'S A MIRACLE IF THIS PROGRAM
*              EVER WORKS.
*    TABLE OF FORMATS
*        INFORMATION INSIDE THE COMPILER IS TREATED IN
*        TWO PRINCIPAL FORMATS, ONE FOR THE SYMBOL
*        TABLE ENTRIES IN THE SCANNER, AND ANOTHER FOR
*        GENERATOR CO-ROUTINE.
*        SYMBOL TABLE EQUIVALENTS ARE IN THE FORMAT
*              KM AAAA LLLL
*        WHERE LLLL IS A LINK TO THE NEXT SYMBOL,
*        FOR SEARCHING
*             < EQUALS 0:   SIMPLE VARIABLE
*               M IS 0:     NO MEMORY ASSIGNMENT AS YET
*                           AAAA IS 0000
*               M IS 1:     ASSIGNED AAAA IN UNIQUE
*                           STORAGE
*               M IS 2:     EQUIVALENCED, NOT YET
*                           ASSIGNED.  AAAA IS LINK TO
*                           OTHER MEMBERS OF THE
*                           EQUIVALENCE CLASS
*               M IS 3:     ASSIGNED AAAA IN COMMON
*
*
*
*
```

```
*
*
*
*
*
*
*
*                M IS 4:    A FORMAL PARAMETER, WHOSE
*                           SUBROUTINES ARE ASSIGNED
*                           AAAA, AAAA+1, AND AAAA+2
*                           IN UNIQUE.
*                M IS 5:    THE SYMBOL IS A 10 DIGIT
*                           CONSTANT.  IF AAAA IS 0,
*                           THIS CONSTANT HAS NOT BEEN
*                           NEEDED IN OBJECT PROGRAM
*                           YET, ELSE IT IS ASSIGNED TO
*                           LOCATION AAAA IN UNIQUE.
*           K EQUALS 3:    ARRAY
*              AAAA LINKS TO THE DIMENSION TABLE
*              ENTRY, M IS IGNORED.  THE DIMENSION
*              TABLE HAS N+1 ENTRIES IF THERE ARE N
*              SUBSCRIPTS TO THIS ARRAY.
*                AAAA+0:   3 M BBBB RRRR
*                AAAA+1:   0 0 TTTT SSSS
*                AAAA+2:   0 0 CCCC 0000
*                AAAA+3:   0 0 CCCC 0000   ETC
*              SSSS IS LINK BACK TO SYMBOL TABLE
*              ENTRY
*              CCCC WORDS, IF PRESENT, ARE LINKS TO
*              SYMBOL TABLE ENTRIES FOR CONSTANTS
*              (EXCEPT FOR THE LAST DIMENSION)
*              TTTT IS THE TOTAL LENGTH OF THE ARRAY
*              M IS 0:    NO MEMORY ASSIGNMENT HAS
*                         BEEN MADE AS YET, BBBB IS 0
*                M IS 1:  THE ADDRESS BBBB IS FOR
*                         A(1), I.E. THE FIRST CELL
*                         OF THE ARRAY, IN UNIQUE
*                         STORAGE
*                M IS 2:  EQUIVALENCED ARRAY A(RRRR),
*                         BBBB IS LINK TO OTHER
*                         ELEMENTS IN EQUIVALENCE
*                         CLASS
*                M IS 3:  SAME AS M EQUAL TO 1 EXCEPT
*                         COMMON STORAGE
*                M IS 4:  FORMAL PARAMETER, BASE
*                         ADDRESS IS STORED IN BBBB
*                         OF UNIQUE STORAGE.
*           K EQUALS 5:    LABEL
*                         AAAA IS THE ASSIGNMENT IN
*                         PROGRAM STORAGE.
*                M IS 0:  UNASSIGNED AS YET.
*                M IS 1:  TEMPORARY ASSIGNMENT FOR DO
*                         LOOPS. AAAA LINKS TO AN ITEM
*                         IN LLIST,
*                            AAAA+0:  02 TTTT XXXX
*                            AAAA+1:  SS SSSS LLLL
*                         WHERE XXXX IS LLIST LINK,
*                         TTTT IS TEMPORARY ASSIGNMENT
*                         OF THE LABEL, SS SSSS IS
*                         LIKE A PERMENENT SYMBOL
*                         TABLE ENTRY FOR LABELS, AND
*
*
*
*
*
```

```
*                    LLLL IS A LINK BACK TO THE
*                    SYMBOL TABLE ENTRY.
*              M IS 2:   AAAA IS THE ASSIGNMENT FOR
*                    THE LABEL.
*           K EQUALS 6:    FUNCTION
*              M IS 2:   ASSIGNED AAAA IN PROGRAM
*                    STORAGE
*              M IS 5:   ASSIGNED AAAA, EXTERNAL
*                    REFERENCE
*              M IS 9:   SPECIAL OPERATOR FOR SCANNER
*                    ONLY
*           K EQUALS 7, 8, OR 9   OPERATOR, RESERVED
*                                              WORD
*           KM AAAA IS CODE FOR OPERATORS.
*     IN EQUIVALENCE LOOPS, A SPECIAL MEANING IS
*     GIVEN FOR K EQUAL TO 9, WHEN M AAAA IS A
*     CHANGE IN REFERENCE POINT OF THE EQUIVALENCE
*     LOOP, PLUS 50000.
*     GENERATOR CODE FORMATS
*          K T SSSS COOP
*     FOR OPERANDS, P IS THE SIGN, 0 PLUS, 5 MINUS
*     T IS THE TYPE:  0 FLOATING, 1 INTEGER,
*                       2 UNSPECIFIED
*           K EQUALS 0:    SIMPLE VARIABLE, OR
*                       A CONSTANT (IF C IS 5)
*                       PERHAPS A HAPPY ARRAY.
*                       SSSS IS A LINK TO THE
*                       CORRESPONDING SYMBOL TABLE
*                       ENTRY.
*              K EQUALS 1:    COMPUTED RESULT IN RA
*              K EQUALS 2:    INDEX REGISTER 1
*                       (DO VARIABLE)
*              K EQUALS 3:    ARRAY
*                       SSSS LINKS TO DIMENSION
*                       TABLE ENTRY WHEN THIS ARRAY
*                       IS SENT FROM SCAN, AND THEN
*                       AFTER THE SUBSCRIPT FOR THE
*                       ARRAY IS PROCESSED, SSSS
*                       LINKS TO AN ENTRY ON THE
*                       ARAS LIST.SEE ROUTINE A FOR
*                       THE FORMATS IN ARAS.
*              K EQUALS 4:    TEMP STORAGE.
*                       SSSS IS THE ASSIGNMENT IN
*                       UNIQUE.
*              K EQUALS 5:    LABEL
*                       HERE SSSS IS A LINK TO THE
*                       CORRESPONDING SYMBOL TABLE
*                       ENTRY.
*              K EQUALS 6:    FUNCTION
*                       SSSS IS LINK TO SYMBOL TABLE
*              K EQUALS 7:    SPECIAL
*                       IN THE OPERAND STACK THIS IS
*                       SOMETIMES USED FOR AN ARRAY
*                       WITHOUT A SUBSCRIPT
*
*
*
```

```
*
*
*
```

```
*
*
*
*
*
*
*
*
*       DIMENSION   9941510000 99 WDDIM
*       COMMON      9941520000 99 WDCOM
*       EQUIVLENCE  9941530000 99 WDEQU
*       SIN         9841200000 98 SINF
*       COS         9841210000 98 COSF
*       SQRT        9841190000 98 SQRTF
*       TAN         9841220000 98 TANF
*       ARCTAN      9841230000 98 ATANF
*       LN          9841240000 98 LNF
*       EXP         9841250000 98 EXPF
*       ABS         9841260000 98 ABSF
*       FLOAT       9841540000 98 FLOTF
*       FIX         9841550000 98 FIXF
*       PUNCH       9941590000 99 WDPCH
*       CALL        9941600000 99 WDCAL
*       NOT         9841610000 98 BCOMP
*       OR          7941630000 79 BOR
*       AND         8041620000 80 BLAND
*       CARDS       6941660000 69 WDPRG
*
```




```
*   G.  GENERATOR CONTROL
*       THIS ROUTINE CONTROLS THE
*       GENERATOR CO-ROUTINE.
*       THE NORMAL EXIT AT THE COMPLETION OF A GENER-
*       ATED ITEM IS TO G1, WHICH STARTS THE
*       PROCESSING OF THE NEXT ITEM. AT THE END OF
*       GENERATING CODE FOR CERTAIN OPERATORS, EXIT
*       OCCURS TO G10 RATHER THAN G1, SINCE WE MAY
*       WISH TO PERFORM SEVERAL OPERATIONS BEFORE
*       SCANNING ANOTHER ITEM.
*   G1. SCAN NEXT ITEM.
*       ACTIVATE THE SCANNER COROUTINE.
*       NORMALLY THIS MEANS WE ENTER STEP S1.
*   G2. ISIT AN OPERATOR
*       IF THE ITEM SCANNED IS AN OPERATOR, GO TO G6.
*   G3. OPERAND STACKED
*       PUT THE ITEM AT THE TOP OF THE OPERAND STACK.
*   G4. IS IT AN ARRAY
*       IF THE OPERAND IS A DIMENSIONED VARIABLE,
*       GO TO A1.
*   G5. SCAN NEXT ITEM
*       IF THE NEXT ITEM IS A LEFT PARENTHESIS, WE
*       TENTATIVELY HAVE A FUNCTION CALL SO WE GO
*       TO      STEP F1.
*       OTHERWISE WE GO BACK TO STEP G2.
*   G6. WHAT KIND OPERATOR
*       IF THE OPERATOR JUST SCANNED IS ONE THAT
*       REQUIRES IMMEDIATE ACTION (CODE 99), BRANCH
*       TO THE ROUTINE FOR THIS OP.
*       IF WE HAVE A UNARY OPERATOR (CODE 96) SUCH
*       AS LN OR ABS, GO TO G20.
*             OTHERWISE WE HAVE A BINARY OPERATOR
*       OR A DELIMITER WHOSE PRECEDENCE IS TO BE
*       TESTED.
*   G7. PUT OP IN OHOLD.
*       PUT THE OPERATOR JUST SCANNED INTO LOCATION
*       'OHOLD' BEFORE DECIDING WHAT TO DO WITH IT.
*  G10.P(RATOR):P(OHOLD)
*       CHECK THE PRECEDENCE OF THE TOP OPERATOR ON
*       THE OPERATOR STACK AGAINST THE PRECEDENCE OF
*       THE OPERATOR IN 'OHOLD'.
*       IF IT IS LESS (E.G., IN A+B*C, + IS LESS
*       THAN *), WE MUST WAIT BEFORE OPERATING
*       FURTHER SO WE GO TO G19.
*       IF IT HAS GREATER PRECEDENCE OR
*       EQUAL PRECEDENCE,HOWEVER,THE OPERATOR ON TOP
*       OF THE STACK IS REMOVED AND WE BRANCH TO THE
*       APPROPRIATE ROUTINE FOR THIS OP.
*       PRECEDENCE IS 70 FOR VARIOUS KINDS OF LEFT
*       PARENTHESES,   73 FOR :    75 FOR  EQUALS
*       78 FOR COMMA, 79 FOR OR, 80 FOR AND,
*       82 FOR PLUS AND MINUS, 84 FOR UNARY MINUS,
*       FOR MULTIPLY, AND FOR DIVIDE,   87 FOR POWER,
*       AND 99 FOR UNARY OPERATORS
*  G19.COMMA OR SEMICOLON
*       IF OHOLD HAS A PRECEDENCE WHOSE UNITS DIGIT
```




```
*
*
*
*
*
*
*
*
*       IS1,3,6,OR 8 IT MEANS WE ARE TO BRANCH TO
*       THIS  OP NOW THAT THE PRECEDENCE HAS BEEN
*       CHECKED.  AT PRESENT THIS IS USED ONLY FOR
*       SEMICOLON (EON OF STATEMENT) OR COMMA AND THI
*       MEANS BRANCH TO THE ROUTINE SPECIFIED BY THE
*       CURRENT MODE.
*               OTHERWISE WE GO TO G20 TO PUT OHOLD
*       ON THE OPERATOR STACK
*    G20.OPERATOR STACKED
*       THE OPERATOR IS PUT ON TOP OF THE OPERATOR
*       STACK AND WE RETURN TO G1.
*    CODING DETAILS:
*       UPON ENTRY TO GET, REGISTER A CONTAINS THE
*       CURRENT ITEM AND REGISTER X CONTAINS THE
*       PREVIOUS ITEM. THESE ARE IN 'GENERATOR CODE'
*       WHICH IS EXPLAINED IN THE TABLE OF FORMATS
*       IN THE BEGINNING OF THE FLOWCHARTS.
*
```




```
*    S.  SCANNER CONTROL
*        THIS ROUTINE CONTROLS THE SCANNER CO-ROUTINE.
*        NORMALLY ENTRY TO THE SCANNER IS TO STEP S1
*        WHICH BEGINS TO SCAN A NEW ITEM.
*    S1. NEXT CHARACTER
*        GET THE NEXT CHARACTER FORM THE INPUT CARD
*        (ROUTINE N).
*    S2. WHAT KIND
*        IF THE CHARACTER IS NUMERIC, IT IS THE
*        BEGINNING OF A CONSTANT, SO WE GO TO C1.
*        A DECIMAL POINT ALSO MEANS A CONSTANT, GO TO
*        STEP C2.
*        IF THE CHARACTER IS ALPHABETIC IT MEANS THE
*        FIRST LETTER OF AN IDENTIFIER, SO WE GO TO
*         S3.
*        IF THE CHARACTER IS BLANK,RETURN TO S1.
*        OTHERWISE WE HAVE A SPECIAL CHARACTER.  EACH
*        SPECIAL CHARACTER IS TREATED EXACTLY AS AN
*        IDENTIFIER TO LENGTH 1 AND WE GO TO STEP S5.
*    S3. LOOK FOR IJKLMN
*        IF THIS CHARACTER IS THE LETTER I THROUGH N,
*        RECORD FOR FUTURE REFERENCE THAT THIS
*        IDENTIFIER IS INTEGER TYPE. ALSO PREPARE TO
*        BUILD UP TO FIVE CHARACTERS OF EVERY IDEN-
*        TIFIER IN A COMPUTER WORD, IN THE FORM
*        ZZZZZNNNNN WITH LEADING BLANKS.
*    S4. NEXT CHARACTERS
*        SUCCESSIVELY GET CHARACTERS FROM THE CARD
*        (ROUTINE N) UNTIL THE FIRST NON-ALPHNUMERIC
*        CHARACTER APPEARS. IF THE TERMINAL CHARACTER
*        IS NONBLANK, PUT IT BACK ON THE CARD SO IT
*        WILL COME THROUGH AGAIN NEXT TIME.
*    S5. SEARCH SYMBOL TABLE
*        ACTIVATE ROUTINE T TO SEARCH FOR THIS IDENT-
*        IFIER OR SPECIAL CHARACTER IN THE SYMBOL
*        TABLE. IF NOT FOUND, IT IS ENTERED IN THE
*        TABLE AS A SIMPLE VARIABLE.  IF FOUND, THE
*        CODE FOUND IS USED IN STEP S10.
*    S10.TRANSLATE TO GEN CODE.
*        WE HAVE AN ITEM WHICH WE WANT TO SEND
*        TO THE GENERATOR, BUT IT IS IN SYMBOL TABLE
*        FORMAT RATHER THAN GENERATOR FORMAT.
*        SPECIFICATIONS OF THESE FORMATS ARE GIVEN AT
*        THE BEGINNING OF THE FLOWCHART LISTINGS.
*        THE CONVERSION IS MADE AT THIS POINT. IF THE
*        SPECIAL CODE 69 OCCURS HERE A BRANCH IS MADE
*        TO THE SPECIAL SCANNER OPERATOR WHICH NEVER
*        GETS TO THE GENERATOR CO-ROUTINE, SUCH AS
*        TRACE,LIST,CARDS,ETC. THE APOSTROPHE OPERATOR
*        (MEANING END OF CARD), ROUTINE Q, IS ONE OF
*        THESE SPECIAL SCANNER OPERATORS    , THE
*        OTHERS ARE MENTIONED IN STEP U29.
*    S20.SEND TO GEN
*        THE CODED ITEM IS SENT TO GEN. USUALLY
*        THIS IS TO STEP G1. UPON REENTRY, SCAN WILL
*
*
*
*
*
```

```
*
*
*
*
*
*
*
*
*
*
```

START UP AGAIN AT 51.




```
*   N.  'GET NEXT CHARACTER' ROUTINE
*   N1. WAS CHAR PUT BACK
*       IF A CHARACTER HAS BEEN 'PUT BACK' ONTHE CARD
*       RE-EMIT THIS CHARACTER AND EXIT.
*   N2. END OF WORD
*       IF WE ARE NOT AT THE END OF THE CURRENT
*       TEN-COLUMN PART OF THE CARD, GO TO STEP N10.
*       ELSE WE MUST BRING UP ANOTHER SECTION OF THE
*                CARD.
*   N3. END OF CARD
*       IF WE ARE AT THE END OF THIS CARED,   GO TO
*       STEP N20.
*   N4. GET NEW WORD
*       BRING UP THE NEW WORD. THIS MEANS USUALLY
*       THAT THE NEXT TEN ZONES AND NEXT TEN
*       NUMERICS ARE BROUGHT UP. SPECIAL ACTION IS
*       TAKEN ON THE 8TH WORD OF 80-COLUMN  CARDS
*       TO STOP AFTER COLUMN 72, AND ON THE FIRST
*       WORD TO START EITHER AT COLUMN 7 OR AT
*       COLUMN 1 IF THERE IS A LABEL.
*   N10.EXTRACT NEXT CHAR
*       REMOVE THE NEXT CHARACTER FROM THE CARD AND
*        EXIT.
*   N20.GET NEW CARD
*       UNLOAD HSR BUFFER IF IT HAS NOT ALREADY BEEN
*       UNLOADED. IF NO CARD IS CURRENTLY IN PROCESS,
*       GIVE 2223 ERROR HALT.
*   N21.MOVE BUFFERS
*       INITIATE READING NEXT CARD, AND TRANSFER
*       HSR INTERLACE TO PRINTER INTERLACE.
*       PRINT OUT THE CARD IMAGE, TOGETHER WITH
*       LEVEL + BAND.
*       RESET EMITTER AND GO TO N4.
```




```
*    T.  SYMBOL TABLE SEARCH.
*        THIS SUBROUTINE IS USED TO LOOK UP IDENTIFIER
*        SPECIAL CHARACTERS, CONSTANTS, AND STATEMENT
*        NUMBERS (LABELS) IN THE BIG TABLE.  IF NOT
*        IN THE TABLE, THE ITEM IS ENTERED IN.
*    T1. SCRAMBLE
*        MULTIPLY ITEM BY 1010101010 AND THEN  ADD
*        (0 FOR CONSTANTS, LENGTH FOR IDENTIFIERS,
*        OR 99 FOR STATEMENT NUMBERS). TAKE THE
*        RESULT MOD 100, GIVING THE STACK HEAD NUMBER
*        FOR THIS SYMBOL.
*    T2. IS STACK EXHAUSTED
*        IF THISSTACK HAS BEEN ENTIRELY PROCESSED,
*        INSERT THIS ITEM INTO THE TABLE ON THIS
*        STACK.  EXIT.
*    T3. DOES SYMBOL MATCH
*        COMPARE THE CURRENT ITEM IN THE STACK
*        AGAINST THE DESIRED SYMBOL. IF THERE IS NO
*        MATCH, GO BACK TO  T2.
*    T4. GET TABLE ENTRY
*        GET THE CORRESPONDING ENTRY FOR THE SYMBOL WE
*        HAVE JUST FOUND.  EXIT.
*    CODING DETAILS:
*        AT INPUT, REGISTER A CONTAINS THE LENGTH OF
*        SYMBOL, REGISTER X CONTAINS THE CODE TO USE
*        IF NOT FOUND IN THE TABLE, RL CONTAINS THE
*        EXIT INSTRUCTION, TEMP2 CONTAINS THE SYMBOL.
*        AT EXIT, RL CONTAINS THE LOCATIONS OF THE
*        TABLE ENTRY IN ITS M ADDRESS, AND TEMP4 IS
*        THE EQUIVALENT OF THE SYMBOL.
*
```




```
*   L.  LINKED MEMORY SUBROUTINES.
*       THESE SUBROUTINES ARE USED IMPLICITLY IN MANY
*       PLACES OF THE PROGRAM, TO STORE AND RETRIEVE
*       INFORMATION FROM A POOLED MEMORY AREA.
*       THE FORMAT FOR POOLED MEMORY IS
*            STACK HEAD:  00 LINK 0000
*            AVAIL STACK  00 LINK 0000
*       OTHER ITEMS ARE IN TWO WORD FORMAT:
*             LINK     INFO1  LINK   1111112222
*             LINK+1       I N F O 2 1111111111
*       ZERO LINK INDICATES THE END. THE POOL IS
*       KEPT BETWEEN LOCATIONS MEML1 AND MEMU1
*       THE SYMBOL TABLE AND STACKS WORK DOWN FROM
*       MEMU1, DIMENSIONS AND EQUIVALENCE ENTRIES
*       ARE INSERTED UP FROM MEML1.
*       IN THIS SECTION, ENTRANCE L1 IS CALLED 'INS'
*       AND IT IS FOR INSERTING ITEMS, WHILE ENTRANCE
*       L10 IS FOR DELETING ITEMS FROM STACKS AND IT
*       IS CALLED 'REM'.
*   L1. IS AVAIL EMPTY
*       IF THE AVAIL STACK IS NOT EMPTY,REMOVE AN
*       ITEM AND GO TO L4.
*   L2. MEML:MEMU
*       IF THERE IS NO ROOM FOR ANOTHER ITEM, GIVE
*       THE I'M FULL ERROR ALARM.
*   L3. RESERVE TWO
*       DECREASE MEMU BY 2, WE WILL USE THESE TWO
*       LOCATIONS FOR THE NEW ITEM.
*   L4. INSERT ITEM
*       PUT THE NEW ITEM INTO THE MEMORY, FIX UP
*       LINKS PROPERLY.  EXIT.
*   CODING DETAILS FOR INS:
*       RB1 CONTAINS STACK HEAD LOCATION
*       RL  CONTAINS EXIT INSTRUCTION
*       RA  CONTAINS INFO2,RX CONTAINS INFO1
*       AT EXIT, RL IS NEW CONTENTS OF STACK HEAD,
*       RX IS INFO2.
*   L10.IS STACK EMPTY
*       IF STACK HAS NO ITEMS,GO TO EXIT2.
*   L11.REMOVE ITEM
*       REMOVE TOP ITEM OF STACK
*   L12.MAKE LOCATION AVAIL
*       PUT THE LOCATION JUST FREED ONTO THE AVAIL
*       STACK.  EXIT1.
*   CODING DETAILS FOR REM:
*       RB1 IS THE STACK HEAD LOCATION,
*       RX IS THE EMPTY EXIT (EXIT2),
*       RL IS THE ORDINARY EXIT1.
*       OUTPUT: RB1 IS THE LOCATION, RL IS INFO1.
*       INFO2 IS STILL IN MEMORY.
*
```




```
*   C.  CONSTANT SCANNER
*   C1. SET TYPE INTEGER
*       INITIALIZE  N  TO THE NUMBER JUST SCANNED.
*       SET TYPE INTEGER. GO TO C3.
*   C2. SET FLOATING TYPE.
*       SET  N TO FLOATING POINT TYPE.
*   C3. NEXT CHARACTER
*       GET THE NEXT NON-BLANK CHARACTER FROM THE
*       CARD (ROUTINE N).
*   C4. WHAT KIND
*       IF CHARACTER IS NUMERIC,SET N TO 10N+CHAR.
*       GO TO C3.
*       IF A DECIMAL POINT, GO TO C2.
*       IF ALPHABETIC, GO TO C5.
*       IF SPECIAL CHARACTER,PUT IT BACK ON THE CARD,
*       AND GO TO C6.
*   C5. E H OR M
*       IN A STATEMENT LABEL CONTEXT WE GO IMMEDIATEL
*       TO C6.  OTHERWISE WE GO TO C10 FOR AN E,
*       TO  C20 FOR AN M,
*       TO C30 FOR AN H,
*       OTHERWISE IT IS THE END OF THE CONSTANT
*       (PROBABLY SYNTACTICALLY INCORRECT) AND WE GO
*       TO STEP C6.
*   C6. ADJUST FOR TYPE
*       IF FLOATING POINT TYPE OCCURRED, CONVERT N TO
*       FLOATING POINT FORMAT, ELSE SET N TO 1000
*       TIMES N.
*   C7. IS IT A LABEL
*       IF LABEL CONTEXT,ENTER SPECIAL ROUTINE FOR
*       THIS CASE,DEPENDING ON THE SETTING OF THE
*       LABEL SWITCH. THE LABEL SWITCH IS AUTOMAT-
*            ICALLY SET OFF EVERY TIME GEN IS
*       ENTERED; GEN WILL SET IT WHENEVER A LABEL MAY
*       BE EXPECTED.
*   C8. LOOK UP IN TABLE
*       ACTIVATE ROUTINE T FOR THIS CONSTANT, THEN GO
*       TO S10 TO SEND A CONSTANT CODE TO GEN.
*   C10.NORMALIZE
*       INSERT A DECIMAL POINT IF NONE PRECEDED,
*       E.G. .2E5.
*   C11.NEXT CHARACTER
*       ACTIVATE ROUTINE N FOR THE NEXT CHARACTER.
*   C12.WHAT KIND
*       IF BLANK, RETURN TO C11.
*       IF NUMERIC,PUT BACK ON CARD,RECORD + SIGN.
*       TO C13.
*       IF PLUS OR MINUS, RECORD THE SIGN. TO C13.
*       OTHERWISE GIVE THE BAD CONSTANT ALARM.
*   C13.NEXT NUMBERS
*       CONTINUE ACTIVATING ROUTINE N UNTIL A NON-BLA
*       NK, NON-NUMERIC CHARACTER APPEARS.
*   C14.ADJUST EXPONENT
*       ADD THE EXPONENT TO THE FLOATING POINT
*       CONSTANT. IF OVERFLOW OR UNDERFLOW OCCURS,
*       GIVE THE BAD CONSTANT ALARM.
*       OTHERWISE RETURN TO C7.
*
```



C20.GET N CHARACTERS
GET NEXT N CHARACTERS FROM CARD INCLUDING BLANKS AND BUILD MACHINE CODE CONSTANT. GO TO C32.

C30.GET N CHARACTERS
SET HOLLERITH SWITCH IN ROUTINE N; THIS SWITCH SIGNALS THAT ROUTINE TO TRANSMIT CHARACTERS IN CARD CODE ON 90-COLUMN SYSTEMS AND ALSO TO SUPPRESS A SPECIAL HIGH-SPEED SKIP OVER BLANK COLUMNS WHICH IT USUALLY HAS. GET THE NEXT N CHARACTERS FROM THE CARD, AND BUILD AN ALPHA CODE CONSTANT IN CARD CODE.

C31.ZERO FILL
IF N IS LESS THAN 5, ADD ZEROES TO FILL THE CONSTANT. RESTORE THE HOLLERITH SWITCH TO NORMAL. IF N IS MORE THAN 5, CRAZY CONSTANTS ARE GENERATED

C32.TYPE UNSPECIFIED.
SET THE TYPE OF THIS CONSTANT TO UNSPECIFIED. GO TO C7.




```
*    Q.  SPECIAL SCANNING ROUTINES
*        ENTRANCE TO Q1 OCCURS WHEN THE END OF CARD
*        ( WHICH IS DETECTED BY AN APOSTROPHE INSERTED
*        BY ROUTINE N) IS SENSED.  ENTRANCE Q10 IS
*        USED TO DIVERT NORMAL CONTROL OF SCAN, IN
*        ORDER TO EMIT A STRING OF INSERTED ITEMS
*        BEFORE RESUMING ORDINARY SCANNING.
*    Q1. SEND SEMICOLON
*        SEND SEMICOLON TO GEN ROUTINE, INDICATING
*        END OF THE STATEMENT.
*    Q2. END OF DO RANGE
*        IF THE CARD JUST COMPLETED IS THE END OF A
*        DO RANGE, GO TO D40.
*    Q3. ANY LABEL
*        IF COLS 1-5 OF THE NEXT CARD ARE BLANK,TO S1.
*        IF COL 1 IS NUMB SIGN GO TO SPECIAL RESERVED
*        WORD ENTERING PROCEDURE.
*    Q4. SCAN FROM COL 1
*        SET TO SCAN THIS CARD AT COLUMN 1 RATHER THAN
*        COLUMN 7,AND SET THE LABEL SWTICH (C7) TO
*        JUMP TO THE CHECKING ROUTINE MENTIONED IN THE
*        COMMENT JUST BEFORE STEP D40.  THEN
*        RETURN TO S1.
*    Q10.ADJUST CO-ROUTINE LINKS.
*        STORE CURRENT STARTING PLACE FOR SCAN CO-RTNE
*        IN EXIT OF THIS DIVRT SUBROUTINE. WE WILL
*        COME BACK TO THIS AFTER ALL SPECIAL ITEMS
*        HAVE BEEN INSERT IN THE PSEUDOCODE.
*    Q11.NEXT ITEM.
*        LOOK AT THE NEXT ITEM TAKEN FROM THE INSER-
*        TION TABLE. IF IT IS ZERO, WE ARE DONE
*        INSERTING AND SO WE EXIT TO RESTART THE SCAN
*                CO-ROUTINE.
*    Q12.SEND TO GEN.
*        SEND ITEM TO GEN,THEN RETURN TO Q11.
*    CODING DETAILS:  DIVT2 IS USED TO RE-INSERT THE
*        PREVIOUSLY SCANNED ITEM AT THE END OF THE
*        OTHER INSERTS. DIVT1 IS USED TO RESET GEN
*        TO ENTER AT G1. DIVRT IS THE NORMAL ENTRY.
*        REGISTER A CONTAINS THE STARTING T-TABLE
*        ENTRY. THIS ROUTINE IS ENTERED FROM GEN.
*
*
*
```

```
*    I.  ASSEMBLER STRUCTURE
*    TABLE OF CONTENTS
*        THIS SECTION IS A COMPLEX OF SUBROUTINES FOR
*        ASSEMBLING THE MACHINE LANGUAGE INSTRUCTIONS.
*        THE NAMES OF THESE VARIOUS LEVELS AND THEIR
*        FUNCTIONS ARE
*        I1.  ASM1   MACRO ASSEMBLER ... ASSEMBLES
*                      1 TO 5 INSTRUCTIONS AND/OR
*                      PSEUDO-INSTRUCTIONS.
*        I25. ASM2   ASSEMBLES ENCODED INSTRUCTIONS,
*                    FIXING UP THE ADDRESSES OF OPERAND
*        I30. ASM25  HALF ASMBLER,LIKE ASM2 EXCEPT IT
*                 DEALS WITH ONE ADDRESS  M,C  ONLY.
*        I35. ASM28 SPECIAL ASSEMBLER FOR ADDRESSES OF
*                   SIMPLE VARIABLES AND CONSTANTS.
*        I50. ASIGN  FINDS ADDRESSES OF OPERANDS
*        I60. LS#    FINDS ADDRESSES OF STATEMENT LABEL
*        I70. CASIN  FINDS ADDRESSES OF CONSTANTS.
*        I80. ASM3      ASSEMBLES INSTRUCTIONS AND
*                     FIXES UP REFERENCES TO'NEXT INST.'
*        I90. ASM4     PROCESSES ASSEMBLED INSTRUCTIONS
*                   AND LOCATIONS, IN OR OUT OF SEQUENCE,
*                   AND PERHAPS LISTS THEM.
*        I95. ASM5   PUT ONE ITEM ON OUTPUT CARD.
*
```




```
*    I.  I80. ASSEMBLER 3
*        THIS SUBROUTINE ASSMELBLS ABSOLUTE INSTRUC-
*        TIONS AND FIXES UP REFERENCES TO 'NEXT'.
*        A ONE-CYCLE DELAY IS KEPT, AN INSTRUCTION IS
*        NO PUT OUT UNTIL THE NEXT INSTRUCTION COMES
*        ALONG.
*    I80.IS NXLOC SET
*        IF NO PARTICULAR LOCATION FOR THE CURRENT
*        INSTRUCTION HAS BEEN CHOSEN, CHOOSE THE NEXT
*        LOCATION IN THE INTERLACE SEQUENCE.
*    I81.FILL PREV INST
*        FILL BLANK ADDRESSES IN PREVIOUS INSTRUCTION,
*        IF ANY, WITH THE LOCATION OF THIS ONE.
*    I82.ASSEMBLER 4.
*        ACTIVATE ROUTINE I91 TO OUTPUT THE PRECEDING
*        INSTRUCTION.  EXIT.
*    CODING DETAILS: RX IS ORRQSUOOFF  WHERE RK ARE
*        RELOCATION DIGITS FOR M AND C, S IS SIGN, AND
*        FF ARE 0 OR 1 FOR NON-BLANK OR BLANK ADDRESS,
*        RESPECTIVELY.  RA IS THE INSTRUCTION, RL IS
*        THE EXIT. ASM31-ASM37 ARE SPECIAL ENTRANCES
*        FOR THE MOST COMMON CASES IN SETTING RX.
*
```




```
*   I.  I90. ASSEMBLER 4.
*       THIS SUBROUTINE PROCESSES ASSEMBLED INSTRUC-
*       TIONS AND LOCATIONS. ENTRY I90 IS USED FOR
*       OUT-OF-SEQUENCE LINES, I91 FOR THE PROGRAM
*       SEQUENCE.
*   I90.SET **********
*       SAVE COMMENT RESERVED FOR NEXT INSTRUCTION IN
*       PROGRAM SEQUENCE, AND INSERT THE COMMENT
*       **********.
*   I91.PRINT, MAYBE
*       IF LIST MODE IS ON, PRINT THE ASSEMBLED LINE
*       AND THE COMMENT.
*   I92.ASSEMBLER 5
*       PUT THE CONTROL WORD INTO THE OUTPUT
*       (ROUTINE I95)
*       AND ALSO STORE THE COMMENT FOR THE NEXT
*       INSTRUCTION LINE.
*   I93.ASSEMBLER 5
*       PUT THE INSTRUCTION WORD INTO THE OUTPUT
*       (ROUTINE I95).  EXIT.
*   CODING DETAILS:
*       ASM43,ASM44 PUT REGISTER A AS OUT-OF-SEQUENCE
*       LINE INTO NEXT LOCATION OF UNIQUE STORAGE
*       ASM42 PUTS TEMP2 AS OUT-OF-SEQUENCE INTO
*       LOC SPECIFIED BY 7 ADDRESS OF RA, RELOCATION
*       DIGIT FOR M BEING SPECIFIED IN REGISTER L.
*       ASM41,ASM4 HAVE CONTROL WORD IN REGISTER A,
*       INSTRUCTION WORD IN REGISTER X.
*
```




```
*   I.  I95. ASSEMBLER
*       THIS SUBROUTINE IS THE SOLE COMMUNICATION
*       BETWEEN THE COMPILER AND THE OUTPUT CARDS.
*   I95.STORE WORD
*       PUT THE OUTPUT WORD IN THE PUNCH INTERLACE.
*   I96.END OF CARD
*       IF THE CARD IS NOT FULL YET, EXIT.
*   I97.CHECK CARD
*       UNLESS NO CARDS MODE IS IN EFFECT, UNLOAD
*       THE BUFFER. THE THE 2ND READ STATEION IS NON-
*       BLANK, SUM CHECK THE IMAGE AVAILABLE THERE.
*       GIVE 1112 HALT IF THIS FAILS, AND DUMP HSR
*       BUFFER.
*   I98.COMPUTE CHECK SUM.
*       COMPUTE SUM OF NUMERIC PORTIONS OF FIRST
*       SEVEN WORDS, AND PLACE IN WORD 8 OF CARD.
*   I99.PUNCH
*       PUNCH CARD, INCREASE SEQUENCE NUMBER,  EXIT.
*
*
*
```




```
*    I.  I50.  ASIGN SUBROUTINE
*        THIS SUBROUTINE FINDS,OR MAKES,THE MEMORY
*        ASSIGNMENT FOR SIMPLE VARIABLES, ARRAYS, OR
*        TEMP STORAGES. IT IS NOT A TRUE SUBROUTINE,
*        FOR IF THE ITEM TURNS OUT TO BE A CONSTANT
*        OR HAPPY ARRY, IT JUMPS INTO THE MIDDLE OF
*        ASM28 ROUTINE.
*    I50.IS IT A TEMP
*        IF THE ITEM TO BE ASSIGNED IS A TEMP STORAGE,
*        GO TO I52.
*    I51.WHAT IS TABLE ENTRY
*        IF THE TABLE ENTRY INDICATES THIS ITEM IS
*        DEFINED IN UNIQUE OR COMMON,GOTO DEFX.
*        IF THE ITEM IS A PARAMETER,GO TO THE PARAMETE
*        EXIT. IF THE ITEM IS A CONSTANT, GO TO STEP
*        I38 IN ASM28,OR IF DOING A FUNCTION CALL GO
*        TO CASIN,STEP I70.
*        IF THE ITEM IS UNDEFINED AND EQUIVALENCED TO
*        OTHER ITEMS,GO TO E1.
*        IF THE ITEM IS UNDEFINED,NOT EQUIVALENCED,
*        ASSIGN IT IN UNIQUE STORAGE AND GO TO DEFX.
*        FINALLY IF THE ITEM IS A HAPPY ARRAY,ASSUME
*        WE HAVE BEEN CALLED BY ASM28;ADJUST OP CODE
*        FOR INDEXING IF NECESSARY,THEN CONVERT TO A
*        SIMPLE VARIABLE AND RECYCLE AT I51.
*    I52.REINSTATE TEMP
*        UNLESS PROCESSING A DO STATEMENT, THE TEMP
*        STORAGE LOCATION IS PUT BACK ON THE LIST OF
*        POTENTIAL TEMP STORAGES FOR FURTHER USE.
*        GO TO DEFX
*    CODING DETAILS:   RA IS THE OPERAND STACK ENTRY,
*        RL IS THE EXIT FOR A PARAMETER, RX IS THE
*        EXIT FOR A DEFINED NON-PARAMETER.
*
```




```
*    I.  I25. ASSEMBLER 2.
*        THIS SUBROUTINE ASSEMBLES MACHINE LANGUAGE
*        INSTRUCTIONS OF AN ALMOST SYMBOLIC NATURE:
*        THE OP-CODE IS THE TRUE OP BEFORE INDEXING,
*        AND THE ADDRESSES ARE EITHER ABSOLUTE,REFER
*        TO NEXT INSTRUCTION,OR REFER TO OPERANDS.
*        IN PARTICULAR,AN ARRAY OPERAND IS ALLOWED,
*        AND THIS MAY CAUSE MANY INSTRUCTIONS TO BE
*        GENERATED. IF THE OPERAND IS NOT A LABEL,
*        HOWEVER, THE ASSUMPTION IS MADE THAT IT GOES
*        IN M ADDRESS AND THAT C ADDRESS REFERS TO NXT
*    I25.ASSEMBLE 2.5 ON M
*        SEND THE M ADDRESS TO ASM2.5 FOR ASSEMBLY.
*        (IF IT IS AN OPERAND,WE WILL NEVER COME BACK
*        FROM ASM2.5,SEE THAT ROUTINE.)
*    I26.ASSEMBLE 2.5 ON C
*        SEND C ADDRESS TO ASM2.5 FOR ASSEMBLY.
*    I27.ASSEMBLE 3
*        SEND THE COMPILED INSTRUCTION TO ASM3 FOR
*        OUTPUT AND FINAL TOUCHES.  EXIT.
*    CODING DETAILS: ADDRESS 9999 MEANS NEXT. ADDRESS
*        9911 MEANS OPERAND STACK + 11. FOR EXAMPLE,
*        9901 IS THE TOP OF THE OPERAND STACK.  ADDRES
*        SES LESS THAN 9901 ARE ABSOLUTE.
*        AT INPUT RA IS A CODED INSTRUCTION,RL IS EXIT
*        LINE.
*
```




```
*   I.  I30. ASSEMBLERS 2.5 AND 2.8
*       ASM2.5 DOES HALF THE JOB OF ASM2. G.V.
*       ASM2.8 IS USED FOR SIMPLE VARIABLES, TEMP
*       STORAGES, AND SUBSCRIPTS.
*   I30.WHAT ADDRESS
*       IF THE ADDRESS TO BE ASSEMBLED IS ABSOLUTE,
*       SET CORRESPONDING R-DIGIT ZERO AND EXIT.
*       IF THE ADDRESS REFERS TO NEXT INSTRUCTION,
*       TRANSMIT THIS INFORMATION AND TEMPORARILY SET
*       THE ADDRESS ZERO. EXIT.
*                 OTHERWISE THE ADDRESS IS AN OPERAND
*       AND FURTHER TESTS ARE NECESSARY.
*   I31.WHAT KIND OF OPERAND
*       FETCH THE OPERAND SPECIFIED AND CHECK TO SEE
*       WHAT KIND IT IS.
*       FOR A SIMPLE VARIABLE OR TEMP STORAGE, GO TO
*       ASM28,STEP I35,AFTER WHICH WE EXIT FROM ASM2.
*       FOR AN ACCUMULATOR SYMBOL THIS IS A BAD MESS.
*       FOR AN INDEX VARIABLE,ASSUME WE WERE CALLED 8
*       BY ASSEMBLER 1 FOR A STORE OPERATION. TRANS-
*       FER BACK TO ASM1 EMITTING THE INSTRUCTIONS
*       TO LOAD RB1.
*       FOR AN ARRAY VARIABLE GO TO STEP I44.
*       FOR A LABEL,GO TO THE LABEL ASSIGN ROUTINE
*       (I60) AND THEN  EXIT.
*   I35.ASSIGN VARIABLE
*       GO TO ROUTINE I50 TO GET THE ASSIGNMENT FOR
*       THIS SIMPLE VARIABLE.
*       IF IT IS NOT A PARAMETER,GO TO STEP I42
*       IF IT IS A CONSTANT,WE GET TO STEP I38.
*                 OTHERWISE IT'S A PARAMETER.
*   I36.CHECK OP CODE
*       FOR A SIMPLE VARIABLE PARAMETER, WE CHOOSE
*       ONE OF THREE SUBROUTINES IN THE OBJECT CODE,
*       DEPENDING WHETHER THE OP IS TO BE LDL, LDA,
*       OR STL.  FOR A STA WE DO ATL, STL. FOR OTHER
*       OPERATIONS, WE DO LDL, OP RL.
*   I38.CHECK FOR ZERO
*       IF THE CONSTANT IS ZERO,AND IF THIS IS A
*       ZERO SUBSCRIPT ON A PARAMETRIC ARRAY GO TO
*       STEP I46. OTHERWISE FOR A ZERO CONSTANT, ADD
*       ONE TO THE OP CODE AND SET 7 AND C TO NXT.
*       GO TO ASM3 AND THEN EXIT FOR ASM2.
*   I39.CHECK FOR IIR
*       SEE IF THE OP IS LDA AND IF IT CAN BE CHANGED
*       INTO IIR; IF SO, DO THIS AND EXIT.
*       FROM ASM2 VIA ASM3.
*   I40.ASSIGN CONSTANT
*       USE THE CASIN ROUTINE (I70), DISPLAY THE
*       COMMENT 'CONST'.
*   I42.ASSEMBLE 3
*       GIVE APPROPRIATE COMMENT, THEN  EXIT FROM
*       ASM2 VIA ASM3.
*   I44.GET SUBSCRIPT
*       IN ASM2.5 WE HAVE AN ARRAY OPERAND.
*       IF THE SUBSCRIPT IS NOT ALREADY IN REGISTER
*       A, COMPILE CODE TO STORE A IN TEMP IF NEC-
*       ESSARY, AND THEN TO LOAD A WITH THE SUBSCRIPT
```




```
*
*
*
*
*
*
*
*
*       (USING ASM2.8, STEP I35).
*   I45.WHAT KIND ARRAY
*       (REFER TO STEP A24 WHERE THE VARIOUS CASES OF
*       ARRAY WERE DEFINED.) HAPPY ARRAYS DO NOT
*       COME THROUGH THIS PART,BUT WE MUST BRANCH
*       3 WAYS FOR THE OTHER TYPES OF ARRAYS:
*       SAD, GO TO I47.
*       ORDINARY, GO TO I48.
*            PARAMETRIC,GO TO NEXT STEP.
*   I46.PARAMETER CODE
*       IF CORE MODE IS ON, COMPILE
*           ADD 1F,LDX RA,LDA PAR,ADD RX RA.
*       ELSE COMPILE ADD PAR (OR LDA PAR IF SUBSCRIPT
*       IS ZERO), ADD NXT RA.  GO TO I49.
*   I47.SAD CODE
*       IF CORE MODE IS ON, COMPILE ADD 1F,
*       LDX RA, IIR ORELATIVE, ADD RX RA.
*       ELSE COMPILE ADD FUDGE, ADD NXT RA.
*       GO TO I49.
*   I48.ORDINARY CODE
*       COMPILE ADD NXT RA.
*   I49.COMPILE OP
*       NOW COMPILE THE ORIGINAL OP-CODE DESIRED FOR
*       THIS ARRAY OPERAND, PLUS 4 IF INDEXING IS
*       SPECIFIED. PUT NAME OF ARRAY AS COMMENT.
*   CODING DETAILS WILL BE OMITTED SINCE ASM2.5
*   AND ASM2.8 ARE ONLY FOR INTERNAL USE BY ASM2.
*
*
*
*
```




```
*    I.  I60. LSW  FOR ASSIGNING STATEMENT LABELS.
*        THIS ROUTINE HANDLES THE LOGIC FOR LABEL
*        ADDRESSES. THE PROBLEMS SOLVED ARE THOSE
*        OF FORWARD REFERENCES AND OF POTENTIAL GO TO
*        OUT OF DO LOOPS.
*    I60.CHECK LABEL
*        CHECK THAT THE OPERAND WHICH IS SUPPOSED TO
*        BE A LABEL IS ACTUALLY A STATEMENT NUMBER.
*        IF NOT, GIVE THE BAD LABEL ALARM.
*    I61.IN DO LOOP
*        IF WE ARE IN A DO LOOP GO TO STEP I64 UNLESS
*        WE WANT THE ABSOLUTE LOCATION OF THE LABEL
*    I62.ASSIGN
*        IF THE LABEL IS UNDEFINED,PICK LOCATION,
*        DEFINE IT, AND EXIT. IF THE LABEL IS TEMPO-
*        RARILY UNDEFINED (SEE BELOW),DO STEP I62 ON
*        THE AUXILIARY WORD. IF THE LABEL IS ALREADY
*        DEFINED, SIMPLY EXIT.
*    I64.TEMP ASSIGN
*        IN DO LOOP (AS OPPOSED TO DONT LOOP) WE MAKE
*        A TEMPO-A-Y ASS&GNMENT FOR THE LOCATION TO GO
*        TO,WHICH STORES R81 BEFORE GOING TO THE
*        ACTUAL LOCATION. THE EXTRA INFORMATION IS
*        KEPT IN LLIST, IN THE FORM
*        SYMBOL TABLE ENTRY LLLL: 51AAAAXXXX
*                                 AAAA:   02TTTT
*                                 AAAA+1: XSSSSSLLLL
*        WHERE XSSSSS IS THE OLD SYMBOL TABLE ENTRY,
*        TTTT IS THE TEMPORARY ASSIGNMENT.
*        IN THIS STEP,WE CREATE THE LLIST ENTRY IF
*        NONE HAS BEEN MADE YET FOR THIS LABEL. OTHER-
*        WISE WE USE THE TEMPORARY ADDRESS. ALSO IF
*        THE  LABEL  HAD NO PERMANENT ADDRESS AND THE
*        LABEL HAS NOW OCCURRED IN COLS 1-5, WE SET
*        THE PERMANENT ADDRESS EQUAL TO THE TEMPORARY
*        ADDRESS.    EXIT.
*    CODING DETAILS:
*        ENTRANCE LSW IS USED FOR THE BRANCH ON DO
*        LOOP. ENTRANCE LSWOF IS USED FOR GETTING
*        ABSOLUTE LOCATIONS AS WITH A FORMAT OR
*        ASSIGN STTATEMENT.  RL IS THE EXIT LINE.
*        OUTPUT IS 02AAAA0000 IN REGISTER A.
*
```




```
*   I.  I70. CASIN  ASSIGNING CONSTANTS.
*   I70.ALREADY ASSIGNED
*       IF THE CONSTANT HAS ALREADY BEEN ASSIGNED,
*       OUTPUT THE ASSIGNMENT. EXIT.
*   I71.PICK UNIQUE
*       PICK THE NEXT LOCATION IN UNIQUE STORAGE FOR
*       THIS CONSTANT
*   I72.COMPILE CONSTANT
*       OUTPUT THE CONSTANT OUT-OF-SEQUENCE USING ASS
*       EMBLER 4(I90).  EXIT.
*   CODING DETAILS:RX IS EXIT LINE, RB1 IS SYMBOL
*       TABLE REFERENCE. OUTPUT IS 01AAAA0000 IN RL.
*
*
*
*
*
*
*
*
```




```
*   I.  I1.  ASSEMBLR 1
*       THIS IS A MACRO-ASSEMBLR
*       WHICH IS GIVEN A LIST OF TWO-DIGIT INSTRUC-
*       TION NUMBERS.  THESE NUMBERS ARE EITHER
*       REFERENCES TO A LIST OF STANDARD INSTRUCTIONS
*       WHICH ARE PROCESSED BY ASSEMBLER 2, OR THEY A
*       ARE REFERENCES TO PSEUDO-INSTRUCTIONS NUMBER
*       I2 THRU I23.  THE PSEUDO-INSTRUCTIONS ARE
*       GIVEN HER IN THIS SECTION.  THE PURPOSE OF
*       ASM1 IS TO STEP THROUGH ALL 2-DIGIT
*       CODES, AS AN INTERPRETIVE ROUTINE.
*       'LOOP' REPRESENTS THE PLACE TO RETURN TO
*       STEP TO THE NEXT 2-DIGIT CODE.
*   I1. CHECK SPECIAL CASES
*       I1,I2,AND I3 ARE USED TO PROVIDE SLIGHTLY
*       BETTER CODE FOR CERTAIN BINARY OPERATORS
*       OR FOR IF-STATEMENTS WITH LABELS EQUAL, BY
*       CHANGING THE ORDER OF OPERATION.  LOOP.
*   I4. CHECK SUBSCRIPT
*       WHEN A BINARY OPERATION BETWEEN TWO ARRAY
*       VARIABLES IS USED, A TEST IS MADE HERE TO
*       SEE WHETHER EITHER SUBSCRIPT IS ALREADY IN
*       THE ACCUMULATOR, FOR EFFICIENCY.    LOOP.
*   I5. CLEAR ACC
*       IF THE ACCUMULATOR IN THE OBJECT PROGRAM
*       IS IN USE, COMPILE THE INSTRUCTION
*       'STA TEMP.'   LOOP.
*   I6. SET ACC AVAIL
*       THE ACCUMULATOR IS SET AVAILABLE, SINCE THE
*       PREVIOUSLY COMPUTED RESULT IS TO BE USED
*       NEXT.   LOOP.
*   I7. TRACE
*       IF TRACE MODE IS NOT ON, EXIT FROM ASM1.
*       OTHERWISE PREPARE THE INSTRUCTION LDX NAME
*       PREPARATORY TO TRACING.   LOOP.
*   I8. OP V2
*       EITHER OP V2 NXT  OR
*         LDL V2,OP RL IS COMPILED,
*       'WE ARE WORKING ON THE BINARY OPERATION
*           V1 OP V2)  THEN LOOP.
*   I9. PO V1
*       NOTE: V1 OP V2   EQUALS  V2 PO V1
*       EITHER  PO V1 NXT  OR
*       LDL V1, PO RL IS COMPILED.   LOOP.
*   I10.OP RL
*   I11.PO RL
*       THIS PSEUDO OP IS USED TO SELECT ONE OF TWO
*       ALTERNATIVES, WHICH ARE GIVEN AS PARAMETERS
*       TO ASM1, DEPENDING ON WHICH OPERAND IS IN
*       RL AND WHICH IS IN RA.   LOOP.
*   I12.OP RL NXT
*       COMPILE OP RL NXT.   LOOP.
*   I13.LIRJ NXT SUB
*       THIS COMPILES THE LINKAGE TO SUBROUTINES,
*       INCLUDING THE CONTROL INFORMATION TO BRING A
*       NEW SUBROUTINE IF THE SUBROUTINE HAS NOT
*
*
*
*
```




```
*
*
*
*
*
*
*
*       BEEN USED BEFORE.  LOOP.
*   I14.STORE INTO RB1
*       COMPILE  LIR1 0000 NXT, WITH THE DO VARIABLE
*       AS COMMENT.  LOOP.
*   I15.ATL CONDITIONALLY
*       COMPILE  ATL 0000 NXT  UNLESS THE PRECEDING
*       INSTRUCTION IN SEQUENCE WAS AN LIR3 (IN WHICH
*       CASE THE ANSWER IS ALREADY IN RL).  LOOP.
*   I16.SHIFT
*       I16 AND I17 ARE USED FOR SHIFT COMMANDS
*       WHEN COMPILING CODE TO MULTIPLY BY POWERS
*       OF 10.  LOOP.
*   I18.UNARY OPERATOR
*       DEPENDING ON THE UNARY OPERATOR, THE
*       SUBROUTINE REFERENCE IS COMPILED USING I13.
*   I19.GO TO 3F,2:
*       USED FOR MAKING FORWARD REFERENCES AT
*       THE BEGINNING OF DO LOOPS AND IN INPUT-
*       OUTPUT LISTS.  LOOP.
*   I20.TGR 9F 3F
*       THIS IS FOR THE TRANSFER INSTRUCTION FOR
*       EXITING FROM DO LOOPS.  LOOP.
*   I21.NINEF DO
*       THIS IS SIMPLY USED TO MARK THIS AS A DO
*       RATHER THAN A DONE LOOP.
*   I22.BUF      IF
*       USED AT BEGINNING OF FUNCTION OR SUBROUTINE.
*        LOOP.
*
*
*
*
*
*
*
*
```


2358
I22,BUF
1F
LOOP




```
*  B.  ARITHMETIC OPERATORS
*      THIS SECTION CONTAINS THE GENERATORS FOR
*      ARITHMETIC OPERATORS, ENTERED FROM STEP G6
*      OR FROM STEP G10.  AN ODD NUMBERED STEP HERE
*      INDICATES AN ENTRY FROM STEP G6 (WHEN SYMBOL
*      IS FIRST SENSED) AND AN EVEN NUMBERED STEP
*      IN THIS SECTION INDICATES AN ENTRY FROM
*      G10 ( OFF THE OPERATOR STACK ).
*  B1. MINUS SIGN
*      CHECK IF THE PRECEDING ITEM WAS AN OPERAND OR
*      RIGHT PARENTHESIS. IF SO, A BINARY MINUS
*      OPERATOR IS SUBSTITUTED AND WE GO TO STEP G7.
*      IF NOT, A UNARY MINUS OPERATOR IS SUBSTITUTED
*      AND WE GO TO STEP G20.
*  B3. PLUS SIGN.
*      CHECK AS IN STEP B1 FOR UNARY OR BINARY.
*      ON BINARY PLUS,CHANGE TO THE BINARY ADD
*      OPERATOR AND GO TO STEP G7.
*      A UNARY PLUS IS IGNORED. GO TO G1.
*  B4. SUBTRACTION OP
*      CHECK IF THE OPERATOR IN OHOLD IS A RIGHT
*      PARENTHESIS AND IF THE TOP OF THE OPERATOR
*      STACK IS LEFT PARENTHESIS AFTER AN IF. IN
*      THIS CASE AND IF THE SIGNS OF THE TOP TWO
*      OPERANDS ARE EQUAL, SUBTRACTION IS NOT
*      CARRIED OUT. THE IF OPERATOR IS REMOVED
*      FROM THE STACK AND WE GO TO STEP  B27.
*      OTHERWISE NEGATE THE TOP OPERAND AND
*      CHANGE TO BINARY PLUS. STEP B8.
*  B6. NEGATION OP
*      CHANGE SIGN OF TOP OPERAND. EXIT TO G10.
*  B8. ADDITION OP
*      CHECK TYPES OF OPERANDS. IF THEY ARE MIXED
*      GIVE AN ERROR ALARM.
*      IF BOTH ARE FLOATING POINT,GO TO B90.
*      IF FIXED POINT,CHECK IF WE ARE ADDING A
*      CONSTANT IN AN ARRAY SUBSCRIPT. IF NOT,
*      GO TO B89. HOWEVER IF WE ARE ADDING  0 + V
*      THE ADDITION IS SUPPRESSED.
*      IN THE ARRAY SUBSCRIPT CASE, RECORD IF THE
*      CONSTANT IS GREATER THAN +1. MULTIPLY THE
*      CONSTANT BY THE APPROPRIATE DIMENSION
*      AND ADD THIS TO THE BASE. EXIT TO G10.
*  B11.ASTERISK
*      CHECK FOR SECOND ASTERISK AND CHANGE TO A
*      MULTIPLY OR POWER OPERATOR; GO TO G7.
*  B12.MULTIPLY
*      IF FLOAT-FLOAT, GO TO B90.
*      IF MIXED TYPE, GIVE ERROR ALARM.
*      IF FIX-FIX, SET 0*V EQUAL TO 0. IN OTHER
*      CASES, WE MAY CHECK FOR POSSIBILITY OF
*      ADD RA  AND/OR  SHIFT COMMNDS TO IMPLEMENT
*      MULTIPLICATION, ELSE GO TO B90.
*  B15.LEFT PARENTHESIS
*      PUT A LEFT PARENTHESIS OPERATOR ON THE STACK,
*      STEP G20. WHEN IT COMES OFF THE STACK IT WILL
*      NECESSARILY BE FORCED OFF BY ITS MATCHING
```


2563
FXFL
**2
OTH
ALARM
U10
B20.EXPONENTIATION
2572
B22.AND,OR
2576
B25.WORD IF
G20
2580
B26.IF-LEFT-PAREN
2585
B27.FINISH IF-STATEMENT
2633
B89.GENERATE MACHINE OP
G10
2643
B90.GENERATE LIBRARY REF
G10

```
*
*
*
```




```
*   A.  PROCESSING OF ARRAY SUBSCRIPTS
*       WHEN A DIMENSIONED VARIABLE IS SENT FROM THE
*       SCANNER, ENTRY IS MADE TO A1.  A COMMA
*       BETWEEN SUBSCRIPTS CAUSES ENTRY TO A10.
*   A1. IS LEFT PAREN NEXT
*       SCAN NEXT ITEM. IF IT IS NOT A LEFT
*       PARENTHESIS,GO TO THE UNDIMENSIONED ARRAY
*        SWITCH. THIS SWITCH IS NORMALLY SET TO THE
*       'MISSING LEFT PARENTHESIS' ALARM WHICH
*       INSERTS A LEFT PARENTHESIS INTO THE
*       STATEMENT AND RETURNS HERE.
*   A2. SET ARRAY MODE
*       THE MODE STACK RECEIVES FOUR NEW ENTRIES:
*       2 0000  ARRAY MODE (A10 FOR COMMA,
*                           MISSING RIGHT PAREN FOR $)
*       2 9999  BASE CALCULATION
*       2 9998  CURRENT PRODUCT OF DIMENSIONS
*       2 9997  REFERENCE TO DIMENSION LIST
*   A3. EMIT % 0 +
*       FOR CONVENIENCE, THE CHARACTER ( 0 + ARE
*       INSERTED. THIS LEFT PARENTHESIS IS A SPECIAL
*       ONE WHICH SENDS CONTROL TO STEP A20 WHEN
*       THE MATCHING RIGHT PARENTHESIS COMES ALONG.
*       EXIT TO G1.
*   A10.CHECK INDEX.
*       IF THIS IS THE FIRST SUBSCRIPT AND ITS
*       CURRENT VALUE IS RB1 CODE, INDEXING IS SET
*       UP AND THE SUBSCRIPT IS REPLACED BY ZERO.
*       THIS OCCURS ONLY IF THE FIRST SUBSCRIPT IS
*       DOVAR & CONSTANT, WHERE THE CONSTANT IS
*       GREATER THAN -30, AND IF WE ARE NOT CALLING
*       A FUNCTION.
*       THE IMPORTANT ASSUMPTION IS MADE HARE THAT
*       NEITHER UNIQUE NOR COMMON STORAGE WILL BE
*       ASSIGNED TO CORE LOCATIONS B000 - B029.
*       WITH THIS CONVENTION, THE NUMBER OF SAD
*       ARRAYS(SEE SECTION A24) IS GREATLY REDUCED.
*   A11.POTENTIAL NEGATIVITY
*       IF ANY CONSTANTS GREATER THAN 1 OCCURRED
*       DURING THE LAST SUBSCRIPT ALONG WITH
*       ANYTHING OTHER THAN DOVAR, THIS ARRAY IS
*       MARKED AS HAVING A POTENTIALLY NEGATIVE
*       SUBSCRIPT.
*   A12.ADJUST MULTIPLIER
*       IF THERE ARE NO MORE DIMENSIONS, THE EXTRA
*       SUBSCRIPT ALARM IS GIVEN, ELSE IT IS
*       MULTIPLIED TO GIVE THE CURRENT PRODUCT OF
*       DIMENSIONS.
*   A13.EMIT  + N ( 0 +
*       FOR CONVENIENCE, THE COMMA IS TRANSFORMED
*       INTO THE CHARACTERS +N(0+    THIS LEFT
*       PARENTHESIS IS LIKE A MULTIPLICATION SYMBOL,
*       ONLY THE CHECK AT STEP A11 IS MADE FIRST.
*   A20.INDEXING,NEGATIVITY
*       WE HAVE NOW SCANNED THE ENTIRE SUBSCRIPT
*       OF THE ARRAY. STEPS A10 AND A11 ARE PERFORMED
*
*
*
```




```
*
*
*
*
*
*
*
*
*
*       THEY ARE REDUNDANT UNLESS THE ARRAY IS
*       SINGLY SUBSCRIPTED.
*    A21.CHECK FIXED POINT
*       IF SUBSCRIPT IS FLOATING, GIVE ERROR ALARM.
*    A22.COMPUTE SUBSCRIPT
*       ITSELF, PRODUCE CODE TO LOAD IT WITH TRUE
*       SIGN INTO THE ACCUMULATOR.
*    A23.EQUIVALENCE DECL.
*       IF WE ARE IN AN EQUIVALENCE DECLARATION,
*       EXIT TO THE EQUIVALENCE ROUTINE E30.
*    A24.WHAT TYPE ARRAY
*       THERE ARE FOUR KINDS OF ARRAYS, AND WE DECIDE
*       NOW WHAT KIND THIS IS.
*       IF THE ARRAY IS PARAMETRIC, GO TO A27.
*       CONSTANTS IN THE SUBSCRIPT ARE ADDED TO THE
*       BASE. IF THE BASE HAS THEREBY BECOME NEGATIVE
*       OR TOO LARGE OR IF THE SUBSCRIPT IS
*       POTENTIALLY NEGATIVE, THIS IS CALLED A SAD
*       ARRAY, AND WE GO TO A26.
*       EXAMPLE: A(J+2), WHERE J MAY BE NEGATIVE
*       IF THE SUBSCRIPT IS NOW ZERO, THIS INDICATES
*       THAT IT WAS ALL CONSTANT EXCEPT PERHAPS FOR
*       INDEX REGISTER MODIFICATION, SO GO TO A28.
*                  ELSE IT IS AN ORDINARY ARRAY.
*    A25.CODE 3SLLLLI000
*       FOR AN ORDINARY ARRAY, THE CODE 3SLLLLI000
*       IS SET UP,WHERE  S  IS THE STORAGE TYPE,
*       LLLL IS THE BASE LOCATION, AND  I  IS 0 OR 4
*       FOR INDEXING.  TO A29.
*    A26.CODE 2BBBBBS000
*       FOR A SAD ARRAY,THE CODE 2BBBBBS000 IS SET
*       UP, WHERE  S  IS THE STORAGE TYPE, BBBB IS
*       THE BASE LOCATION PLUS 50000, PLUS 40000 IF
*       INDEXING.  TO A29.
*    A27.CODE 1BBBBBPPPP
*       FOR A PARAMETRIC ARRAY THE CODE 1BBBBBPPPP
*       IS SET UP, WHERE BBBBB IS THE BASE LOCATION
*       PLUS 50000, PLUS 40000 IF INDEXING, AND
*       PPPP IS THE LOCATION OF THE PARAMETER. TO A29
*    A28.CODE AS SIMPLE VAR.
*       THIS ARRAY IS CHANGED TO LOOK ALMOST LIKE
*       A SIMPLE VARIABLE.
*    A29.MOVE SUBSCRIPT
*       THE STATUS OF THINGS IS CHANGED TO:
*       SAD:        PAR:        HAP:        ORD:
*             OPERAND STACK ENTRY:
*        3TAAAA0000 3TAAAA0000 0TAAAA0000 3TAAAA0000
*             LOCATIONS AAAA AND AAAA+1:
*        000000CCCC 000000CCCC 090100CCCC 000000CCCC
*        2BBBBBS000 1BBBBBPPPP 090100000C 3SLLLLI000
*             LOCATIONS CCCC AND CCCC+1:
*        SUBSCRIPT  SUBSCRIPT  0SLLLL**** SUBSCRIPT
*        ZZZZZNNNNN ZZZZZNNNNN ZZZZZNNNNN ZZZZZNNNNN
*       WHERE ZZZZZNNNNN IS THE ARRAY NAME, AND
*
*
*
*
*
```

```
*
*
*
*
*
*
*
*
*
*
*
```

T INDICATES THE TYPE. EXIT TO G1.



* U. UNARY OPERATORS AND SPECIAL GENERATORS
* COMPARE WITH THE INTRODUCTORY REMARKS OF
* SECTION B. ODD-NUMBERED STEPS INDICATE ENTRY
* FROM G6. EVEN NUMBERED, FROM G10.
* U1. EQUALS SIGN
* THIS IS A SWITCH WHICH IS SET IN SEVERAL
* PLACES. IF THIS EQUALS SIGN OCCURS IN A DO
* STATEMENT, GO TO D3. IF IT IS IN AN INPUT-
* OUTPUT STATEMENT, GO TO #17. OTHERWISE THIS
* IS A PLAIN OLD EQUALS SIGN, AND WE PUT A
* REPLACEMENT OPERATOR ON THE STACK. G20.
* U2. REPLACEMENT SETUP.
* IN A MULTIPLE ASSIGNMENT STATEMENT WE ENTER
* AT STEP U2 THE FIRST REPLACEMENT OPERATOR,
* STEP U4 SUCCEEDING TIMES. CHECK TYPES, AND
* IF DIFFERENCE IS PRESENT PUT OUT THE CODE TO
* FIX OR FLOAT. IF THE TYPES ARE THE SAME,
* DECIDE WHETHER TO PUT THE RIGHT-HAND SIDE IN
* REGISTER A OR NOT. REGISTER L IS SELECTED IF
* THERE IS A MULTIPLE ASSIGNMENT STATEMENT, OR
* IF THE LEFT-HAND PART IS NOT A SIMPLE VARIABL
* OR IF TRACE MODE IS ON.
* THE CODING TO PUT THE RIGHT-HAND SIDE, WITH
* TRUE SIGN, INTO THE SELECTED RIGISTER, IS
* ACCOMPLISHED BY SELECTING A
* TABLE ENTRY AND ACTIVATING ASM1(ROUTINE I).
* U4. REPLACEMENT OPERATOR
* PUT OUT CODING TO STORE A OR L IN THE
* APPROPRIATE LOCATION AND POSSIBLY TO
* CAUSE TRACING, USING ASSEMBLER 1(ROUTINE I).
* REMOVE OPERAND FROM STACK. EXIT TO G10.
* U10. UNARY OPERATORS
* IN THE CASE OF FIX, EXP, SIN, COS, TAN, ATAN, LN,
* SQRT, CHECK THAT THE ARGUMENT IS FLOATING
* POINT. SQUARING, THE 'NOT' OPERATOR, AND
* FLOAT PLUS THE ONES MENTIONED EARLIER ARE
* THAN CALLED FROM THE LIBRARY SUBROUTINES,
* USING A TABLE ENTRY AND ACTIVATING ASSEMBLER
* 1. THERE ARE TWO CASES, DEPENDING WHETHER THE
* ARGUMENT IS NEGATED OR NOT. IN THE CASE OF
* ABS, A SPECIAL TABLE ENTRY FOR AN OPEN
* SUBROUTINE IS USED.
* U12. END OF STATEMENT
* AT THE END OF MOST STATEMENTS WE CHECK THAT
* THE OPERATOR AND OPERAND STACKS ARE EMPTY,
* ELSE GIVE THE ERROR 'MISSING RIGHT PARENTHE-
* SIS' OR 'MISSING OPERAND' OR 'EXTRA OPERAND'.
* U13. WORD 'GO'
* SET LABEL CONTEXT ON, AND SCAN THE NEXT ITEM
* (ROUTINE S). THE WORD TO IS IGNORED BY
* FORTRAN. IF THE NEXT ITEM IS A LABEL, PUT IT
* IN A BLANK ADDRESS OF THE PRECEDING
* INSTRUCTION OR ELSE CREATE A JMP INSTRUCTION,
* THEN GO TO G1.
* IF THE NEXT ITEM IS A VARIABLE, COMPILE CODE
* TO STORE RB1 IF WE ARE IN A DO LOOP, THEN




```
*
*
*
*
*
*
*
*
*
*       CODE TO JUMP TO THE VARIABLE ITSELF.  U21
*       FINALLY IF IT IS A LEFT PARENTHESIS,
*       WE SET UP GO MODE, COMPILE EACH LABEL
*       OUT OF SEQUENCE, THEN WHEN THE RIGHT
*       PARENTHESIS COMES ALONG WE RETURN TO G1 TO
*       PROCESS THE EXPRESSION.
*   U14.END COMPUTED GO.
*       COMPILE CODE TO GET THE EXPRESSION WITH
*       TRUE SIGN IS REGISTER A, THEN
*       ADD NXT RA,  JMP TO THE TABLE.
*   U17.WORD 'ASSIGN'
*       SET LABEL CONTEXT,AND PLACE THE ASSIGN
*       OPERATOR ON THE STACK. THE WORD 'TO'
*       IS IGNORED BY FORTRAN.
*   U18. ASSIGN OP
*       CREATE A CONSTANT FOR THE ABSOLUTE LOCATION
*       OF THE LABEL (USE I62), THEN INTERCHANGE
*       OERANDS AND TREAT ANALOGOUS TO REPLACEMENT
*       AT STEP U2.
*   U21.'DIMENSION'
*       WHEN A DIMENSION DECLARATION APPEARS THE REST
*       OF THE COMPILER IS RIGGED UP TO HANDLE THIS
*       STATEMENT PROPERLY BY SITTING UP DIMENSION
*       MODE. WHEN A NAME COMES ALONG, A SECOND MODE
*       IS SET UP, AND THIS MODE CREATES THE
*       TABLE ENTRIES FOR AN ARRAY VARIABLE.
*       AT THE END, EXIT TO G1.  NO STORAGE
*       ASSIGNMENTS ARE MADE YET, THEY ARE MADE
*       WHEN THE ARRAY IS FIRST REFERENCED.
*   U27.'COMMON'
*       SET UP COMMON MODE, MARK EACH IDENTIFIER
*       THAT COMES ALONG AS COMMON AND ALLOCATE
*       THE STORAGE FOR IT.
*   U29.CONTROL WORDS
*       THE WORDS NO,TRACE,LIST,CORE,CARDS REALLY
*       NEVER GET PAST THE SCANNER, THEY ARE
*       DETECTED AT STEP S10. THEY MERELY SET
*       INTERNAL SWITCHES INSIDE THE COMPILER.
*       AND RUN OFF TO G1.
*
```




```
*   D.  DO LOOP CONTROL
*       WHEN THE WORD DO OR THROUGH IS SENSED, ENTRY
*       IS MADE TO STEP D1.
*   D1. SET UP FOR LABEL
*       DO MODE IS SET UP. A SWITCH IS SET SO THAT
*       WHEN THE NEXT EQUAL SIGN OCCURS,CONTROL GOES
*       TO STEP D3. SEMI-LABEL CONTEXT IS SET UP
*       SO THAT THE LABEL FOLLOWING COMES IN AS A
*       CONSTANT,YET STEP C5 GOES IMMEDIATELY TO C6
*       IN THE CONSTANT SCANNER. GO TO G1.
*   D3. ZERO COMMA COUNT
*       THE FACT THAT A COMMA MAY HAVE OCCURRED
*       BEFORE THE CONTROLLED VARIABLE IS FORGOTTEN.
*       AT THE END OF THIS STATEMENT,CONTROL WILL
*       PASS TO STEP D5. GO TO G1.
*   D5. CHECK COMMAS
*       IF LESS THAN TWO COMMAS HAVE OCCURRED,
*       INSERT  ',1'  IN THE PSEUDOCODE.
*   D6. STORE EXP IN TEMP
*       COMPILE CODE TO STORE REGISTER A IF THERE IS
*       A COMPUTED RESULT THERE. SET A SWITCH SO THAT
*       THE TEMP STORAGES USED TO HOLD COMPUTED
*       RESULTS ARE MADE PERMANENT STORAGES
*       (SEE STEP I52).
*   D7. DO OR DONT
*       THIS IS A DONT LOOP UNLESS:
*       A) THE WORD THROUGH WAS NOT USED
*       B) NO DO IS IN PROGRESS
*       C) BOTH THE STARTING VALUE AND INCREMENT
*       ARE CONSTANTS.
*       IN CASE OF A DONT LOOP,GO TO STEP D10.
*   D8. BEGIN DOO
*       SET THINGS UP FOR PUTTING VARIABLE IN AN
*       INDEX REGISTER. SET SWITCH FOR SPECIAL
*       HANDLING OF LABELS. COMPILE LIR1 N 3F,
*       2 IIR1 M,  LDL V, TGR 9F.  GO TO STEP D20.
*   D10.LDA INIT 3F
*       COMPILE LDA WITH INITIAL VALUE.
*   D11.  V + INC
*       ARTIFICIALLY INSERT  +V  INTO THE PROGRAM,
*       THUS RUNNING THROUGH THE ORDINARY ADD
*       GENERATOR TO CREATE CODE TO PUT THE SUM OF
*       V + INC IN REGISTER A.
*   D12.LDL, TGR
*       COMPILE  3 LDL FIN, TGR 9F, STA V
*   D20.LABEL IN TABLE
*       PUT THE LABEL NUMBER,TOGETHER WITH THE PER-
*       TINENT ADDRESSES FOR LINKING UP CONTROL
*       (9F,28) INTO THE DO STACK. EXIT TO D12.
```


3229
D20,LABEL IN TABLE
U12




```
*    F.  FUNCTION CALLS
*        TRANSFER IS MADE TO STEP F1 IF WE HAVE AN
*        UNDIMENSIONED IDENTIFIER FOLLOWED BY A LEFT
*        PARENTHESIS,NOT OCCURRING IN A DIMENSION DEC.
*    F1. ASSIGN F
*        IF THIS IS A NEW FUNCTION DEFINE IT. IF IT IS
*        A CONSTANT OR SIMPLE VARIABLE,TREAT AS
*        IMPLIED MULTIPLICATION.
*    F2. SET FUNC MODE
*        SET UP FUNCTION MODE,AND ALSO PUT A SPECIAL
*        LEFT PARENTHESIS OPERATOR ON THE STACK.
*        AS WE PASS OVER THE LIST OF PARAMETERS,
*        CODE IS COMPILED TO COMPUTE THEM  AND STORE
*        THEM IN TEMP, IF THE PARAMETER IS A CONSTANT
*        OR INDEX REGISTER. AS THE RIGHT PARENTHESIS
*        CLOSING THE FUNCTION CALL OCCURS, TRANSFER
*        WILL GO TO STEP F4. GO NOW TO STEP G1.
*    F4. BEGIN REVERSE PASS
*        BEGIN NOW A RIGHT-TO-LEFT PASS OVER THE
*        PARAMETERS. RESERVE THE UNIQUE STORAGE FOR
*        THEM, THEN PROCESS EACH PARAMETER IN TURN.
*        THE TYPES OF CODE PRODUCED ARE:
*        FOR SIMPLE VARIABLE PARAMETER-PARAMETER
*              IIR HHHH, ERS PARAM, STA LIST
*              AND LIST IS MARKED AS TEMP STORAGE.
*        FOR A LABEL (I-O SUBROUTINES ONLY), CODE
*                    00 LLLL 0000 (OUT OF SEQUENCE).
*        FOR AN ARRAY,  IIR A0, STA LIST.
*        FOR A SIMPLE VARIABLE OR TEMP STORAGE,
*                    00 LLLL 0000 (OUT-OF-SEQUENCE).
*    F5. LIR3
*        AFTER ALL PARAMETERS HAVE BEEN PROCESSED,
*        COMPILE THE INSTRUCTION
*                LIR3 U(I)FUNCT, AND THE
*        NEXT INSTRUCTION GOES TO LOCATION U(I).
*        THE PARAMETERS HAVE BEEN LISTED IN U(I+1),
*        U(I+2), ETC.
*        IF THIS CALL IS NOT IN A CALL STATEMENT, TREA
*        THE RESULT AS A COMPUTED QUANTITY IN
*        REGISTER A.  GO TO G1.
*        NOTE: IF A CALL STATEMENT IS GIVEN WITH
*        NO PARAMETERS, NO REFERENCE TO UNIQUE
*        STORAGE IS MADE.
*
```




```
*    0.  D40. CLOSE OF DO RANGE.
*        AS EACH STATEMENT LABEL IS SCANNED IT IS
*        CHECKED AGAINST THE TOP OF THE DO STACK
*        TO SEE WHETHER THIS STATEMENT IS THE END OF
*        THE DO RANGE. IF IT IS, THE NEXT APOSTROPHE
*        OPERATOR (END OF STATEMENT) SENDS CONTROL
*        TO STEP D40.
*    D40. GO TO 28
*        EFFECTIVELY COMPILE GO TO THE INCREMENTATION
*        PHASE AT THE BEGINNING OF THE DO LOOP CODING,
*        AND SET THE NEXT INSTRUCTION LOCATION TO BE
*        9F, THE ADDRESS FOR EXHAUSTION OF THE DO.
*    D41.DO OR DONT
*        IF THE LOOP JUST ENDED WAS A DONT LOOP,
*        SKIP TO STEP D50.
*    D42.EMPTY LLIST
*        TURN OFF THE VARIOUS INDICATORS WHICH ARE
*        SET DIFFERENTLY WHILE WE ARE IN A DO LOOP.
*        THEN FOR ALL LABELS WHICH WERE GIVEN
*        TEMPORARY ASSIGNMENTS, WE HAVE AN LLIST
*        ENTRY AND WE NOW OUTPUT THE INSTRUCTIONS
*                T      IIR1 0
*                       STA  V      P
*        WHERE V IS THE DO VARAIBLE, T IS THE TEM-
*        PORARY ASSIGNMENT, P IS THE PERMANENT
*        ASSIGNMENT. THE TEMP ASSIGNMENT IS THEN
*        FORGOTTEN.
*    D50. ANY MORE
*        IF ANOTHER DO LOOP ENDS ON THIS
*        STATEMENT,RETURN TO STEP D40. ELSE
*        GO TO Q3.
*
```




```
*    X.  PROCESSING FORMAT STRING
*    X1. COMPILE 02
*        THE INSTRUCTION 02 MMMM CCCC IS COMPILED
*        WHERE MMMM IS THE STARTING LOCATION OF THE
*        FORMAT CODE. WITH THIS TRICK, A FORMAT LABEL
*        IS LIKE ANY STATEMENT LABEL.
*        NOW WE TRANSLATE THE FORMAT INTO A SPECIAL
*        PSEUDOCODE. THIS CODE GENERATES INSTRUCTIONS
*        OF THE FORM OP NNN WWW DD, CORRESPONDING
*        TO FORMAT SPECIFICATION 'NNN E WWW.DD'.
*        OPCODES 0-10 CORRESPOND RESPECTIVELY TO
*        ()PIEFXAHM/
*    X2. RESET OP,N,W,D
*        CLEAR OP, N, W, AND D TO ZERO
*    X3. NEXT CHARACTER
*        GET THE NEXT CHARACTER FROM THE FORMAT LIST.
*        IF IT IS BLANK, DO X3 AGAIN.
*        IF IT IS A DECIMAL POINT, CYCLE N,W,D LEFT 1
*        AND RETURN TO X3
*        IF IT IS NUMERIC, SET D TO 10*D PLUS CHAR  X3
*        IF IT IS ALPHABETIC OR SPECIAL CHARACTER,
*        LOOK IT UP IN A TABLE TO SEE WHAT TO DO.
*        AN E F I A OR M MEANS GO TO X4.
*        A PLUS OR MINUS MEANS GO TO X5.
*        AN X OR P MEANS GO TO X6.
*        A LEFT PARENTHESIS MEANS GO TO X7.
*        COMMA SLASH AND RIGHT PARENTHESIS GO TO X8.
*        THE LETTER H MEANS GO TO X9.
*        AN APOSTROPHE MEANS WE GO TO X11.
*    X4. SET OP,CYCLE.
*        SET OP TO THE APPROPRIATE NUMBER, AND CYCLE
*        N,W, AND D LEFT 1. RETURN TO X3.
*    X5. SET SIGN INTO W
*        SET W TO 0 OR 1 (PLUS OR MINUS),RETURN TO X3.
*    X6. ASSEMBLE THIS OP
*        MOVE D TO N, THEN ASSEMBLE
*        OPNNNWWWDD INTO THE FORMAT CODE.RETURN TO X2.
*    X7. ASSEMBLE 2 LINES
*        MOVE D TO N AND ASSEMBLE, THEN INSERT A WORD
*        OF ZEROES INTO THE FORMAT CODE. THIS WORD
*        IS USED AS A SCRATCH PAD BY THE FORMAT
*        PROCESSING PACKAGE. RETURN TO X2.
*    X8. ASSEMBLE TWO OPS
*        IF DECIMAL POINT HAS NOT APPEARED, CYCLE
*        N,W,D LEFT 1. IF PREVIOUS OP IS WAITING
*        ASSEMBLE IT, AND CLEAR W. IF CURRENT IS NOT
*        A COMMA, ASSEMBLE IT TOO.
*        NOTE THAT ON  N/  THE COUNT N COMES OUT IN W.
*    X9. ASSEMBLE H OP
*        MOVE D TO N AND ASSEMBLE.
*    X10.INSERT LITERAL
*        OUTPUT 5 CHARACTERS OF THE LITERAL AT A TIME
*        UNTIL THE H LITERAL IS COMPLETED.
*        THE ROUTINE FOR H LITERALS IN THE CONSTANT
*        CONDENSER IS USED, WITH ZERO FILL AT THE
*        RIGHT. RETURN TO X2.
*    X11.ASSEMBLE 99 OP
*
*
*
```



THE APOSTROPHE SIGNALS THE END OF THE STATEMENT. ASSEMBLE A TERMINATION LINE AND GO OUT.




```
*   W.  INPUT-OUTPUT (READ,PUNCH,PRINT)
*       THIS SECTION IS WITHOUT DOUBT THE CLIMAX OF
*       THE COMPILER. AT LEAST 95% OF THE CODING OF
*       THIS COMPILER PROGRAM CAN BE ACTIVE WHILE
*       PROCESSING A SINGLE I/O LIST.
*   W1. SET TWO OPERANDS
*       SET UP TWO OPERANDS, ONE FOR THE EDITING
*       SUBROUTINE AND ONE FOR THE DRIVER SUBROUTINE
*       (I-O DEVICE).  SET UP TO EXPECT A LABEL.
*       GO TO G1. WE WILL RETURN TO STEP W2 WHEN
*       THE COMMA IS SENSED.
*   W2. CALL FUNCTION
*       USE THE FUNCTION CALL ROUTINE (ROUTINE F) TO
*       CREATE INITIAL ENTRY TO THE I/O SUBROUTINE.
*       THEN SET UP I/O MODE.  IF AN UNDIMENSIONED
*       ARRAY VARIABLE OCCURS WE WILL GO TO STEP
*       W5. ON A COMMA WE GO TO STEP W10.
*       AT THE END OF THE STATEMENT, WE GO TO STEP
*       W50.NOW WE GO TO THE COMMA ROUTINE,STEP W10.
*   W5. UNDIM ARRAY
*       AN UNDIMENSIONED ARAY A IS CONVERTED INTO
*       (A(*I*), *I* IS 1,N)
*       USING ROUTINE Q10    WHERE *I* IS A DUMMY
*       VARIABLE AND N IS THE PRODUCT OF THE ARRAY
*       DIMENSIONS.
*   W10.SCAN FOR (
*       SCAN NEXT ITEM (CD-ROUTINE S). IF IT IS THE
*       END OF THE STATEMENT,GO TO STEP W50. IF IT IS
*       A LEFT PARENTHESIS, GO TO STEP W12.
*       OTHERWISE INSERT AN  IN  OR  OUT  OPERATOR
*       ON THE STACK THEN GO TO G2.  IN IS STEP W14,
*       OUT IS STEP W15.
*   W12.INTERRUPT SEQUENCE
*       CREATEA BREAK IN THE INSTRUCTION SEQUENCE,
*       FOR WHICH CODE WILL BE INSERTED LATER. PUT A
*       SPECIAL LEFT PARENTHESIS ON THE STACK.  THIS
*       SPECIAL LEFT PARENTHESIS IS STEP W20.
*       GO TO STEP  W10 AGAIN.
*   W14.IN
*       COMPILE LIR3    SUB, STL V. GO TO G10.
*   W15.OUT
*       COMPILE LDA V, LIR3    SUB. GO TO G10.
*       SUB IS ONE OF THREE ENTRIES, DEPENDING ON
*       THE TYPE (FLOAT,FIX,UNSPECIFIED) OF V.
*   W17.EQUALS SIGN
*       AN EQUALS SIGN HAS APPEARED, SO WE PULL THE
*       SPURIOUS IN OR OUT OPERATOR OFF THE STACK.
*       WE NOW COURAGEOUSLY JUMP INTO THE MIDDLE
*       OF THE THROUGH ROUTINE, STEP D1.
*   W20.  (LIST)
*       THE RIGHT PARENTHESIS MATCHING A LEFT HAS BEE
*       ENCOUNTERED. IF AN IMPLIED DO LOOP OCCURRED
*       INSIDE, WE USE PARTS OF ROUTINE D TO CREATE
*       CODING FOR THE DONT LOOP CONTROL.  FINALLY
*       THE INTERRUPTIONS FROM STEP W12 ARE ALL
*       LINKED TOGETHER PROPERLY.  GO TO G1.
*
*
*
*
```


3669
W50.END
W50.END
COMPILE LIR3 SUB. THE ENDING SUBROUTINE.
AND THEN EXIT.
EXIT




```
*   P.  FUNCTION AND SUBROUTINE DECLARATIONS
*   P1. COMPILE PREAMBLE
*       COMPILE IIR1 0000, BUF    1F, LIR1 0000,
*       (AND LDA 0001, ATL  IF FUNCTION)
*   P2. SET UP CARD
*       SET UP THE NAME OF THE FUNCTION INTO THE
*       OUTPUT CARDS, INITIALIZE OTHER THINGS LIKE
*       THE MEANING OF RETURN.  A MAIN PROGRAM
*       IS DISTINGUISED FROM A SUBPROGRAM
*       ONLY BY DEFAULT.
*   P3. SCAN PARAMETERS
*       SCAN UNTIL THE END OF THE STATEMENT,
*       COLLECTING ALL PARAMETERS ON THE OPERAND
*       STACK. WE GET TO STEP P4 AT THE END
*       OF THE STATEMENT.
*   P4. SCAN AHEAD
*       IF THE NEXT ITEM SCANNED IS ANOTHER END OF
*       STATEMENT OR DIMENSION, GO TO G2.
*   P5. GENERATE THUNKS
*       ELSE WE ASSUME ALL DIMENSIONED PARAMETERS
*       HAVE BEEN NAMED, AND WE COMPILE CODE TO TRANS
*       FER FROM THE PARAMETER LIST TO UNIQUE STORAGE
*       TEN INSTRUCTIONS FOR NON-DIMENSIONED
*       PARAMETERS AND TWO FOR DIMENSIONED ONES.
*       THEN OFF TO G2.
*
*
*
```




```
*  Z.  INITIALIZATION AND TERMINATION
*      Z1 IS ENTERED AT THE BEGINNING OF EACH
*      PROGRAM AND SUBPROGRAM.
*  Z1. SET UP HEADER TABLE
*      THE HEADER CARD INFORMATION IS KEPT IN A 50-
*      POSITION CIRCULAR TABLE. IF MORE THAN 50
*      TOTAL ITEMS ARE PUT IN, A FLAG IS SET
*      SO THAT LOAD-AND-GO OPERATION IS DISALLOWED.
*  Z2. CLEAR SYMBOL TABLE
*      ALL SYMBOLS EXCEPT RESERVED WORDS ARE
*      REMOVED FROM THE SYMBOL TABLE.
*  Z3. INITIALIZE COUNTERS
*      VARIOUS THINGS ARE RESET, E.G. SUBROUTINE
*      PACKAGE REQUESTS, STORAGE ALLOCATION REQUESTS
*      COUNTERS ARE SET UP TO INDICATE A MAIN
*      PROGRAM. THESE WILL BE EFFECTIVE UNLESS
*      A FUNCTION OR SUBROUTINE DECLARATION FOLLOWS.
*      START COMPILING BY TROTTING FORTH TO G1.
*  Z50.END IS SENSED
*      AN END CARD MEANS WE SIMULATE A RETURN
*      STATEMENT (I.E. GO TO EXIT).
*  Z51.PUNCH HEADERS
*      PUNCH AND PRINT HEADER INFORMATION.
*  Z52.READ NEXT CARD
*      IF NO MORE INPUT CARDS ARE IN THE BUFFER,
*      PUNCH OUT SEVERAL BLANK CARDS AND STOP.
*      IF THE NEXT CARD IS THE BEGINNING OF PASS2,
*      TRANSFER TO THE SECOND PASS UNLESS AN ERROR
*      OCCURRED IN THE PRECEDING PROGRAMS.
*      OTHERWISE WE GO TO Z1 TO PROCESS ANOTHER
*
*
*
```




```
*    E.  EQUIVALENCE DECLARATIONS.
*        IT IS ALMOST IMPOSSIBLE TO EXPLAIN HOW THE
*        PROCESSING OF EQUIVALENCE DECLARATIONS
*        WORKS IN THIS COMPILER. IT DOES SEEM TO
*        WORK, HOWEVER.  EQUIVALENCE CLASSES ARE KEPT
*        IN CIRCULARLY-LINKED CHAINS.  IT IS EASY TO
*        MERGE TWO CHAINS INTO ONE. WHEN AN ITEM
*        OF A CHAIN IS FIRST REFERENCED AFTER AN
*        EQUIVALENCE DECLARATION, WE GO TO E1. FORMATS
*        OF THE CHAIN ENTRIES APPEAR IN THE TABLE
*        OF FORMATS.
*    E1. SEARCH THROUGH CHAIN
*        TRAVERSE THE CHAIN ONCE TO SEE HOW MUCH
*        UNIQUE STORAGE IS TO BE RESERVED.
*    E2. ASSIGN CHAIN
*        TRAVERSE THE CHAIN AGAIN, ASSIGNING EVERY
*        VARIABLE IN THE CHAIN RELATIVE TO THE OTHERS.
*        GO TO DEFX.
*    E3. 'EQUIVALENCE'
*        ON THE EQUIVALENCE DECLARATION, VARIOUS
*        MODES ARE SET UP.  AT THE END OF EACH
*        EQUIVALENCE, A CHECK IS MADE TO SEE IF
*        ANY OF THE ITEMS WAS PREVIOUSLY DEFINED.
*        IF SO, THE ENTIRE CHAIN IS THEN DEFINED,
*        AS IN STEP  E2.
*
```

10000	0645	4284	4285	4286	4287	4289	4290	4291	4292	4297	4299	4301
	4303	4311	0646	0646	4271							
20000	0647	4318	4319	4320	4321	4322	4323	4324	4325	4326	4365	4366
	4367	4368	4369	4370	4371	4372	4373	4414	4415	4416	4417	4418
	4419	4420	4421	4422	0648	0648	0649	0649	0650	0650	0651	0651
	0652	0652	0653	0653	0654	0654	0655	0655	0656	0656	0657	0657
	0658	0658	0659	0659	0660	0660	4297	4298	4299	4300	4301	4302
	4303	4304	4314	4316								
30000	0661	4328	4329	4330	4331	4332	4333	4334	4335	4336	4337	4338
	4339	4340	4341	4342	4343	4344	4345	4346	4347	4348	4349	4350
	4351	4352	4353	4354	4355	4356	4357	4358	4359	4360	4361	4362
	4363	4364	4377	4378	4379	4380	4381	4382	4383	4384	4385	4386
	4387	4388	4389	4390	4391	4392	4393	4394	4395	4396	4397	4398
	4399	4400	4401	4402	4403	4404	4405	4406	4407	4408	4409	4410
	4411	4412	4413	4278								
50000	0212	1637	1638	1639	1640	1641	1645	1691	1692	1693	1694	1695
	1699	1633	1679	1729	3860	3970	4513	4590	4600			
80000	0571	0573	0574	0575	0576	0577	0578	0579	0580	0581	0582	0583
	0585	0586	0587	0588	0589	0590	0591	0593	0594	0595	0597	0598
	0599	0601	0602	0603	0605	0606	0607	0609	0610	0611	0613	0614
	0615	0617	0618	0619	0620	0621	0622	0623	0625	0626	0627	0628
	0629	0631	0632	0633	0635	0572	0572	0584	0592	0596	0600	0604
	0608	0612	0616	0624	0630	0634	0636	0924				
90000	0213	4633	4634	4635	4636	4637	4642	4643	4644	4645	4652	4653
	4654	4655	4656	4557	4569							
-SASM	1659	1657	1658									
-ASSM	1683	1733	1681	1731								
-ADD	2498	2497	2513									
-AL1	4315	4312										
-AL2	4310	4307										
-ALRM	4270	4314	4316									
-AR2	2843	2840										
-ASSM	1685	1735	1682	1683	1732	1733						
-ASM5	1676	1725	1672	1675	1722	1726						
-ASN1	1831	1828										
-ASN2	4007	3993										
-ASN3	4022	4017	4020	4021								
-ASN4	1802	1801										
-BM	2416	2414										
-CHFL	2744	2743										

-COR	3145	3142		
-CRD2	1088	1085		
-CRD3	1093	1087	1089	
-CRD	0963	0961		
-DO2	3174	3173		
-EEE	2889	2887	2888	
-EQ1	4127	4126	4134	
-EQU8	4198	4194		
-EQV1	4052	4046		
-EQV2	4055	4052		
-EQV3	4044	4039	4043	4073
-EQV4	4061	4059		
-EQ	4094	4092		
-ERUT	1358	1356		
-FB	3758	3755		
-FIL1	1765	1759	1764	
-FIL2	1750	1768	1776	
-FNC1	3335	3333		
-FUNC	3333	3332		
-GET	2969	2967		
-GOD1	4467	4465		
-GOD	4464	4462	4466	
-GOT1	1784	1783	1785	
-GOTO	1782	1780		
-HF1	1880	1877		
-HF2	1882	1880		
-HOT	3539	3535		
-I18	2332	2329		
-IF1	2594	2591		
-IF2	2597	2596		

-IF3	2607	2602									
-INP1	0861	0875	0901	0837							
-INRA	2867	2866									
-ISIS	4504	4503	4505								
-KIND	1250	1248									
-L1	2456	2453									
-L2	2462	2459									
-LIS	3140	3137									
-MAG	2755	2753									
-MUL1	4258	4216									
-MUL	4215	4214									
-OP1	0686	0684									
-OP2	0706	0697									
-OP3	0732	0730	0736	2459	2547	2562	2579	2858	2938	3049	5061
-OP4	0707	0706	2456	2462							
-PAR1	3290	3288									
-PAR4	3306	3303									
-PAS2	3965	3954	3974								
-PN	2708	2695									
-POT1	3949	3947									
-POT2	3951	3949									
-POT	3944	3942									
-PR1	1603	1600									
-PR2	1563	1585	1602	1604							
-PRG	3150	3147									
-RE	2884	2879	2883								
-SAC	2432	2431									
-SCRM	1147	1145									
-SEND	0817	0813									
-TRC	3135	3132									

A0000	0111	2465	2486	2488	249[illegible]	2538	2539	2541	2543	2556	2557	2559
	2561	2564	2565	2567	2568	2861	2862	2863	2864	2484	2537	2555
	2563	2860										
ABSF	0071	2942										
ACC	0492	1996	2049	2056	2062	2236	2249	2434	2436	2439	2505	2508
	2832	2835	2962	4470								
ADDNX	2011	2010	2030	2086	3877							
AEQU	4174	2758										
ALARM	3974	1149	1338	1898	1900	2490	2598	2626	2630	2723	2745	2936
	2941	2958	3101	3128								
ALF	0565	4279	4306									
ANSL	2435	2415	2490	2531	3630	3632	4222					
ANSR	2502	2500	2545									
ARAMD	5063	2664										
ARAS	2851	5063										
ARA*	2738	5059										
ARAS	0533	2834	2841	2848	2960	4471						
ARA+	2707	5063										
ARA%	2739	5060										
AREX1	2003	1948										
AREX2	2097	2016	2096									
AREX	1993	1947	1988	1992								
ARITH	2373	2484	2537	2555	2563	2860						
ARRAY	2652	0691										
ASGN1	1804	18[illegible]3	4030									
ASIGN	1794	1912	2761	3268								
ASM11	2174	2173	2993	3022	3221	3226	3435	3723				
ASM1	2173	2429	2894	3619	3638	3670						
ASM25	1875	1855	1860									
ASM28	1909	1896	1992									
ASM2	1850	2185	2280	2876	3209	3295	3300	3786				
ASM31	1518	1517	1789	1870	1977							

ASM32	1506	1510	1929	1959	2316	3271	4266					
ASM33	1507	1509	3033	3275	3454	3721	3729	3773	3784	3791		
ASM34	1509	2009	2073	2078	2261							
ASM35	1510	2081										
ASM36	1511	2310	3311									
ASM37	1515	3717	3752									
ASM3	1517	1506	1507	1513	1515	1938	1951	2012	2042	2045	2351	2364
ASM41	1550	3354										
ASM42	1544	2169	3015	3283								
ASM43	1539	3523	3563									
ASM44	1540	1539	3567									
ASM4	1556	1534	3732									
ASM5	1632	1617	1620	3924	3968	4589	4598	4604				
ASM5C	3966	3944	3945	3946	3951							
ASM5D	3969	3878	3929									
ASM5E	4594	4564										
ASM5F	4599	4571	4593									
ASM5T	0551 4601	1633	1632	1642	1644	1696	1698	3861	3971	4514	4578	4591
ASMF1	3554	3518	3521	3532								
ASMF2	3556	3553	3555	3568								
ASMFJ	3552	3529	3551									
ASMTR	2893	2869	3038	3630								
ASS1	0075	3028										
ASS2	3031	3030										
ATAN	4979	29 3										
ATANF	0068	29 3										
ATL	1929	1928	2322	2882								
AVAIL	0494	1190	1204	1221	1226	3826	4439					
B0000	0112	2386	2387	2388	2389	2390	2391	2392	2393	2394	2395	

B05	5129	0765	1430	1614	4485							
B10	5130	0862	0863	0876	0877	1553	1653	3832	3921			
B5	5128	1609										
BAND	0495	1004	1058	1746	1747	1748	3681	3845	3885			
BCOMP	0105	2916										
BED	3128	3961	4067	4093	4177	4192						
BIG01	5081 3842	0706 3844	0771 3846	1824 4489	1950	2171	2356	2396	2897	3244	3453	3724
BIG02	5082	1600	2395	2574	2917	3014	3402	3659	4100	4122		
BIG03	5083	3775										
BIG04	5084	1085	2109	2259	3492	4204	4312					
BIG05	5085 4137	0868 4157	0882	0906	1364	1938	2016	2774	3279	3850	3995	4049
BIG07	5086	1958	2041									
BIG09	5087	2812										
BIG0G	5088	3716										
BIG10	5089	1549	1987	2431	2796	2979	3322	3697	3993	4046	4237	
BIG13	5090	3638	3669									
BIG20	5091	2362	2792	3582	4263							
BIG21	5092	0808	2679	2699	3290							
BIG24	5093	3783										
BIG25	5094	0618	1921	1955	1991	3763						
BIG29	5095	3032										
BIG30	5096	0684	1917	2068	2279	2406	2788	2842	3060	3765	4060	
BIG37	5097	4261										
BIG40	5098	2571	2596	3173	3297	3332	3896					
BIG50	5099	0869	0883	0884	0925	0944	2111	3130	3386	3423	3767	3848
BIG60	5100	0817	1801	2070	2113	2887	3353	3720	4007	4052		
BIG69	5101	2078										
BIG70	5102	1828	2469	3755	4039	4059	4126					

BIG71	5103	0697									
BIG77	5104	1929									
BIG87	5105	2349	2753								
BIG90	5106	1755	1768	2442	2840	2866	4092	4138	4159		
BIG99	5107	0750	1780	2743	3303						
BIN-	0048	2463									
BINAL	2402	2451	2619								
BINER	2490	2486	2488	2539	2541	2557	2559	2565			
BIN!#	0063	2859	2857	2891							
BIN&	0051	2484	2480								
BINOP	2400	2551	2575								
BIN*	0057	2537	2738								
BIN**	0061	2563									
BINSB	2399	2455	2538	2556	2581	2554	2571	3980	4257	4258	
BKOF	0869	0884	0925	0864	0867	1389					
BKON	0863	0877	0903	1410							
BKSW	0862	0876	0902	0853	0875	0901	0939	1390	1411		
BLANO	0106	2572									
BME	1900	0215	2415								
BOOLS	2942	2950	3104	3126							
BOR	0107	2573									
BR1	1234	1253	1978	2117	2141	2146	3425	3754	3769	4042	
BR2	1233	3118	3330	3341	3598	4094					
BR	1235	1227	1234	1804	1982	4193					
BU1	0950	1052	1665	1673	1714	1723					
BU	0951	0949	0950	3931							
C0000	0113 1802	1812 1811	1827 1826	1838 1838	1939 1940	2000 1999	2022	2086	3987	0114	0114	1794
C345	4925	2614									
C3#4	4927	2615									
C3#5	4928	2616									

C4#5	4926	2222	2227	2617								
CALMD	5076	3328										
CALPK	2296	2295	3585									
CALRM	1337	1335	1336	1357	1361							
CALS	3320	5076										
CAL.	3319	5076										
CASIN	2158	1942	1960	2026	2257	3781						
CHALT	0959	0949	3932									
CHI	0566	0951	0973	1025	4288	4295						
CHOLD	0553	1551	1608	2255								
CLACC	2048	1939	2244	3176	3292							
CLD	3549	3464	3548									
CMOVE	0974	1026	0948									
COL15	0497	1099	1425	1426								
COLON	2583	2477	2582									
COMMD	5064	3127										
COMON	0044	3114	3117	3847	3887							
COMPL	4986	2915										
COMS	3127	5064										
COMT	0498 4486	1509	1510	1552	1606	1607	1615	1914	1969	2099	2303	2314
COM.	3108	3127	5064									
CONO	0249	2499	2544	2581	2691	2696	2783	2946	4175			
CON2	4995	2570										
CONST	1362	1310	1311	2025	2256	3603	3780	4247				
COP	4929	2219	2276	2400								
COR10	2018	2000										
COR11	2037	2022										
CORES	2074	2018	2037									
COS	4982	2901										

PHILADELPHIA, PA.
SAME AS SPERRY RAND CORPORATION, UNIVAC DIVISION

COSF	0066	2901								
CRAND	2963	2949	3747							
CRDC	0954	0960	0963	0971	1023	4487				
CRDSW	0554	0962	0951	0964	0973	1025	4488			
CREAD	0948	0943	1102							
CSUB	4924	2349								
CTP	1014	1018								
CTRC	4923	2894								
CYC1	3545	3542	3543	3544						
CYCLE	3544	3475	3513							
D1MMD	5065	3040	3235							
D1MS	3104	2619	3323	3327	5065					
D1M%	3103	3083	3099	3100	5065					
DIM	3043	3236								
DIMMD	5066	3068								
DIMS	3070	5066								
DIM%	3071	5066								
DIM$	0084	3024								
DIVBS	0499	1464	1469	1476	1477					
DIVRT	1464	1463	2628	2632	2737	3222				
DIVT1	1462	1461	2655	3174						
DIVT2	1460	2536	3293	3608						
DOCK3	2440	2437	2439	2506						
DOEOF	1426	3448	4481							
DOEON	3390	3382	3447							
DOESW	0560	1425	1422	3383	3449	4482				
DOIF	2590	2589	3168							
DOMD	5067	3160	3644							
DON	0487	3183	3229	3680	3722	3734	3737	3738	3749	3751
DONT1	0101	3223								

DONT	3215	3169	3193									
DOO	3229	3170										
DOOST	0534	3232	3377	3390	3442	4473						
DO$1	0108	3172	3171									
DO$	3170	5067										
DO$SB	3171	3170	3648									
DOTAG	0500	2984	3187	3194	3408	4490						
DOVAR	0501	0805	2311	2987	3212	3411	3439	4474				
DOWN	3312	3251										
DO↑	3168	5067										
DSAVE	0557	1461	1478	1480	2624	4475						
DUA	3293	2620	2621	3238	4076							
DUMMY	0228	3829										
E0000	0115	0765	0786	0787	0788	0789	0790	0792	1274	1277	1278	1283
	1285	1291	1302	1326	1328	1334	1335	1336	1344	1346	1347	1348
	1349	0241	0677	0753	0785	0786	0787	0796	1282	1284	1294	1301
	1323	1325	1327	1333	1343	1345						
EEE	1898	1897	2888									
ENTER	3633	3629	3632									
EQ1MD	5068	4074										
EQ1$	3125	3124	3673	5068								
EQ1↑	4079	4078	5068									
EQASN	4031	4030	4209									
EQSVB	4090	4089	4188									
EQUMD	5069	2757	4087									
EQU$	4211	5069										
EQU↑	4089	5069										
EQU%	0100	4168										
EROUT	1321	1297										
EXIT1	0507	0836	0938	1108	1122	1133	1163	1169	1216	1217	1232	1259
	1258	1273	1632	1644	1698	3691	3705	3713	4032	4067	4071	4090
	4173											
EXIT2	0508	1363	1369	1539	1544	1550	1557	1620	2110	2126	2150	3568

	3966	3969	3972	4599	4608							
EXIT3	0509 3356	1388 3365	1411	1519	1538	2051	2073	2162	2170	3006	3015	3349
EXIT4	0510 3348	1909	1933	1946	1959	1977	2074	2083	2296	2304	2307	3329
EXIT5	0511	1865	1908	2099								
EXIT6	0512	1851	1870	1895	1897	3662	3667					
EXIT7	0513	2174	2189	2190	3778	3791						
EXIT8	0514	3171	3228	3284	3292	3938	3951					
EXIT9	0515	3252	3309									
EXP	4977	2899										
EXPF	0070	2899										
EXPL	2586	2585	2589									
EXPL8	2587	2586	2975	3000	3003	3028	3586					
F0000	0116	3267	3268	3276	3279	3294	0117	3266	3267			
FARNL	1739	1524	2122	2130	2336	2339	2340	2344	2358	3326	3663	
FASIN	3329	3237	3324									
FBSB1	3774	3758	3770									
FBSUB	3778	3764	3766	3768								
FCEX	3278	1939	3268									
FCMD	5070	2686	3241									
FC$	3246	5070										
FC%	3242	5070										
FC#	0102	3247										
FGFG	4526	4545	4603									
FMSUB	3564	3538	3541									
FILNX	2354	2353	3309	3327								
FILUP	1750	1529	1781	2354	2996	3438	3665	3725				
FIXA	4985	2862	2895									
FIXF	0099	2895										
FLOTA	4984	2863	2911									

FLOTF	0098	2911										
FOR95	3149	2601	4150									
FORCE	3526	3495	3497	3498	3511							
FS	0491	3336	3337	3342	3831							
FSIGN	3516	3508	3509	3510								
FSW	3542	3463	3475	3527								
FSWOF	3543	3462										
FSWON	3551	3474	3542	3543								
FUNCT	3234	0694										
GEN	0678	0822	1422	1474	1481							
GENX	0516	0676	0682	1463								
GET	2964	2754	2873	3020	3218	3289	3631					
GOMD	5071	3001										
GO$	3020	5071										
GOSUB	3006	3015	3036									
GOTO	1777	2338	2982	3025	3373	3398	3656	3793				
GO%	3003	5071										
GO%	0073	3016										
H0000	0118	0122	0122	0123	0123	0124	0124	0125	0125	0126	0126	0127
	0135	0135	0136	0136	0137	0968	0970	0975	0976	0977	0981	0982
	0983	0986	0987	0991	0992	0993	0996	0997	0999	1007	1008	1020
	1022	1027	1028	1032	1033	1037	1038	1042	1043	1047	1048	1052
	1053	1072	1073	1077	1078	4527	4528	4529	4530	4531	4532	4533
	4534	4546	4547	4548	4549	4550	4551	4552	4553			
H10	5127	0969	1021	3979	4307							
H1	5125	1986	3321									
H5	5126	1095	1574	2290	2445	3880						
HALT	3953	3957	3975									
HCC	0961	0960	0974	1026								
HDW2	0128	0138	3958	3960								
HDW3	0129	0139	3964									
HEAD1	3693	3799	3883									
HEAD	4996	3357	3359	3795	3801	4479						

HOL	3532	3505										
HOLSB	1388	1387	3566									
HROUT	1387	1299										
HWD1	0127	0137	3933									
10000	0142	2187	2190	2192	2193	2194	2195	2196	2197	2198	2199	2200
	2201	2202	2203	2204	2205	2206	2207	2208	2209	2210	2211	2212
	2213	2214	2215	2216	2217	2218	2221	2226	2231	2244	2248	2252
	2263	2268	2284	2285	2291	2293	2311	2315	2318	2327	2336	2344
	2355	2358	4259	4262	0143	0143	2180	2182	2243	2252	2253	2254
	2264	2280	2314	2335	2875	3202	3203	3299	3785			
IFMD	5072	2584										
IF$	2595	5072										
IF%	2589	5072										
IF%	0053	2580										
IMPUO	3662	3640	3654									
IN	3629	3573										
INCR1	0479	0639	4476									
INCRE	0502	1740	1994	3146	4477							
INCUQ	1790	1541	2046	2055	217	2958	3012	3771				
INDEX	2678	2712	2739									
INIT	3794	3935	4508									
INITT	3807	3805	4461									
INS2	2841	2830	2838									
INS99	1188	1148	1169									
INS	1169	0738	1821	2138	2841	3233						
INSMD	3041	3040	3107	3328	3591	3735						
INSRT	0738	0737	3616	3621								
IO1MD	5078	3591										
IO1$	3592	5078										
IO1%	3593	5078										
IO2MD	5079	3596										
IO2$	3668	3592	3611	5079								

SAME TO SPERRY RAND CORPORATION, UNIVAC DIVISION

IO2•1	0109	3618	3613										
IO2•	3609	3597	3628	3675	5079								
IO3MD	5080	3623											
IO3S	3674	5080											
IO3•	3675	5080											
IOARA	3598	3594											
IO#	3639	3587	3652										
IOOP	3578	3615											
IO%	3642	5062											
ISMD1	3042	3041	3160										
IWORD	0503	1533	1538	1758	1759	1775	1776	2319	3828				
IX	2186	2185	2223	2228	2237	2244	2249	2261	2310	2316	2321	2328	
	2334	2343	2353	2357	2364	4269							
&5ASM	1658												
&ASSM	1682	1732											
&ADD	2514												
&AL1	4313												
&AL2	4308												
&ALRM	4317												
&AR2	2842												
&ASSM	1684	1734											
&ASM5	1673	1723											
&ASN1	1829												
&ASN2	3994												
&ASN3	4008												
&ASN4	1817												
&BM	2415												
&CHFL	2747	2744											
&COR	3143												
&CRD2	1086												
&CRD3	1090	1625	4317										

&CRD	0962		
&DO2	3175		
&EEE	2868		
&EQ1	4129		
&EQU%	4195		
&EQV1	4047		
&EQV2	4053		
&EQV3	4040		
&EQV4	4060		
&EQ	4093	4104	
&ERUT	1357		
&FB	3769		
&FIL1	1756		
&FIL2	1769		
&FNC1	2536	2535	
&FUNC	3345	3344	
&GET	2968		
&GOD1	4466		
&GOD	4463		
&GOT1	1786		
&GOTO	1781		
&HF1	1879		
&HF2	1885		
&HOT	3536		
&I18	2330		
&IF1	2592	2939	
&IF2	2600	2597	
&IF3	2603		
&INP1	0840	1107	1121
&INRA	2877	2879	2972

&ISIS	4507											
&KIND	1251											
&L1	2455											
&L2	2460											
&LIS	3138											
&MAG	2754											
&MUL1	4217											
&MUL	4257	4231										
&OP1	0697											
&OP2	0698	0972	1024									
&OP3	0731											
&OP4	0733											
&PAR1	3289	3291										
&PAR4	3304											
&PAS2	3955	3962										
&PN	2696											
&POT1	3948											
&POT2	3950											
&POT	3943											
&PR1	1601											
&PR2	1605											
&PRG	3148											
&RE	2880											
&SAC	2402	2434	2446	2964	3318							
&SCRM	1149											
&SEND	0815											
&TRC	3133											
#OFF	2856	3165	3672									
JOOOO	0144	4882	4883	4884	4885	4886	4888	4889	4890	4891	4892	4893
	4894	4895	4896	4897	4899	4900	4901	4902	4903	4904	4905	4906
	4907	4908	4909	4910	4911	4912	4913	4914	4915	4916	4917	4918

	4919	4920	4921	4922	0145	2427	2861	2864	2880	2883	2919	2922
	2931	2968	2969	4252	4253							
JMPRL	1785	1927										
K0000	0146	4775	4776	4777	4778	4779	4780	4781	4782	4783	4796	4797
	4798	4799	4800	4801	4805	4808	4811	4814	4818	4819	4820	4821
	4822	4823	4824	4825	4826	4827	4844	4845	4846	4847	4848	4849
	4850	4851	4852	4853	4854	4855	4856	4857	4858	4859	4860	0147
	0147	0148	0148	0149	0149	0150	0150	0151	0151	0152	0152	0153
	0153	0154	0154	0155	0155	0156	0156	0157	0157	0158	0158	0159
	0159	0844	0845	0846	0847	0848	0849	0850	0857	0858	0874	0900
	0978	0979	0980	0984	0985	0988	0989	0990	0994	0995	0998	1000
	1001	1002	1006	1009	1010	1030	1031	1035	1036	1040	1041	1045
	1046	1050	1051	1055	1056	1061	1068	1069	1075	1076	1080	1081
	1087	1089	1093	1094	1103	1117	4462					
KINO	1238	0753	0785	1284	1327	1345	3469					
KN200	5138	1741	3886									
KON1	0238	5134	1643	1697	3260	3308	3358	3750	3788	3824	4179	
KON2	0240	5135	1193	2523	3256	3794	4454					
KON30	5137	1246	1328	2778								
KON3	5136	2379	2382	2449	3761							
KON.5	5133	1319	3191	4249								
KON*E	3980	4212	2545									
L0000	0160	2122	2125	2126	2127	2128	2146	0101	0161	2141	2124	2145
	2157											
LABEL	5045	1436	1451									
LABL	0074	3366										
LABLX	3370	2151	3369									
LAST	0504	0678	0682	1460	3122	3757						
LBLX1	3371	2156	3370									
LC	0559	1084	1086	1088	1599	1601	1603	3939	4311	4313	4315	4468
LCARD	4442	4441										
LDCN1	4512	45 6										
LDCN2	4511	45 7										
LDCN3	4510	4638										
LDCN4	4509	4639	4642									
LDLOF	2886	2885	2890									

LDLON	2860	2853	2856									
LEFT	3521	3496	3512									
LEOFF	1311	0630	1292	3166	4483							
LESW	0537 3367	1310 4484	0681	1293	1307	1309	1359	1361	1414	2588	3155	3167
LEVEL	0505	1003	1057	1739	1745	3825						
LEXP1	3376	3366										
LEXP	3385	2587										
LIR1	2317	1512	2315	2320								
LIT10	5143	2012	2038									
LIT11	5144	1951										
LIT1	5139 2659	0774 2701	0775 4584	0795	1375	1396	1407	1506	1677	1727	1879	1972
LIT4	5140	1405										
LIT5	5141	0777	1296	2479	2482	2526	3537					
LIT8	5142	0777	1298	1892								
LIT99	5145	3388										
LITA	5146	1350	4242									
LITB	5147	1239										
LLIST	0536	2136	2143	3414	4469							
LN	4978	2904										
LNF	0069	2904										
LOOP1	2177	1904	2176									
LOOP	2175	2174	2186	2224	2229	2290						
LPREN	5044	0693	2577	2653	2977	3612	4080					
LSW	0555	2103	1905	2981	3004	3196	3369	3410	3437	4498		
LSWOF	2108	3035	3276	3409	4497							
LSWON	2109	3195										
MAGET	2748	2747	3169									
MCAL	2598	2597	3019	3592								
MDOP1	0736	0734	0735	3002								

MDOP2	0734	3241										
MDOP	0735	2665	3069	4088								
MEML1	0481	0641	3807									
MEML2	0482	0642	4428									
MEML	0531	1194	3049	3050	3077	3078	3808	4145	4153	4167	4168	4171
MEMLL	0480	0640	4432	1433	1446	4428	4430					
MEMU1	3973	38,9	3816	4432	4453	4455						
MEMU2	0484	0644	3973									
MEMU	0527	1192	1196	3810	4433							
MISUB	2621	3125	3312	4491								
MLP	2624	2578	4081									
MODE	0227	5073	3874									
MROUT	1370	13,1										
MRP	2629	2851	2945	3070	3246	4211						
MZERO	5132	1151	1241	2301								
NOOOO	0162	0844	0845	0846	0847	0848	0849	0850	0857	0874	0900	0940
	0843	0940	3804									
NO1	5077											
N78	3571											
NAME	3691	3690	3803									
NAMEC	3252	3251	3593									
NEXTC	0506	0827	0830									
NINEF	0490	2342	2347	2355	2357	3230	3657	3664				
NNUMS	0517	0853	0888	0890	0908	0917	0919	0934	0936	0939		
NOMAL	2941	21,5	2592	2920								
NOMLZ	1255	13,7	1324									
NORM	0683	0679	0694	1462	3741	3757						
NORMX	0085	0675	0215	0737	2460	2586	2850	2915	2941	2962	2982	3005
	3042	3103	3124	3169	3245	3317	3375	3661	3738	3792	3875	3981
	4089	4187	4210	5058								
NOS	2943	2951	3233	3674	5073							

NOTAG	0519	0815	3131	3133	313	3143	3148	4480				
NO↑	2939	2940	3319	5073								
NPAR1	1969	1961	1968									
NPAR2	1970	1927	1969									
NPAR	1968	1911										
NWORD	0521	0843	0841	0842	0943	3805						
NXLOC	0496 3667	1520 3682	1523 3727	1782 3857	2047	2343	2354	3024	3375	3433	3441	3660
NXTCH	0558 3468	0853	0677	0750	0784	0829	0832	1283	1326	1344	1377	1398
NXTN	0834	0831										
NXTW	0830	0828	4508									
NZONS	0518	0853	0834	0886	0915	0931	3849					
00000	0163	3369	3695	3891	3897	3918	3923	3963				
OARA*	5059	2476	5061									
OARA%	5060	2494	2665	2710								
OBIN-	5046	2456										
OBIN&	0244	2462										
OBIN#	5047	2858										
OBN**	5048	2562										
ODIM%	5049	3069										
OEQU%	5050	4088										
OFC%	5057	3240										
OGO%	5056	3052										
OMOLD	0520	0707	0713	0727	2468							
OIF%	5051	2466	2579									
OIO%	5062	3620										
OLDLC	0522	1530	1532	3854								
OLPRN	5058	2547										
ONE15	5131	2144	3683									
ONWRD	3568	3506										

OOPO	0234	5054	2938									
OPO	0072	2955										
OPX	0710	0707	2401	2440	2441	2483	2508	2892	3039	4256		
O*	5053	2534										
OTYPE	0523	2398	2430	2443	2575	2898	2907	2918	2934	2972		
OUN-	5055	2455										
OUT	3631	3575	3577									
OWDIM	5052	3740										
POOOO	0164	4762	4763	4764	4765	4766	4767	4768	4769	4770	4771	4772
	4773	4774	4785	4786	4787	4788	4789	4790	4791	4792	4793	4794
	4795	4853	4834	4835	4836	4857	4838	4859	4840	4841	4842	4843
	0165	0165	0166	0166	0167	0167	0168	0168	0169	0169	0170	0170
	0171	0171	0172	0172	0173	0173	0174	0174	0175	0175	0176	0176
	0177	0177	1554	1555	1564	1566	1572	1573	1579	1580	1589	1590
	1593	1594	1602	1604	1612	1613	3833	3834	3902	3903		
PANIC	3979	4270	2622	3975								
PAR1	0524	2218	2221	2226	2263	2268	2271	2284	2285	2288	2330	2332
	2403	2447	4262									
PAR2	0525	2173	2187	2269	2272	2281	2286	2289	2293	2308	2327	2335
PAR3	0526	4235	4260	4267								
PARMO	5075	3735										
PARS	3739	3743	5075									
PARSB	3284	3242	3247									
PAR+	3736	5075										
PASS2	3937	3935										
PAUSF	4988	2925										
PCHOF	1675	1726	3149									
PCHON	1647	1721	3150									
PCHSW	1646	1720	1645	1699	3151							
PNSUB	2693	2713	2738	2740								
POP	3518	3502	3507									
POUT	3938	3932	3937									
POZMO	5074	2948										

POZS 2930 5074

POZ+ 2940 5074

PRIME 4462 5150

PRMS 4573 4640

PRNT 1562 1583 3922 3979

PROF 1607 1561 1582 3139 4493

PRON 1560 1572 3140

PRTS# 1606 1558 3141 4494

Q0000 0178 4931 4932 4933 4934 4935 4936 4937 4938 4939 4940 4941
4942 4943 4944 4945 4946 4947 4948 4949 4950 4951 4952 4953
4954 4955 4956 4957 4958 4959 4960 4961 4962 4963 4964 4965
4966 4967 4968 4969 4970 4971 4972 4973 4974 4975 4976 2485
2501 2538 2556 2561 2564 2567 2568 2572 2573 3980 4257 4258

R0000 0179 4863 4864 4865 4866 4867 4873 0133 0183 0184 0184 0185
0185 0186 0186 0187 0187 0188 0188 0189 0190 0196 0196 0197
0197 0198 0198 0199 1637 1638 1639 1640 1641 1645 1652 1654
1663 1671 1672 1680 1681 1682 1683 1684 1685 1691 1692 1693
1694 1695 1699 1706 1707 1713 1721 1722 1730 1731 1732 1733
1734 1735 3703 3704 3705 3711 3712 3713 3865 3871 4521 4522
4540 4541 4613 4614 4615 4616 4617 4618 4624 4625 4626 4627
4628 4629

RAND 0219 0226 2930 2963 3875

RATOR 0561 4661 0710 0717 0738 2463 2491 2707 2868 2943

REM 1217 0717 2054 2961 3391 3415 3819 4461

REMRT 0717 0716 2477 3607 3639

RESCN 3757 3617 3756

RESET 3462 3454 3518 3523 3529 3539 3541

RETRN 3793 3792 3876

RRRR 4084 4111 4133 4142 4182

RWD1 0190 0189 1676 1678 1725 1728 3879 3881 4594 4598 4605 4607

RWORD 0528 1531 1536 1752 1764 1769 1771 1778 3827

$ 0242 1415 3123 3610 3742

*LOAD 3936 3934

S0000 0202 0804 0809 0811 0813 0819 0820 0821 0203 0203 0204 0803

SACC	2431	2430	3318									
SCAN1	0241	0730	0822	1431	1446	3131	3136	3141	3146	3151	4495	
SCAN9	0822	0807	0808	0812	0819	0820	0821	1436	1451	4440		
SCAN	0676 4079	0675	0692	2533	2576	2652	2976	3016	3368	3609	3685	3739
SCANX	0529	0677	0676	0679	1465	4496						
SCNXX	0530	1468	1479	1481								
SEND1	0798	0797	1320									
SEND	0797	0791	3389									
SETNS	0827	0786	0787	1302	1323	1334	1335	1336	1346	1347	1348	
SGN**	2562	2535										
SHEAD	3356	3899										
SHFT4	0944	0941										
SHFT	0532	0853	0852	0938	0942	1435	1450					
SHFTF	0946	0859	0945									
SIGN-	0049	2452										
SIGN'	0080	1415	3568									
SIGN&	0050	2458										
SIGN#	0062	2853	3159	3588	3653	3673						
SIGN$	0059	2550	2942	3027								
SIGN*	0056	2533										
SIGN/	0060	2555										
SIGN+	0058	2548										
SIGN%	0046	2547										
SIN	4983	29 0										
SINF	0065	29 0										
SQRT	4981	29 5										
SQRTF	0064	29 5										
SQUAR	2923	2571										
SRCH1	1130	0791	1129									

SRCH	1129	1366	3389									
STAN	0939	0957	0946	1437	1452							
STOPF	4989	2926										
STORE	0042	2772										
SUBDF	3349	2357	3340									
TOOOO	0205	4998	4999	5000	5001	5002	5003	5004	5005	5006	5007	5008
	5009	5010	5011	5012	5013	5014	5015	5016	5017	5018	5019	5020
	5021	5022	5023	5024	5025	5026	5027	5028	5029	5030	5031	5032
	5033	5034	5035	5036	5037	5038	5039	5040	5041	5042	5043	0206
	0242	0243	0244	0245	2536	2628	2632	2655	2726	2737	3174	3185
	3222	3293	3606	3608								
TAN	4980	2952										
TANF	0067	2952										
TARA*	0054	5061										
TARA%	0055	2656										
TAS32	2316	2315	4261									
TASM2	2185	2184	2283									
TEMP1	0538	1169	1212	1224	1230	1291	1295	1558	1581	1616	1805	1815
	1827	1835	3115	3119	3416	3430	3991	4023	4031	4042	4043	4048
	4050	4056	4139	4150	4160	4164						
TEMP2	0539	0706	0779	0783	0792	1132	1143	1256	1265	1267	1274	1280
	1285	1288	1308	1313	1325	1356	1357	1360	1362	1372	1376	1393
	1404	1438	1540	1556	1560	1563	1591	1619	1817	1823	2129	2135
	2168	2768	2775	2777	2787	2789	2807	2814	2836	3011	3281	3350
	3355	3384	3385	3565	3614	3617	3988	3997	4001	4010	4012	4026
	4037	4070	4136	4158								
TEMP3	0540	0776	0788	0789	0796	0797	0804	0812	0818	1129	1137	1270
	1282	1290	1312	1341	1352	1371	1385	1392	1399	1402	1414	1518
	1537	2859	2837	3567	3812	3820	3821	3990	4002	4005	4006	4017
	4019	4028	4035	4065	4154	4172	4562	4566				
TEMP4	0541	0798	1130	1148	1163	1343	1349	1354	1397	1403	1517	1539
	1788	1865	1973	3996	4003							
TEMP5	0542	1813	1814	1876	1883	1910	1916	1949	1954	1976	1985	1990
	3269	3273	3372	3374	3393	3399	3404	3465	3533	3536	3546	3559
	3557											
TEMP6	0543	1915	3395	3446	3466	3513	3551					
TEMP7	0544	1853	1884	1896	1908	2097	3470	3473	3547	3550	3554	3561
TEMP8	0545	1856	1869	3467	3516	3545	3548	3559	3563			
TEMP9	0546	1857	1862	3482	3494	3526	3528					

TEMPS	0535	1821	2054	3855	4473							
THETA	0562	1091	1092	4284	4285	4286	4287	4293				
THREF	0489	2337	2352	2359	3625	3726						
TMP10	0547	1850	1855	1858								
TMP11	0548	1980	1993	2005	2013	2023	2031	2082	2088	2091	2093	
TMP12	0549	1984	2098									
TMP13	0550	1993	2177	2186	3760	3787	3789					
TOB	2340	3649										
TOB10	2342	3646										
TOBSW	2339	2338	3647	3650								
TRACE	4987	2893										
TRCOF	2254	2870	3134	4501								
TRCON	2255	3139										
TRCSW	2253	2871	3136	4502								
TROFF	1822	1820	3177									
TRON	1819	3227	4499									
TRSW	0556	1818	1817	3178	3228	4500						
TW095	5148	2452	2458	3052								
TW08	0488	2341	3231	3627								
TYPE	0493	0773	0794	0807	1279	1303	1316	1320	1321	1413	3387	
UASW	0552	2620	2654	3106	3126	3239	3313	3595	4077	4492		
UN-	0047	2481										
UNIQU	0043 3759	1790 3762	1793 3774	1832 3843	1834 3892	2075 4025	2164 4029	3031	3257	3259	3452	3719
UNOP1	2446	2444	4256									
UNOP2	2445	2974										
UNOP3	2442	2881	2884									
UNOP	2441	2919	2934									
V0000	0207	1895	1897	1902	1905	1978	0208	1894				
VAR	3513	3474	3499	3500	3501	3503	3504					

WOOOO	0209 3839	4990	4991	4992	4993	4994	1825	2072	2300	2302	2305	3838
WARN	4997	3362	3797	3953								
WD	0564	4276	4309									
WDCAL	0104	3328										
WDCOM	0096	3125										
WDCOR	0082	3142										
WDDIM	0095	3040	2996									
WDDOI	3156	3155	3641									
WDDO	0045	3152										
WDEND	0088	3876										
WDEQU	0097	3981	4074									
WDFMT	0093	3452										
WDFOR	0079	4513	4429									
WDFUN	0089	3676										
WDGO	0076	2975										
WDIF	0052	2576										
WDLIS	0078	3137										
WDNO	0077	3130										
WDPCH	0103	3574										
WDPOZ	0086	2925										
WDPRG	0110	3147										
WDPRT	0092	3576										
WDRED	0091	3572										
WDRTN	0094	3792										
WDS	0563	4274	4310									
WDSTP	0087	2926										
WDSUB	0090	3678										
WDTRC	0081	3132										
WDTRU	0083	3133										
XOOOO	0210	3468	3470	3474	3476	3477	3495	3496	3497	3498	3499	3500

	3501	3502	3503	3504	3505	3506	3507	3508	3509	3510	3511	3512
	3467	3469	3473	3484	3485	3516	3544					
X05	5120	1100										
X1	5117	1761	1786	1971	2087	2742	2767	2800	2846	2909	2914	2933
	2970	3162	3316	3346	3405	4033	4064	4099				
X3	5118	3635										
X45	5123	2297	3255									
X49	5121	0895	2811									
X5	5122	1105	1119	1656								
X89	5124	3487	3492									
X9	5119	1108	1122	2189	2408	3779						
XCO	5116	2142	3426	4120								
XC	5110	1511	1546	1774	1868	1936	2134	2346	2361	2551	2795	3056
	3889	4061	4113									
XLINE	3684	3793	3859									
XM1	5114	0728										
XM	5109	1067	1230	1234	1803	1875	1907	2720	2826	3010	3113	3280
	3380	3394	3401	3422	3445	3581	3602	3687	4009	4041	4054	4069
	4130	4561										
XMC	5111	2684	2786	3163	3643	3895						
XMH	5115	1806	2014	2024	2126	2147	2154	2802	3371	3397	3418	3431
	3994	4047	4095									
XO	5108	0714	0811	1766	1852	2282	2318	2422				
XOC	5113	1208	1548	1952	2060							
XOM	5112	0819	0820	0821	1657	1703	1770	1783	2127	2128	3061	4581
Z0000	0211	4662	4663	4664	4665	4666	4667	4668	4669	4670	4671	4672
	4673	4674	4675	4676	4677	4678	4679	4680	4681	4682	4683	4684
	4685	4686	4687	4688	4689	4690	4691	4692	4693	4694	4695	4696
	4697	4698	4699	4700	4701	4702	4703	4704	4705	4706	4707	4708
	4709	4710	4711	4712	4713	4714	4715	4716	4717	4718	4719	4720
	4721	4722	4723	4724	4725	4726	4727	4728	4729	4730	4731	4732
	4733	4734	4735	4736	4737	4738	4739	4740	4741	4742	4743	4744
	4745	4746	4747	4748	4749	4750	4751	4752	4753	4754	4755	4756
	4757	4758	4759	4760	4761	1142	3814	4456				
ZLINK	4085	4118	4146	4189								
ZZONS	4609	4464	4515	4608								

SAME TO SPERRY RAND CORPORATION, ET AL. DEMAND