


```
.NLIST
.TITLE MAC$DEFINE      MACRO LIBRARY DEFINITION FILE FOR MACRO
.IDENT 'V04-000'
```

```
*****
*  COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
*  DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
*  ALL RIGHTS RESERVED.
*
```

```
*  THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
*  ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
*  INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
*  COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
*  OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
*  TRANSFERRED.
*
```

```
*  THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
*  AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
*  CORPORATION.
*
```

```
*  DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
*  SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
*
*
*****
```

```
♦♦
: FACILITY:      VAX MACRO ASSEMBLER OBJECT LIBRARY -- FACILITY NUMBER 125.
```

```
: ABSTRACT:
```

```
: The VAX-11 MACRO assembler translates MACRO-32 source code into object
: modules for input to the VAX-11 LINKER.
```

```
: ENVIRONMENT:
```

```
: AUTHOR: Benn Schreiber, CREATION DATE: 20-AUG-78
```

```
: MODIFIED BY:
```

```
 V03-002 ROP0024      Robert Posniak  18-JUL-1984
           Add new flag (FLG$V NULCHR) to indicate null
           parameter in IRP definition.
```

```
 V03-001 MTR0031      Mike Rhodes     13-Apr-1983
           Add the .LINK directive terminal definition to the macro
           $MAC GRAMMARDEF. Additionally, $MAC TIRCMDDEF has been
           deleted and $MAC OBJCODDEF has been modified to include
           the $OBJDEF macro (from SYSS$LIBRARY:STARLET.MLB).
```

```
 V03.00  MTR0003      Mike Rhodes     15-Mar-1982
           Added two new flags to allow Macro to exit with the
           proper exit status. The flags FLG$V EXTERR and FLG$V EXTWRN
           are set to indicate that a non-assembly error (eg. RMS, LBR,
           SUM, etc.) has occurred. Fixes SPR #11-41651(A).
```

```
 V02.21  MTR0001      Mike Rhodes     02-Feb-1982
           Add FLG$V DLIMSTR to correct the handling of "-;"
           strings in delimited .ASCII strings. QAR #890 and
           SPR #11-42904.
```

```
ML=
MF=
MG=
MH=
MI=
MJ=
MK=
ML=
MM=
MN=
MO=
MP=
MQ=
MR=
MS=
MT=
MU=
MV=
MW=
MX=
MY=
MZ=
NA=
NB=
NC=
ND=
NE=
NF=
NG=
NH=
NI=
NJ=
NK=
NL=
NM=
NO=
NP=
NQ=
NR=
NS=
NT=
NU=
NV=
NW=
NX=
NY=
NZ=
OA=
OB=
OC=
OD=
OE=
OF=
OG=
OH=
OI=
OJ=
OK=
OL=
OM=
ON=
OO=
OP=
OQ=
OR=
OS=
OT=
OU=
OV=
OW=
OX=
OY=
OZ=
PA=
PB=
PC=
PD=
PE=
PF=
PG=
PH=
PI=
PJ=
PK=
PL=
PM=
PN=
PO=
PP=
PQ=
PR=
PS=
PT=
PU=
PV=
PW=
PX=
PY=
PZ=
QA=
QB=
QC=
QD=
QE=
QF=
QG=
QH=
QI=
QJ=
QK=
QL=
QM=
QN=
QO=
QP=
QQ=
QR=
QS=
QT=
QU=
QV=
QW=
QX=
QY=
QZ=
RA=
RB=
RC=
RD=
RE=
RF=
RG=
RH=
RI=
RJ=
RK=
RL=
RM=
RN=
RO=
RP=
RQ=
RR=
RS=
RT=
RU=
RV=
RW=
RX=
RY=
RZ=
SA=
SB=
SC=
SD=
SE=
SF=
SG=
SH=
SI=
SJ=
SK=
SL=
SM=
SN=
SO=
SP=
SQ=
SR=
SS=
ST=
SU=
SV=
SW=
SX=
SY=
SZ=
TA=
TB=
TC=
TD=
TE=
TF=
TG=
TH=
TI=
TJ=
TK=
TL=
TM=
TN=
TO=
TP=
TQ=
TR=
TS=
TT=
TU=
TV=
TW=
TX=
TY=
TZ=
UA=
UB=
UC=
UD=
UE=
UF=
UG=
UH=
UI=
UJ=
UK=
UL=
UM=
UN=
UO=
UP=
UQ=
UR=
US=
UT=
UU=
UV=
UW=
UX=
UY=
UZ=
VA=
VB=
VC=
VD=
VE=
VF=
VG=
VH=
VI=
VJ=
VK=
VL=
VM=
VN=
VO=
VP=
VQ=
VR=
VS=
VT=
VU=
VV=
VW=
VX=
VY=
VZ=
WA=
WB=
WC=
WD=
WE=
WF=
WG=
WH=
WI=
WJ=
WK=
WL=
WM=
WN=
WO=
WP=
WQ=
WR=
WS=
WT=
WU=
WV=
WW=
WX=
WY=
WZ=
XA=
XB=
XC=
XD=
XE=
XF=
XG=
XH=
XI=
XJ=
XK=
XL=
XM=
XN=
XO=
XP=
XQ=
XR=
XS=
XT=
XU=
XV=
XW=
XX=
XY=
XZ=
YA=
YB=
YC=
YD=
YE=
YF=
YG=
YH=
YI=
YJ=
YK=
YL=
YM=
YN=
YO=
YP=
YQ=
YR=
YS=
YT=
YU=
YV=
YW=
YX=
YY=
YZ=
ZA=
ZB=
ZC=
ZD=
ZE=
ZF=
ZG=
ZH=
ZI=
ZJ=
ZK=
ZL=
ZM=
ZN=
ZO=
ZP=
ZQ=
ZR=
ZS=
ZT=
ZU=
ZV=
ZW=
ZX=
ZY=
ZZ=
```


KAD
KBY
KDO
KFI
KFL
KLO
KQU
KWO
KBL
KBL
KBL
KBL
KBL
KBL
KIF
KII
KIF
KIF
KIF
KIR
KIR
KRE
KEN
KEN
KMA
KMC
KME
KEN
KMD
KDE
KDS
KEN
KEN
KVE
KAL
KEV
KOD
KEX
KGL
KIN
KLI
KLI
KNL
KNA
KNC
KPA
KPS
KRE
KSA
KTI
KID
KSB
KWE
KRE
KRE
KRE
KER
KPR
KWA
KNT
KOP

.SBTTL DECLARATIONS

: INCLUDE FILES:

: MACROS:

: EQUATED SYMBOLS:

: OWN STORAGE:

KENI
KXFE
KASO
KCRG
KNCF
KDFL
KSGP
KSGP
KBLI
KBLI
KBLI
KBLI
KGFJ
KHFI
KOCI
KREI
KLII

```
.SBTTL SYMBOL_BLOCK DEFINITIONS
```

```
++
THIS MACRO DEFINES THE SYMBOL AND PSECT BLOCK OFFSETS
--
```

```
.MACRO $MAC_SYMBLKDEF
```

```
SYMSK_MAXLEN = 31. ; Maximum symbol name length
```

```
++
ALPHA-NUMERIC SYMBOL BLOCK
```

```
THIS IS THE BASIC SYMBOL BLOCK USED TO INSERT USER-DEFINED
SYMBOLS INTO THE USER SYMBOL TABLE. THE OFFSETS ARE DEFINED
IN RELATION TO THE BEGINNING OF THE SYMBOL BLOCK.
--
```

```
.PSECT $ABS$,ABS
```

```
.=0
```

```
SYMSL_LINK: .BLKL 1 ;LINK TO NEXT SYMBOL OR 0
SYMSB_NAME: .BLKB 1 ;OFFSET FROM BASE TO NAME
SYMSL_VAL: .BLKL 1 ;SYMBOL VALUE (32 BITS)
SYMSW_FLAG: .BLKW 1 ;SYMBOL FLAGS
SYMSB_TOKEN: .BLKB 1 ;TOKEN VALUE
SYMSB_SEG: .BLKB 1 ;SEGMENT (PSECT) DEFINED IN
SYMSK_BLKSI: .BLKB 1 ;FIXED PART SIZE OF A SYMBOL BLOCK
```

```
++
LOCAL SYMBOL (FORM nnnnn$)
```

```
SYMBOL BLOCK IS THE SAME AS A A/N SYMBOL BLOCK. THE SYMBOL
NAME IS STORED AS <1 BYTE>LSB NUMBER + <2 BYTES> VALUE.
--
```

```
++
OPCODE SYMBOL
```

```
OPCODES ARE STORED IN A SEPARATE SYMBOL TABLE. THE SYMBOL
BLOCK TO DEFINE AN OPCODE IS THE SAME AS THE A/N SYMBOL
DEFINITION BLOCK WITH THE FOLLOWING EXCEPTIONS:
```

- 1) SYMSB_SEG DEFINES THE NUMBER OF OPERANDS WHICH THE
SYMBOL MAY HAVE. IF THE SYMBOL IS A GENERIC
SYMBOL (I.E. DIV AS OPPOSED TO DIV2 OR DIV3)
THIS COUNT WILL BE 0 AND A FLAG (SYMSV_GENERIC) WILL
BE SET IN THE SYMSL_FLAG WORD.
- 2) FOLLOWING THE SYMSB_SEG BYTE THERE ARE STORED THE OPERAND
BYTE DESCRIPTORS. THERE IS ONE BYTE FOR EACH
OPERAND THAT AN OPCODE MAY HAVE.

```
++
SYMBOL FLAGS
```

```
THE FOLLOWING FLAGS ARE DEFINED AND MAY BE PRESENT IN THE
FLAGS WORD (SYMSL_FLAG).
--
```

```

.MACRO $$SYM BITDEF      SYMBOL
SYMSM 'SYMBOL=X1
SYMSV 'SYMBOL=X2
X1 = X1 @ 1
X2=X2+1
.ENDM  $$SYM_BITDEF

```

```

X1=1
X2=0

```

```

; BIT ON IN FLAG WORD IMPLIES:
$$SYM_BITDEF DEF      ;SYMBOL HAS BEEN DEFINED
$$SYM_BITDEF WEAK     ;SYMBOL IS DEFINED .WEAK
$$SYM_BITDEF GLOBL   ;SYMBOL IS DEFINED .GLOBAL
$$SYM_BITDEF EXTRN   ;SYMBOL IS DEFINED .EXTERNAL
$$SYM_BITDEF ABS     ;SYMBOL IS ABSOLUTE
$$SYM_BITDEF DEBUG   ;SYMBOL HAS .DEBUG ATTRIBUTE
$$SYM_BITDEF LOCAL   ;SYMBOL IS A LOCAL LABEL
$$SYM_BITDEF REF     ;SYMBOL HAS BEEN REFERENCED
$$SYM_BITDEF ASN     ;SYMBOL CREATED BY ASSIGNMENT STATEMENT
$$SYM_BITDEF EPT     ;SYMBOL CREATED BY .ENTRY
SYMSM_DELMAC=SYMSM_EPT ;MACRO DEFINITION HAS BEEN DELETED
SYMSV_DELMAC=SYMSV_EPT ;MACRO DEFINITION HAS BEEN DELETED
$$SYM_BITDEF ODBG    ;SYMBOL TO BE OUTPUT TO DEBUG RECORD
$$SYM_BITDEF RELPSECT ;SYMBOL IS REFERENCED IN A REL PSECT
$$SYM_BITDEF XCRF    ;DO NOT CREF THIS SYMBOL
$$SYM_BITDEF CRFO    ;INSERT KEY HAS BEEN DONE FOR THIS SYMBOL
$$SYM_BITDEF SUPR    ;BIT IS SET UNTIL SYMBOL IS REFERENCED

```

```

:++
: PSECT NAME BLOCK
:
: THE PSECT NAME BLOCK IS IDENTICAL TO THE A/N SYMBOL BLOCK WITH
: THE FOLLOWING EXCEPTIONS: 1) THE SYMSB_TOKEN BYTE IS UNUSED,
: AND 2) THERE ARE TWO ADDITIONAL FIELDS--THE OPTIONS FLAGS WORD
: (16 BITS) AND THE CURRENT LOCATION COUNTER (32 BITS).
:
:--

```

```

.=0
PSC$L_LINK: .BLKL 1 ;LINK TO NEXT PSECT NAME BLOCK OR 0
PSC$B_NAME: .BLKB 1 ;OFFSET FROM BASE TO PSECT NAME
PSC$L_MAXLGTH: .BLKL 1 ;PSECT MAXIMUM LENGTH
PSC$W_FLAG: .BLKW 1 ;PSECT FLAGS
PSC$B_UNUSED: .BLKB 1 ;UNUSED BYTE
PSC$B_SEG: .BLKB 1 ;PSECT SEGMENT NUMBER
PSC$W_OPTIONS: .BLKW 1 ;PSECT OPTIONS
PSC$L_CURLOC: .BLKL 1 ;PSECT CURRENT LOCATION
PSC$K_BLKSIz: ;FIXED PART SIZE OF PSECT BLOCK

```

```

:++
: PSECT FLAGS
:
:--

```

```

.MACRO $PSC BITDEF      SYMBOL
PSC$M 'SYMBOL=X1
PSC$M_ALLOPTNS = PSC$M_ALLOPTNS ! X1
PSC$V 'SYMBOL=PSC$K_NO_OPTNS
X1=X1@1
PSC$K_NO_OPTNS=PSC$K_NO_OPTNS+1
.ENDM

```



```

X1=1
PSC$K_NO_OPTNS=0
PSC$M_ALCOPTNS=0

$PSC_BITDEF PIC ;PIC CODE
PSC$M_NOPIC=^C<PSC$M_PIC> ;NON-PIC CODE
$PSC_BITDEF LIB ;
PSC$M_USR=^C<PSC$M_LIB>
$PSC_BITDEF OVR
PSC$M_CON=^C<PSC$M_OVR>
$PSC_BITDEF REL
PSC$M_ABS=^C<PSC$M_REL>
$PSC_BITDEF GBL
PSC$M_LCL=^C<PSC$M_GBL>
$PSC_BITDEF SH
PSC$M_NOSHR=^C<PSC$M_SHR>
$PSC_BITDEF EXE
PSC$M_NOEXE=^C<PSC$M_EXE>
$PSC_BITDEF RD
PSC$M_NORD=^C<PSC$M_RD>
$PSC_BITDEF WRT
PSC$M_NOWRT=^C<PSC$M_WRT>
$PSC_BITDEF VEC
PSC$M_NOVEC=^C<PSC$M_VEC>
PSC$M_EXE=PSC$M_EXE+PSC$M_RD ;READ ACCESS FOR EXE
PSC$M_WRT=PSC$M_WRT+PSC$M_RD ;READ ACCESS FOR WRT ALSO
PSC$V_ALIGNMENT = PSC$K_NO_OPTNS ;FIRST BIT OF ALIGNMENT FIELD
PSC$S_ALIGNMENT = 4 ;SIZE OF ALIGNMENT FIELD
PSC$V_ALIGNFLG = PSC$V_ALIGNMENT+PSC$S_ALIGNMENT ; BIT # OF ALIGNMENT FLAG
PSC$M_ALIGNFLG = 1@PSC$V_ALIGNFLG ;ALIGNMENT FLAG
PSC$M_BYTE = <0@PSC$V_ALIGNMENT>!PSC$M_ALIGNFLG ;BYTE ALIGNED
PSC$M_WORD = <1@PSC$V_ALIGNMENT>!PSC$M_ALIGNFLG ;WORD ALIGNED
PSC$M_LONG = <2@PSC$V_ALIGNMENT>!PSC$M_ALIGNFLG ;LONG ALIGNED
PSC$M_QUAD = <3@PSC$V_ALIGNMENT>!PSC$M_ALIGNFLG ;QUAD ALIGNED
PSC$M_PAGE = <9@PSC$V_ALIGNMENT>!PSC$M_ALIGNFLG ;PAGE ALIGNED

PSC$M_DEFAULT = PSC$M_REL!PSC$M_WRT!PSC$M_RD!PSC$M_EXE ;DEFAULTLT PSECT OPTIONS

.PSECT
.MDELETE $MAC_SYMBLKDEF, $$SYM_BITDEF, $PSC_BITDEF
.ENDM $MAC_SYMBLKDEF

```

CRF
CRF
CRF
CRF
CRF
CRF
CRF
CRF
CRF

.MACRO \$MAC_INPBLKDEF

..++

INPUT LINE CONTEXT BLOCK DEFINITIONS

THIS CONTEXT BLOCK IS USED BY THE CHARACTER INPUT ROUTINE TO GET THE NEXT LINE WHEN NEEDED.

..--

\$MAC_MNBDEF

.PSECT \$ABS\$,ABS

.=0

```
INPSL_LINK:      .BLKL  1      ;LINK TO NEXT BLOCK
INPSL_NXTL:      .BLKL  1      ;LINK TO NEXT LINE
INPSL_GETL:      .BLKL  1      ;ADDRESS OF ROUTINE TO GET NEXT LINE
INPSL_IFLVL:     .BLKL  1      ;"IF" LEVEL COUNTER
INPSL_IFVAL:     .BLKL  1      ;"IF" VALUE
INPSL_RPTCNT:    .BLKL  1      ;COUNTER FOR REPEAT/IRP
INPSL_PAGP:      .BLKL  1      ;POINTER TO PAGES USED BY THIS INPUT
                                ;BLOCK
INPSB_ARGCT:     .BLKB  1      ;ARGUMENT COUNT
INPSL_ARGS:      .BLKL  1      ;POINTERS TO ARGUMENTS
INPSK_BLKSIK:    .BLKL  1      ;SIZE OF AN INPUT BLOCK
```

.=0

```
INPSK_IRPSIZ:    .BLKB  <MNB$K_BLKSIK+SYMSK_MAXLEN+1> ;SIZE WHEN MNB IS MADE INTO INP
```

```
.MDELETE $MAC_INPBLKDEF
.ENDM $MAC_INPBLKDEF
```

..++

MACRO NAME BLOCK

THIS MACRO DEFINES THE MACRO NAME BLOCK (MNB) AND THE MACRO ARGUMENT BLOCK (MAB). THESE ARE USED FOR DEFINING MACROS.

..--

.MACRO \$MAC_MNBDEF

.PSECT \$ABS\$,ABS

.=0

```
MNB$K_LINK:      .BLKL  1      ;LINK TO NEXT MNB
MNB$B_NAME:      .BLKB  1      ;OFFSET FROM BASE TO MACRO NAME
MNB$K_TXTP:      .BLKL  1      ;POINTER TO TEXT
MNB$W_FLAG:      .BLKW  1      ;FLAGS
MNB$K_PAGP:      .BLKL  1      ;POINTER TO PAGES USED TO DEFINE MACRO
MNB$K_PAGC:      .BLKL  1      ;COUNT OF PAGES USED
MNB$K_CRSYMF:    .BLKL  1      ;CREATED SYMBOL FLAGS
MNB$B_ARGCT:     .BLKB  1      ;ARGUMENT COUNT (255. MAX)
MNB$K_ARGP:      .BLKL  1      ;POINTER TO ARG LIST
MNB$K_BLKSIK:    .BLKL  1      ;FIXED PART SIZE OF MACRO NAME BLOCK
```

..++

..--

.MAC
X=0
.MAC
ADM
X=X+
.ENC

COD
COD
COD
COD
COD
COD
COD
COD
COD
COD
COD
COD
COD
COD
COD

.MDE
.ENC

\$MAC_GENVALDEF

DEFINES THE COMMONLY USED VALUES. MUST BE INVOKED IN ANY
MODULE THAT REFERENCES ANY OF THESE VALUES.

.MACRO \$MAC_GENVALDEF

```

MAC SUBSYS = 125. ;MACRO-32 FACILITY NUMBER
HASRSZ = 127. ;HASH TABLE SIZE
CR = ^015 ;CARRIAGE RETURN
TAB = ^011 ;HORIZONTAL TAB
FF = ^014 ;FORM FEED
BLNK = ^040 ;BLANK
HYPHEN = ^A/-/ ;HYPHEN
SEMI = ^A/:/ ;SEMI COLON
CHRSV_CVTLWC = ^A/a/ ;CONVERT ANYTHING .GT. LOWERCASE A
CHRSV_NOCVT = ^X7F ;DO NOT CONVERT TO UPPERCASE
INTSK_BUFSIZ = <10*512>-<3*4> ;SIZE OF INT. BUFFER
INTSK_BUFWRN = INTSK_BUFSIZ-100 ;WARNING LIMIT
INPSK_BUFSIZ = 1000. ;Input buffer size
OBJSK_BUFSIZ = 512 ;OBJECT FILE BUFFER SIZE
LSTSK_BUFSIZ = 134. ;LISTING FILE BUFFER SIZE
LSTSK_TITLE_SIZ = 40. ;Size of title sub-string
REGS_PC = 15 ;PC REGISTER
RDXSV_BINARY = 0 ;INDEX FOR BINARY RADIX
RDXSV_OCTAL = 1 ;INDEX FOR OCTAL RADIX
RDXSV_DECIMAL = 2 ;INDEX FOR DECIMAL RADIX
RDXSV_HEX = 3 ;INDEX FOR HEX RADIX
RDXSV_FLOAT = 4 ;INDEX FOR F FLOATING NUMBERS
RDXSV_DOUBLE = 5 ;INDEX FOR D FLOATING NUMBERS
RDXSV_GFLOAT = 6 ;INDEX FOR G FLOATING NUMBERS
RDXSV_HFLOAT = 7 ;INDEX FOR H FLOATING NUMBERS
LSTSK_L_P_PAGE = 60 ;LINES PER PAGE IN LISTING
STBSK_PG_MISS = 10 ;# PAGES TO ALLOCATE FOR EMPTY SYMBOL BUCKET
SYMSK_MAXLEN = 31 ;Maximum characters/symbol
SYMSK_TWOCOL = 16 ;Character size for 2 column symbol table
CHRSM_SPA_MSK = ^X01 ;BIT MASK FOR SPACE-LIKE CHARACTER
CHRSV_SPA_MSK = 0 ;BIT NUMBER FOR SPACE-LIKE CHAR
CHRSM_SYM_DLM = ^X02 ;BIT MASK FOR SYMBOL DELIMITER CHARACTER
CHRSV_SYM_DLM = 1 ;BIT NUMBER FOR SYMBOL DELIM.
CHRSM_SYM_CHR = ^X04 ;BIT MASK FOR CHAR THAT CAN START SYMBOL
CHRSV_SYM_CHR = 2 ;BIT NUMBER FOR SYMBOL CHAR
CHRSM_SYM_CH1 = ^X08 ;BIT MASK FOR CHAR THAT CAN BE IN SYMBOL
CHRSV_SYM_CH1 = 3 ;BIT NUMBER FOR SYMBOL CHAR
CHRSM_NUM_BER = ^X10 ;BIT MASK FOR NUMBER
CHRSV_NUM_BER = 4 ;BIT NUMBER FOR NUMBER
CHRSM_COMMA_CR = ^X20 ;BIT MASK FOR COMMA AND CR
CHRSV_COMMA_CR = 5 ;BIT NUMBER FOR COMMA AND CR
CHRSM_ILL_CHR = ^X40 ;BIT MASK FOR ILLEGAL CHARACTER
CHRSV_ILL_CHR = 6 ;BIT NUMBER FOR ILLEGAL CHARACTER
ARGSK_SIZE = 1000 ;Maximum characters in MACRO argument
AUDSK_SIZE = 16 ;Audit trail string size

```

```

.MDELETE $MAC_GENVALDEF
.ENDM $MAC_GENVALDEF

```

SMAC_MTXDEF

DEFINES THE MACRO TEXT SPECIAL MARKERS USED DURING MACRO AND REPEAT/IRP PROCESSING.

.MACRO SMAC_MTXDEF

MTXS_ARGMRK	=	^XFF	:ARG NO. FOLLOWS (BYTE)
MTXS_TXTLNK	=	^XFE	:LONGWORD OF LINK FOLLOWS
MTXS_LXLEN	=	^XFD	:LEXICAL OPERATOR--LENGTH
MTXS_LXEXT	=	^XFC	:LEXICAL OPERATOR--EXTRACT
MTXS_LXLOC	=	^XFB	:LEXICAL OPERATOR--LOCATE
.		^XFA TO ^XFO	RESERVED
MTXS_LITSTR	=	^XEF	:LITERAL STRING FOLLOWS
MTXS_LITVAL	=	^XEE	:LITERAL VALUE FOLLOWS
MTXS_SYMADR	=	^XED	:SYMBOL ADDRESS FOLLOWS
MTXS_NOMORE	=	^XEC	:NO MORE ARGUMENTS

.ENDM SMAC_MTXDEF

++

MTXS_ARGMRK	FOLLOWED BY A BYTE CONTAINING THE ARGUMENT NUMBER
MTXS_TXTLNK	FOLLOWED BY A LONGWORD OF ADDRESS (TEXT LINK)
MTXS_LITSTR	FOLLOWED BY WORD OF COUNT, THEN ASCII STRING
MTXS_LITVAL	FOLLOWED BY LONGWORD OF VALUE
MTXS_SYMADR	FOLLOWED BY LONGWORD OF SYMBOL ADDRESS

--

++

S

E

T

.SBTTL DEFINE MACRO LIBRARY FILE OFFSETS

.MACRO \$MAC_MLFDEF

\$NAMDEF

.PSECT \$ABSS,ABS

```

.=0
MLFSK_RSFLN    = NAMSC_MAXRSS ; Resultant file name length
MLFSL_QLINK:   .BLKL 2        ; QUEUE LINK WORDS
MLFSL_MCDEF:   .BLKL 1        ; # MACROS DEFINED IN THIS MLB
                                   ; (I.E. IMCALL'S SATISFIED HERE)
MLFSQ_FNAMDS:  .BLKQ 1        ; File name descriptor
MLFSL_CTINDEX: .BLKL 1        ; Control table index
MLFSX_NAMBLK:  .BLKB NAMSC_BLN ; NAM block
MLFST_FNAM:    .BLKB MLFSK_RSFLN ; File name string
MLFSK_BLKSIK:

```

```

.MDELETE $MAC_MLFDEF
.ENDM $MAC_MLFDEF

```

```

:++
:F
:--

```

++
: EACH OPCODE SYMBOL BLOCK IS FOLLOWED BY A SERIES OF WORDS WHICH
: DESCRIBE THE OPERANDS FOR THE OPCODE. THE FOLLOWING MACRO DEFINES
: THOSE WORD DESCRIPTORS.
:--

.MACRO \$MAC_OPRDEF

OPD\$S_SIZE = 5 ;SIZE OF BYTES FIELD
OPD\$V_SIZE = 0 ;POSITION OF BYTES FIELD
OPD\$S_MODE = 5 ;SIZE OF ACCESS MODE FIELD
OPD\$V_MODE = 5 ;POSITION OF ACCESS MODE FIELD
OPD\$M_MODE = 1@OPD\$S_MODE-1@OPD\$V_MODE ;Mask to isolate mode value
OPD\$M_ADDR = 0@<OPD\$V_MODE> ;ADDRESS ACCESS MODE
OPD\$M_READ = 1@<OPD\$V_MODE> ;READ ACCESS MODE
OPD\$M_MODIFY = 2@<OPD\$V_MODE> ;MODIFY ACCESS MODE
OPD\$M_WRITE = 3@<OPD\$V_MODE> ;WRITE ACCESS MODE
OPD\$M_VIELD = 4@<OPD\$V_MODE> ;FIELD ACCESS
OPD\$M_BB = 5@<OPD\$V_MODE>+1 ;BRANCH BYTE
OPD\$M_BW = 6@<OPD\$V_MODE>+2 ;BRANCH WORD
OPD\$M_FLOAT = ^X8000 ;FLOATING POINT (MUST BE SIGN BIT)
OPD\$V_FLOAT = 15 ;BIT NUMBER FOR FLT. PT.
OPD\$M_D_FLOAT = OPD\$M_FLOAT+^X4000 ;D-FLOATING
OPD\$V_D_FLOAT = 14 ;BIT NUMBER FOR D-FLOATING
OPD\$M_G_FLOAT = OPD\$M_FLOAT+^X2000 ;G-FLOATING
OPD\$V_G_FLOAT = 13 ;BIT NUMBER FOR G-FLOATING
OPD\$M_H_FLOAT = OPD\$M_FLOAT+^X1000 ;H-FLOATING
OPD\$V_H_FLOAT = 12 ;BIT NUMBER FOR H-FLOATING
OPD\$M_NOT_32F = ^X4000+^X2000+^X1000 ;NOT SINGLE PREC. IF THIS SET

B = 1 ;BYTE
W = 2 ;WORD
L = 4 ;LONGWORD
F = 4+OPD\$M_FLOAT ;FLOATING
Q = 8 ;QUADWORD
D = 8+OPD\$M_D_FLOAT ;DOUBLE FLOATING
G = 8+OPD\$M_G_FLOAT ;G-FLOATING
O = 16 ;OCTA-WORD
H = 16+OPD\$M_H_FLOAT ;H-FLOATING

AB=OPD\$M_ADDR+B
AW=OPD\$M_ADDR+W
AL=OPD\$M_ADDR+L
AF=OPD\$M_ADDR+F
AD=OPD\$M_ADDR+D
AQ=OPD\$M_ADDR+Q
AG=OPD\$M_ADDR+G
AO=OPD\$M_ADDR+O
AH=OPD\$M_ADDR+H
RB=OPD\$M_READ+B
RW=OPD\$M_READ+W
RL=OPD\$M_READ+L
RF=OPD\$M_READ+F
RD=OPD\$M_READ+D
RQ=OPD\$M_READ+Q
RG=OPD\$M_READ+G
RO=OPD\$M_READ+O
RH=OPD\$M_READ+H
MB=OPD\$M_MODIFY+B
MW=OPD\$M_MODIFY+W

ML=OPDSM_MODIFY+L
MF=OPDSM_MODIFY+F
MD=OPDSM_MODIFY+D
MQ=OPDSM_MODIFY+Q
MG=OPDSM_MODIFY+G
MO=OPDSM_MODIFY+O
MH=OPDSM_MODIFY+H
WB=OPDSM_WRITE+B
WW=OPDSM_WRITE+W
WL=OPDSM_WRITE+L
WF=OPDSM_WRITE+F
WD=OPDSM_WRITE+D
WQ=OPDSM_WRITE+Q
WG=OPDSM_WRITE+G
WO=OPDSM_WRITE+O
WH=OPDSM_WRITE+H
VB=OPDSM_VFIELD+B
VW=OPDSM_VFIELD+W
VL=OPDSM_VFIELD+L
VF=OPDSM_VFIELD+F
VD=OPDSM_VFIELD+D
VQ=OPDSM_VFIELD+Q
VG=OPDSM_VFIELD+G
VO=OPDSM_VFIELD+O
VH=OPDSM_VFIELD+H

.ENDM \$MAC_OPRDEF

.SB
.MA
.IF
MOV
.EN
BSB
.EN
.SB
.MA
MOV
BSB

THIS MACRO DEFINE, THE TERMINAL GRAMMAR SYMBOLS IN THE VAX-11 MACRO GRAMMAR

.MACRO \$MAC_GRAMMARDEF

ERR01	=	1.
ERR02	=	2.
ERR03	=	3.
ERR04	=	4.
ERR05	=	5.
ERR06	=	6.
ERR07	=	7.
ERR08	=	8.
ERR09	=	9.
GOALSY	=	10.
DEOL	=	11.
ID	=	12.
MACTXT	=	13.
DOPCODE	=	14.
DCOMMA	=	15.
DCOLON	=	16.
DEQ	=	17.
DPC	=	18.
DSQOPN	=	19.
DSQCLS	=	20.
DANGOPN	=	21.
DANGCLS	=	22.
DOPN	=	23.
DCLS	=	24.
DPLUS	=	25.
DMINUS	=	26.
DTIMES	=	27.
DDIV	=	28.
DAND	=	29.
DOR	=	30.
DXOR	=	31.
DAT	=	32.
DPOUND	=	33.
DINTEGER	=	34.
DUPA	=	35.
DUPB	=	36.
DUPC	=	37.
DUPD	=	38.
DUPO	=	39.
DUPF	=	40.
DUPM	=	41.
DUPX	=	42.
DBUP	=	43.
DGUP	=	44.
DIUP	=	45.
DLUP	=	46.
DSUP	=	47.
DWUP	=	48.
RRREG	=	49.
DMASK	=	50.
KASCIC	=	51.
KASCII	=	52.
KASCIZ	=	53.
KPACKED	=	54.

.EN
 .SB
 .MA
 .IF
 .MOV
 .EN
 .BSB
 .EN

KEND	=	118.
KXFER	=	119.
KASCID	=	120.
KCROSS	=	121.
KNCROS	=	122.
KDFLT	=	123.
KSGNB	=	124.
KSGNW	=	125.
KBLKG	=	126.
KBLKH	=	127.
KBLKO	=	128.
KGFLOAT	=	129.
KHFLOAT	=	130.
KOCTA	=	131.
KREF16	=	132.
KLINK	=	133.

```

.MDELETE $MAC_GRAMMARDEF
.ENDM $MAC_GRAMMARDEF

```

THIS MACRO DEFINES THE BIT FLAGS THAT LIVE IN THE FLAGS WORD 'MAC\$FLAGS'. A 0 IN A BIT POSITION INDICATES FALSE AND A 1 INDICATES TRUE.

```
.MACRO $MAC_CTLFLGDEF
.MACRO $FLG_DEFINE F
FLGSV 'F' = XT
FLGSM 'F' = X2
X1 = X1 + 1
X2 = X2 @ 1
.ENDM $FLG_DEFINE
```

X1=0
X2=1

\$FLG_DEFINE	ALLCHR	:TRUE INDICATES: :MAC\$GETCHR SHOULD PASS SEMICOLONS :(ALLCHR MUST BE LOW BIT!!!)
\$FLG_DEFINE	BOL	:OPCODE NOT YET FOUND
\$FLG_DEFINE	COMEXPR	:EXPRESSION IS COMPILE TIME
\$FLG_DEFINE	CONT	:ALLOW LINE CONTINUATIONS
\$FLG_DEFINE	DATRPT	:REPEATING DATA DEFINITION
\$FLG_DEFINE	ENDMCH	:CHECK MACRO DIRECTIVES
\$FLG_DEFINE	EVAEXPR	:EXPR TO BE EVAL ON PASS 2
\$FLG_DEFINE	EXPOPT	:EXPRESSION CAN BE OPTIMIZED
\$FLG_DEFINE	INSERT	:INSERT SYMBOL IF NOT FOUND
\$FLG_DEFINE	LSTXST	:LISTING FILE EXISTS
\$FLG_DEFINE	NEWPND	:NEW PAGE PENDING
\$FLG_DEFINE	MACL	:MACRO TEXT LINE PRESENT
\$FLG_DEFINE	MEBLST	:SPECIAL LIST MEB FLAG
\$FLG_DEFINE	OPRND	:SCANNING OPERAND FIELD
\$FLG_DEFINE	P2	:IN PASS 2
\$FLG_DEFINE	SKAN	:ALLOW SCANNING
\$FLG_DEFINE	MACTXT	:READING FROM MACRO TEXT :(FALSE INDICATES READING SOURCE FILE)
\$FLG_DEFINE	ORDLST	:SYMBOL TABLE LIST IS ORDERED :(OPCODES ARE NOT ORDERED IN BUCKETS)
\$FLG_DEFINE	STOIMF	:STORING IMMEDIATE DATA (MAC\$STOIM)
\$FLG_DEFINE	TOCFLG	:PAGE HEADER FOR SUBTITLES NOT NEEDED
\$FLG_DEFINE	CHKLPND	:THERE IS A CHKL PENDING FROM A CONTINUED LINE
\$FLG_DEFINE	OBJXST	:THERE IS AN OBJECT FILE
\$FLG_DEFINE	IIF	:THIS IS .IIF AS OPPOSED TO .IF
\$FLG_DEFINE	IFSTAT	:THIS IS AN IF STATEMENT
\$FLG_DEFINE	NOREF	:DO NOT SET REF WHEN SYMBOL IS FOUND :(USED ONLY BY .NTYPE NOW)
\$FLG_DEFINE	SEQFIL	:INPUT FILE HAS SEQUENCE NUMBERS
\$FLG_DEFINE	SPLALL	:SPECIAL PASS ALL CHARACTERS FOR :READING CERTAIN DIRECTIVES WHILE :DEFINING MACROS
\$FLG_DEFINE	MACLTB	:THERE IS MACRO TEXT IN BUFFER (P2)
\$FLG_DEFINE	RPTIRP	:IN AN IRP OR REPEAT (PASS 1)
\$FLG_DEFINE	IRPC	:IRPC AS OPPOSED TO IRP
\$FLG_DEFINE	CRF	:/CROSS REQUESTED
\$FLG_DEFINE	XCRF	:.NOCROSS IN EFFECT
X2=1		:**INTO SECOND FLAGS WORD!!
\$FLG_DEFINE	CRSEEN	:FLAG FOR TOKEN THAT CR WAS SEEN ONCE.
\$FLG_DEFINE	LEXOP	:ARGSCN CALLED FOR LEXICAL OPERATOR
\$FLG_DEFINE	SPECOP	:SPECIAL OPERATOR OUTPUT FOR LINE (MAC\$BDYSCN)

```

$FLG_DEFINE MOREINP      ;MORE INPUT FILES COMING
$FLG_DEFINE UPAFLG      ;SET WHEN ^A/text/ SEEN
$FLG_DEFINE NTYPEPC    ; Suppress PC check for .NTYPE
$FLG_DEFINE UPMARG     ; Set to get Macro argument upper cased
$FLG_DEFINE UPDFIL     ; Input file is being updated
$FLG_DEFINE OPNDCHK    ; Operand check performed
$FLG_DEFINE FIRSTLN   ; First listing line
$FLG_DEFINE SYM2COL   ; Two column symbol table listing
$FLG_DEFINE MAC2COL   ; Two column macro listing
$FLG_DEFINE OPTVFLIDX ; Optimized ref. will ovFL if indexed
$FLG_DEFINE MOREARG   ; Previous argument had trailing comma
$FLG_DEFINE DBGOUT    ; Output debugger records for abs psectss
$FLG_DEFINE DLIMSTR   ; Pass ALL characters in delimited .ASCIX strings
$FLG_DEFINE EXTERR    ; An external (non-assembly) error has occurred.
$FLG_DEFINE EXTWRN    ; An external (non-assembly) warning has occurred.
$FLG_DEFINE NULCHR    ; Null character as a parameter

```

MAC9
V04-

6C 6

...
: FLAGS IN MAC\$GL_OPSIZE
...

```

OPFSM_LASTOPR = ^X2000 ;LAST OPERAND IN OPCODE
OPFSV_LASTOPR = 13
OPFSM_OPTEXP = ^X1000 ;EXPRESSION HAS BEEN OPTIMIZED
OPFSV_OPTEXP = 12

```

```

.MDELETE $MAC_CTLFLGDEF, $FLG_DEFINE
.ENDM $MAC_CTLFLGDEF

```

.SBTTL CRF_FLG FLAG BITS

.MACRO \$MAC_CRFLAGDEF

CRFSM_DIR	=	1	:CREF DIRECTIVES
CRFSV_DIR	=	0	
CRFSM_MACROS	=	2	:CREF MACROS
CRFSV_MACROS	=	1	
CRFSM_OPCODES	=	4	:CREF OPCODES
CRFSV_OPCODES	=	2	
CRFSM_REGISTERS	=	8	:CREF REGISTERS
CRFSV_REGISTERS	=	3	
CRFSM_SYMBOLS	=	16	:CREF SYMBOLS
CRFSV_SYMBOLS	=	4	
CRFSM_DEFAULT	=	CRFSM_MACROS!CRFSM_SYMBOLS	

.ENDM \$MAC_CRFLAGDEF

MACR
Symb
MACR
PSEC

: A
: BL
Phas

Init
Comm
Pass
Symb
Pass
Symb
Psec
Cros
Asse
The
631
Ther
66 s
0 pa
Macr

-\$25
-\$25
TOTAL
0 GE
Ther
MACR

.SBTTL ADDRESSING MODE DEFINITIONS

:+
:--
THIS MACRO DEFINES THE ADDRESSING MODES.

.MACRO \$MAC_ADRMODDEF
X=0
.MACRO COD SYM
ADMS 'SYM=X
X=X+1
.ENDM

COD	LITERAL	:LITERAL MODE
COD	IMMEDIATE	:IMMEDIATE MODE
COD	ABSOLUTE	:ABSOLUTE
COD	PIC	:PIC
COD	INDEX	:E[R]
COD	REGISTER	:R
COD	RRIND	:(R)
COD	REGAUTODEC	:(R)-
COD	REGAUTOINC	:(R)+
COD	DFRAUTOINC	:@R+
COD	BYTE_DISP	:B^D(R)
COD	DFBYTEDISP	:@B^D(R)
COD	WORD_DISP	:W^D(R)
COD	DFWORDDISP	:@W^D(R)
COD	LONG_DISP	:L^D(R)
COD	DFLONGDISP	:@L^D(R)
	ADMS_MAXMOD	= X-1 ;MAX. ALLOWABLE MODE

.MDELETE \$MAC_ADDRMODDEF, COD
.ENDM \$MAC_ADRMODDEF

```

**
PASS 1 OF THE ASSEMBLER GENERATES AN INTERMEDIATE CODE FILE
WHICH IS PROCESSED BY PASS 2 TO PRODUCE THE OBJECT FILE.
THE INTERMEDIATE CODE HAS THE FOLLOWING FORMAT:

```

```

*****
*   LENGTH   *           LENGTH IN BYTES OF THIS FRAME
*****       *           1 BYTE
*   ACTION   *           ACTION TO PERFORM (SEE CODES BELOW)
*****       *           1 BYTE
*           *
*   DATA    *           DATA ASSOCIATED WITH FRAME
*           *
*****       *           VARIABLE LENGTH

```

```

THE MACRO BELOW DEFINES THE ACTION CODES, AND GENERATES A BRANCH TABLE.
THIS MACRO SHOULD BE INVOKED WITH NO ARGUMENT TO DEFINE THE
SYMBOLS 'INT$ SYMBOL', AND INVOKED WITH THE ARGUMENT
'DISPACTHABLE' TO GENERATE THE PASS2 DISPATCH TABLE.

```

```

.MACRO $MAC_INTCODDEF TYPE

```

```

$COUNT = 0

```

```

.IF DIF <TYPE>,<DISPACTHABLE>

```

```

.MACRO INT SYM
INT$ SYM = $COUNT
$COUNT = $COUNT + 1
.ENDM

```

```

.IFF

```

```

.MACRO INT SYM
.LONG P2$ SYM
$COUNT=$COUNT+1
.ENDM

```

```

.ENDC

```

```

INT   ILG   :ILLEGAL INTERMEDIATE CODE (0)
;***BELOW SYMBOLS ARE ARITHMETIC OPERATORS***POSITION MUST NOT CHANGE
INT   ADD   :ADD TOP TWO ITEMS ON STACK
INT   AND   :LOGICAL AND
INT   ASH   :ASH
INT   DIV   :DIVIDE
INT   MUL   :MULTIPLY
INT   NEG   :NEGATE
INT   NOT   :LOGICAL NOT
INT   OR    :LOGICAL OR
INT   SAME  :UNARY PLUS
INT   SUB   :SUBTRACT
INT   XOR   :EXCLUSIVE OR
;***ABOVE SYMBOLS ARE ARITHMETIC OPERATORS***POSITION MUST NOT CHANGE
INT   ASN   :ASSIGNMENT
INT   AUGPC :AUGMENT PC

```



```

INT  BDST      :GENERATE BRANCH DESTINATION
INT  CHKL      :ALIGN OUTPUT WITH SOURCE LINES
INT  END       :END OF INTERMEDIATE CODE
INT  EPT       :ENTRY POINT DEFINITION
INT  ERR       :PASS 1 ERROR MESSAGE
INT  ETX       :ERROR TEXT FOR .ERROR/.WARN/.PRINT
INT  FNEWL     :FORCE NEW LISTING LINE
INT  LGLAB     :STANDARD (NOT LOCAL) LABEL
INT  MACL      :MACRO TEXT LINE
INT  NEWL      :NEW LINE OF SOURCE TEXT
INT  NEWP      :DEFINE NEW PSECT
INT  OP        :GENERATE OPCODE
INT  PRIL      :PRINT LONG WORD IN LISTING
INT  PRT       :PASS 1 PRINT DIRECTIVE
INT  PSECT     :CHANGE PSECT
INT  REDEF     :.TRANSFER DIRECTIVE
INT  REF       :GENERATE REFERENCE
INT  REST      :RESTORE PSECT
INT  SAVE      :SAVE PSECT
INT  SBTTL     :SUBTITLE
INT  SETFLAG   :SET FLAG IN MAC$GL FLAGS
INT  SETLONG   :STORE LONGWORD VALUE
INT  SPIC      :STORE POSITION INDEPENDENT (NOT USED AT PRESENT)
INT  SPID      :STORE ADDRESS
INT  STIB      :STORE IMMEDIATE BYTE
INT  STIW      :STORE IMMEDIATE WORD
INT  STIL      :STORE IMMEDIATE LONGWORD
INT  STKEPT    :STACK ENTRY POINT
INT  STKG      :STACK GLOBAL SYMBOL
INT  STKL      :STACK LITERAL VALUE
INT  STKPC     :STACK CURRENT PC
INT  STKS      :STACK SYMBOL
INT  STOL      :STORE LONG WORD
INT  STRB      :STORE REPEATED BYTE
INT  STRW      :STORE REPEATED WORD
INT  STRL      :STORE REPEATED LONG
INT  STRSB     :STORE REPEATED SIGNED BYTE
INT  STRSW     :STORE REPEATED SIGNED WORD
INT  STOB      :STORE BYTE
INT  STOW      :STORE WORD
INT  STSB      :STORE SIGNED BYTE
INT  STSW      :STORE SIGNED WORD
INT  WRN       :PASS 1 WARNING MESSAGE
INT  SUME      :Source-update-merge error
INT  INFO      :Information message

.MDELETE      $MAC_INTCODDEF, INT
.ENDM $MAC_INTCODDEF

```

THESE SYMBOLS AND FLAG DEFINITIONS ARE SUPPLIMENTAL TO THOSE DEFINED
BY \$OBJDEF AND ARE USED BY THE PASS 2 ACTION ROUTINES.

.MACRO \$MAC_OBJCODDEF

\$OBJDEF ; DEFINE THE OBJECT CODE.

SYMBOL DEFINITION MASK BITS

SYMSF_WEAK	=	^0001	:	WEAK RESOLUTION
SYMSF_DEF	=	^0002	:	DEFINITION
SYMSF_UNI	=	^0004	:	UNIVERSAL
SYMSF_REL	=	^0010	:	RELATIVE
SYMSF_VALIDATE	=	^0020	:	VALIDATE

END OF MODULE RECORD STATUS

OBJSC_EOM_OK	=	EOMSC_SUCCESS	:	NO ERRORS
OBJSC_EOM_WRN	=	EOMSC_WARNING	:	WARNINGS
OBJSC_EOM_ERR	=	EOMSC_ERROR	:	SERIOUS ERRORS
OBJSC_EOM_ABORT	=	EOMSC_ABORT	:	ABORT LINK

TEXT, INFORMATION AND RELOCATION

TIRSC_STO_LW = TIRSC_STO_L ; STORE LONG WORD DATUM

.MDELETE \$MAC_OBJCODDEF
.ENDM \$MAC_OBJCODDEF

++
: FUNCTIONAL DESCRIPTION:
:--

THIS MACRO, \$INTOUT_X, IS USED WHEN THERE IS NEED TO ONLY
PUT AN ACTION INTO THE INTERMEDIATE FILE. FOR EXAMPLE,
INT\$_CHKL, THE ALIGN SOURCE DIRECTIVE, TAKES NO ARGUMENTS.

```
.MACRO $INTOUT_X      ACTN
MOVZBL #ACTN,R0
BSBW   MAC$INTOUT_X
.ENDM
```

```
.MACRO $INTOUT_LW      ACTN,DATA
INTOUTC2 DATA
MOVZBL #ACTN,R0
ERR=0
.IF IDN <ACTN>,<INT$ERR>
ERR=1
.ENDC
.IF IDN <ACTN>,<INT$WRN>
ERR=1
.ENDC
INT_LW_CALL \CNT
.ENDM
```

```
.MACRO INTOUTC2 D1,D2,D3
.NARG CNT
.IF NB D3
PUSHL D3
.ENDC
.IF NB D2
PUSHL D2
.ENDC
.IF NB D1
PUSHL D1
.ENDC
.ENDM
```

```
.MACRO INT_LW_CALL C
.IF EQ ERR
BSBW MAC$INTOUT_'C'_LW
.IFF
BSBW MAC$INTERR_'C'_LW
.ENDC
.ENDM
```

```
.MACRO $INTOUT_WD      ACTN,DATA
MOVZBL #ACTN,R0
MOVZWL DATA,R1
BSBW MAC$INTOUT_WD
.ENDM
```

```
.SBTTL PUSH/POP ON VALUE STACK
```

```
THESE TWO MACROS ARE USED TO PUSH AND POP FROM THE  
PARSER VALUE STACK.
```

```
.MACRO $VPUSH LOC  
INCL R7  
MOVL LOC,W^MAC$AL_VALSTACK[R7]  
.ENDM $VPUSH
```

```
.MACRO $VPOP LOC  
MOVL W^MAC$AL_VALSTACK[R7],LOC  
DECL R7  
.ENDM $VPOP
```

```
.SBTTL ADJUST PC
```

```
.MACRO $INC_PC CNT  
.IF B CNT  
INCL W^MAC$GL_PC  
.IFF  
ADDL2 CNT,W^MAC$GL_PC  
.ENDC  
.ENDM $INC_PC
```

```
.MACRO $DEC_PC CNT  
.IF B CNT  
DECL W^MAC$GL_PC  
.IFF  
SUBL2 CNT,W^MAC$GL_PC  
.ENDC  
.ENDM
```

```
.SBTTL OUTPUT BYTE TO OBJECT CODE
```

```
.MACRO $OBJ_LJTBYT BYT  
.IF DIF <BYTS>,<R0>  
MOVB BYT,R0  
.ENDC  
BSBW MAC$OUTOBJ  
.ENDM $OBJ_OUTBYT
```

```
.MACRO $OBJ_OUTBYT_0 BYT  
MOVB BYT,(R10)+  
.ENDM $OBJ_OUTBYT_0
```

```
.SBTTL OUTPUT BYTE TO OBJECT CODE, CHECKING FOR BUFFER OVERFLOW
```

```
.MACRO $OBJ_CHKBYT BYT  
.IF DIF <BYTS>,<R0>  
MOVB BYT,R0  
.ENDC  
BSBW MAC$CHKBYT  
.ENDM $OBJ_CHKBYT
```

```
.SBTTL SIGNAL PASS 2 ERROR
```

```
.MACRO $MAC_P2_ERR MSGNAM  
MOVZWL #<MAC$^MSGNAM&^XFFFF>,R0  
BSBW MAC$PASS_2_ERR
```

```
.ENDM $MAC_P2_ERR

.SBTTL OUTPUT BYTES TO LISTING FILE

.MACRO $MAC_LIST_BYTE N
  .IF DIF <N>,ZRO>
  MOVZBL N,R0
  .ENDC
  BSBW MACSLIST_BYTES
  .ENDM $MAC_LIST_BYTE

  .SBTTL SET MACRO ERROR CODE

  .MACRO $MAC_ERR_CODE
  MOVZWL #<MACS 'CODE&^XFFFF>,R0
  .ENDM $MAC_ERR
```

.SBTTL \$MAC_INSERT_SYM MACRO TO PLACE SYMBOLS IN LINKED LIST ^{1 6}

MAC
V04

♦♦
\$MAC_INSERT_SYM -- PLACE SYMBOLS IN ONE LINKED LIST

MACRO TO PLACE SYMBOLS IN ONE LINKED LIST. THIS MACRO IS
USED WHEN ONLY A SINGLE LINKED LIST INSTEAD OF A HASH TABLE
IS USED. THE SYMBOL 'INSYMP' IS THE LINK POINTER, AND
IT SHOULD BE ZEROED BEFORE THE LIST IS CREATED.
--

```
.MACRO $MAC_INSERT_SYM NAM,VL1,FLAG=0,HEAD      ;NAME, VALUE, FLAG, HEAD
.ASCIC /NAM7
.IF NOT_BLANK <HEAD>, HEAD::
INSYTM=.
.LONG INSYMP
INSYMP = INSYTM
.NCHR INSYMC,<NAM>
.BYTE INSYMC+1
.LONG VL1                ;VALUE
.WORD FLAG                ;FLAGS
.BYTE 0                   ;TOKEN
.BYTE 0                   ;SEGMENT
.ENDM $MAC_INSERT_SYM

.MACRO $MAC_INSERT_SYX NAM,VAL,HEAD            ;NAME, VALUE, HEAD
.ASCIC /NAM7
.IF NOT_BLANK <HEAD>, HEAD::
INSYTM=.
.LONG INSYMP
INSYMP = INSYTM
.NCHR INSYMC,<NAM>
.BYTE INSYMC+1
.LONG VAL
.ENDM $MAC_INSERT_SYX

.LIST
.END
```


The image displays a grid of 100 small terminal window screenshots, arranged in a 10x10 grid. Each window shows a different VAX/VMS command and its output. The windows are arranged in a grid, with some windows clearly legible and labeled with their command names. The labels are as follows:

- DATA LIS (top-left)
- DEFINE LIS (middle-left)
- FLOAT LIS (middle-right)
- ERRMSG LIS (lower-middle)
- GETARG LIS (lower-right)
- DATA LIS (bottom-left)
- INPUT LIS (bottom-right)
- ERROR LIS (bottom-center)
- FINISH LIS (bottom-center)
- GETCMD LIS (bottom-center)

The other windows in the grid show various system outputs, including file listings, directory structures, and command execution results. The text is small and dense, typical of a terminal window output.