



```
MM      MM  TTTTTTTTTT  HH      HH      AAAAAA  TTTTTTTTTT  AAAAAA  NN      NN
MM      MM  TTTTTTTTTT  HH      HH      AAAAAA  TTTTTTTTTT  AAAAAA  NN      NN
MMM     MMM  TT          HH      HH      AA      AA  TT          AA      AA  NN      NN
MMM     MMM  TT          HH      HH      AA      AA  TT          AA      AA  NN      NN
MM      MM  TT          HH      HH      AA      AA  TT          AA      AA  NNNN     NN
MM      MM  TT          HH      HH      AA      AA  TT          AA      AA  NNNN     NN
MM      MM  TT          HHHHHHHHHH  AA      AA  TT          AA      AA  NN      NN
MM      MM  TT          HHHHHHHHHH  AA      AA  TT          AA      AA  NN      NN
MM      MM  TT          HH      HH      AAAAAAAAAA  TT          AAAAAAAAAA  NN      NNNN
MM      MM  TT          HH      HH      AAAAAAAAAA  TT          AAAAAAAAAA  NN      NNNN
MM      MM  TT          HH      HH      AA      AA  TT          AA      AA  NN      NN
MM      MM  TT          HH      HH      AA      AA  TT          AA      AA  NN      NN
MM      MM  TT          HH      HH      AA      AA  TT          AA      AA  NN      NN
MM      MM  TT          HH      HH      AA      AA  TT          AA      AA  NN      NN
MM      MM  TT          HH      HH      AA      AA  TT          AA      AA  NN      NN
MM      MM  TT          HH      HH      AA      AA  TT          AA      AA  NN      NN
```

....  
....  
....  
....

```
LL      I I I I I  SSSSSSSS
LL      I I I I I  SSSSSSSS
LL      I          SS
LL      I          SS
LL      I          SS
LL      I          SS
LL      I          SSSSSS
LL      I          SSSSSS
LL      I          SS
LL      I          SS
LL      I          SS
LL      I          SS
LL      I          SS
LL      I I I I I  SSSSSSSS
LLLLLLLLLLLL I I I I I  SSSSSSSS
LLLLLLLLLLLL I I I I I  SSSSSSSS
```

(2)	73
(3)	105
(6)	342
(7)	412
(8)	506
(9)	657
(10)	727
(11)	822

HISTORY : Detailed Current Edit History  
DECLARATIONS : Declarative Part of Module  
MTHSATAN - Standard Single Precision Floating Arc Tangent  
MTHSATAN2 - Standard floating Arctangent With 2 Arguments  
MTHSATAN\_R4 - Special ATAN routine  
MTHSATAND - Standard Single Precision Floating Arc Tangent  
MTHSATAND2 - Standard floating Arctangent With 2 Arguments  
MTHSATAND\_R4 - Special ATAN routine

```
0000 1      .TITLE  MTHSATAN      ; Floating Point Arc Tangent Functions
0000 2      ; (ATAN,ATAN2,ATAND,ATAND2)
0000 3      .IDENT  /2-005/      ; File: MTHATAN.MAR  EDIT:  RNH2005
0000 4
0000 5      *****
0000 6      *
0000 7      *  COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
0000 8      *  DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
0000 9      *  ALL RIGHTS RESERVED.
0000 10     *
0000 11     *  THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
0000 12     *  ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
0000 13     *  INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
0000 14     *  COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
0000 15     *  OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
0000 16     *  TRANSFERRED.
0000 17     *
0000 18     *  THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
0000 19     *  AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
0000 20     *  CORPORATION.
0000 21     *
0000 22     *  DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
0000 23     *  SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
0000 24     *
0000 25     *
0000 26     *  *****
0000 27     *
0000 28     *
0000 29     *  FACILITY: MATH LIBRARY
0000 30     *  +-
0000 31     *  ABSTRACT:
0000 32     *
0000 33     *  MTHSATAN is a function which returns the floating point arc tangent
0000 34     *  value (in radians) of its single precision floating point argument.
0000 35     *  MTHSATAN2 is two arguments floating point arctangent. The call is
0000 36     *  standard call-by-reference.
0000 37     *  MTHSATAN_R4 is a special routine which is the same as MTHSATAN
0000 38     *  except a faster non-standard JSB call is used with the argument in
0000 39     *  R0 and no registers are saved.
0000 40     *
0000 41     *  MTHSATAND is a function which returns the floating point arc tangent
0000 42     *  value (in degrees) of its single precision floating point argument.
0000 43     *  MTHSATAND2 is two arguments floating point arctangent. The call is
0000 44     *  standard call-by-reference.
0000 45     *  MTHSATAND_R4 is a special routine which is the same as MTHSATAND
0000 46     *  except a faster non-standard JSB call is used with the argument in
0000 47     *  R0 and no registers are saved.
0000 48     *
0000 49     *  --
0000 50     *
0000 51     *  VERSION: 01
0000 52     *
0000 53     *  HISTORY:
0000 54     *  AUTHOR:
0000 55     *  Peter Yuo, 15-Oct-76: Version 01
0000 56     *
0000 57     *  MODIFIED BY:
```

```
0000 58 :  
0000 59 : 01-1 Peter Yuo, 22-May-77  
0000 60 :  
0000 61 : --  
0000 62 :  
0000 63 : VERSION: 02  
0000 64 :  
0000 65 : HISTORY:  
0000 66 : AUTHOR:  
0000 67 :     Bob Hanek, 04-Jun-81: Version 02  
0000 68 :  
0000 69 : MODIFIED BY:  
0000 70 :  
0000 71 :
```

```

0000 73      .SBTTL HISTORY - Detailed Current Edit History
0000 74
0000 75
0000 76 : ALGORITHMIC DIFFERENCES FROM FP-11/C ROUTINE:
0000 77 :     1. To avoid various flags subroutine calls have been used.
0000 78 :
0000 79 : Edit History for Version 01 of MTH$ATANATAN2
0000 80 :
0000 81 : 01-1 Code saving from code review March 1977
0000 82 :     Add jacket routine to MTH$ATAN2
0000 83 :     Use proper form of literals so MTH$ATAN2 will work
0000 84 :
0000 85 : 01-5 Signal (0, 0) as INVALID ARG TO MATH LIBRARY.  TNH 16-June-78
0000 86 : 01-6 Move .ENTRY mask definition to module header.  TNH 14-Aug-78
0000 87 : 1-007 - Update version number and copyright notice.  JBS 16-NOV-78
0000 88 : 1-008 - Change symbol MTH_INVARG to MTH$K_INVARGMAT.  JBS 07-DEC-78
0000 89 : 1-009 - Add " " to the PSECT directive.  JBS 21-DEC-78
0000 90 : 1-010 - Define all global symbols using .EXTRN.  JBS 19-JUN-1979
0000 91 : 1-011 - Added degree entry points.  RNH 15-MAR-1981
0000 92 :
0000 93 :
0000 94 : Edit History for Version 02 of MTH$ATANATAN2
0000 95 :
0000 96 : --
0000 97 : 2-002 - Use G^ addressing for externals.  SBL 24-Aug-1981
0000 98 : 2-003 - Added vectored entry point MTH$$AB_ATAN V.  RNH 29-Sep-81
0000 99 : 2-004 - Changed MTH$ATAND2 to MTH$ATAN2D to conform to original spec.
0000 100 :     RNH 05-Oct-81
0000 101 : 2-005 - Un-did previous edit to conform with PL/1 names.
0000 102 :     - Modified small argument logic to avoid an FPA bug in the POLY
0000 103 :     instruction.  RNH 17-Dec-81

```

```

0000 105          .SBTTL  DECLARATIONS      ; Declarative Part of Module
0000 106
0000 107
0000 108  : INCLUDE FILES:          MTHJACKET.MAR
0000 109
0000 110
0000 111  : EQUATED SYMBOLS:
0000 112
0000401C 0000 113          ACMASK = ^M<IV, R2, R3, R4>      ; .ENTRY register mask, int ovf enabled
0FDB40C9 0000 114          LF_PI_OVER_2_HI = ^X0FDB40C9      ; High 24 bits of pi/2
BD2EB43B 0000 115          LF_PI_OVER_2_LO = ^XBD2EB43B      ; Low 24 bits of pi/2
0FDBC0C9 0000 116          LF_MPI_OVER_2 = ^X0FDBC0C9      ; -pi/2
0FDB40C9 0000 117          LF_PI_OVER_2 = ^X0FDB40C9      ; pi/2
00004434 0000 118          LF_180 = ^X00004434      ; 90
0000C3B4 0000 119          LF_M90 = ^X0000C3B4      ; -90
0FDB4149 0000 120          LF_PI = ^X0FDB4149      ; pi
000043B4 0000 121          LF_90 = ^X000043B4      ; 90
0000 122
0000 123
0000 124  : MACROS:          none
0000 125
0000 126  : PSECT DECLARATIONS:
0000 127
00000000 0000 128          .PSECT  _MTH$CODE          PIC,SHR,LONG,EXE,NOWRT
0000 129                                     ; program section for math routines
0000 130
0000 131  : OWN STORAGE:  none
0000 132
0000 133  : EXTERNALS:
0000 134
0000 135          .EXTRN  MTH$$SIGNAL      ; Signal a severe error
0000 136          .EXTRN  MTH$K_INVARGMAT ; Invalid argument to math library
0000 137          .DSABL  GBL      ; No other externals allowed
0000 138
0000 139  : CONSTANTS:
0000 140
0000 141
0000 142  : The MTH$$AB ATAN table is a table of byte entries used to obtain an index
0000 143  : into the ATAN_TABLE. MTH$$AB_ATAN is indexed using the low order bits of
0000 144  : the exponent field and the high order bits of the fraction field. The
0000 145  : MTH$$AB_ATAN table is independent of the data type and is used by all of
0000 146  : the arc tangent routines.
0000 147
0000 148
0000 149  MTH$$AB_ATAN V: ; Simulated vector entry for G and
00000004 0000 150          .LONG  MTH$$AB_ATAN- ; H routines
0004 151  MTH$$AB_ATAN::
09 06 06 03 03 00 00 00 0004 152          .BYTE  ^X00, ^X00, ^X00, ^X03, ^X03, ^X06, ^X06, ^X09
12 0F 0F 0C 0C 0C 09 09 000C 153          .BYTE  ^X09, ^X09, ^X0C, ^X0C, ^X0C, ^X0F, ^X0F, ^X12
18 18 18 15 15 15 12 12 0014 154          .BYTE  ^X12, ^X12, ^X15, ^X15, ^X15, ^X18, ^X18, ^X18
21 1E 1E 1E 1B 1B 1B 1B 001C 155          .BYTE  ^X1B, ^X1B, ^X1B, ^X1B, ^X1E, ^X1E, ^X1E, ^X21
24 24 24 24 21 21 21 21 0024 156          .BYTE  ^X21, ^X21, ^X21, ^X21, ^X24, ^X24, ^X24, ^X24
27 27 27 27 27 27 24 24 002C 157          .BYTE  ^X24, ^X24, ^X27, ^X27, ^X27, ^X27, ^X27, ^X27
27 27 27 27 27 27 27 0034 158          .BYTE  ^X27, ^X27, ^X27, ^X27, ^X27, ^X27, ^X27
003B 159
003B 160

```

```

003B 162 :
003B 163 :
003B 164 :
003B 165 :
003B 166 :
003B 167 :
003B 168 :
003B 169 :
003B 170 :
003B 171 :
003B 172 :
003B 173 :
003C 174 :
003C 175 :
003C 176 :
F87E3ED7 003C 177 :
0A99B21B 0040 178 :
2CE73ED7 0044 179 :
FB703F03 0048 180 :
F372325E 004C 181 :
422F3F03 0050 182 :
0054 183 :
F63E3F1F 0054 184 :
B326B253 0058 185 :
ADF13F1E 005C 186 :
0060 187 :
E4EC3F47 0060 188 :
4A61B2AA 0064 189 :
69623F45 0068 190 :
006C 191 :
C3D13F7F 006C 192 :
678D3298 0070 193 :
A30A3F7A 0074 194 :
0078 195 :
DB973F9F 0078 196 :
315D3323 007C 197 :
F28D3F9A 0080 198 :
0084 199 :
9E8E3FC7 0084 200 :
F1A6335E 0088 201 :
56713FBE 008C 202 :
0090 203 :
33B63FFF 0090 204 :
C9A0B31E 0094 205 :
BFB03FEC 0098 206 :
009C 207 :
F8EB4026 009C 208 :
4695B38C 00A0 209 :
F4394013 00A4 210 :
00A8 211 :
0712405E 00A8 212 :
6A34B399 00AC 213 :
E62C4036 00B0 214 :
00B4 215 :
CBD84095 00B4 216 :
99953108 00B8 217 :

```

\*\*\*\*\* Constants for ATAN \*\*\*\*\*

Each entry of the ATAN TABLE contains the the values of XHI, ATAN\_XHI\_LO and ATAN\_XHI\_HI respectively. The table is indexed by a pointer obtained from the MTR\$SAB ATAN table. NOTE: For performance reasons it is important to have the ATAN\_TABLE longword aligned.

.ALIGN LONG

ATAN TABLE:

```

; Entry 0
.LONG ^XF87E3ED7 : 0.105454430E+00
.LONG ^X0A99B21B : -.225614927E-08
.LONG ^X2CE73ED7 : 0.105066113E+00
; Entry 1
.LONG ^XFB703F03 : 0.128888845E+00
.LONG ^XF372325E : 0.324436344E-08
.LONG ^X422F3F03 : 0.128182158E+00
; Entry 2
.LONG ^XF63E3F1F : 0.156212777E+00
.LONG ^XB326B253 : -.308063752E-08
.LONG ^XADF13F1E : 0.154960409E+00
; Entry 3
.LONG ^XE4EC3F47 : 0.195209205E+00
.LONG ^X4A61B2AA : -.495610708E-08
.LONG ^X69623F45 : 0.192784816E+00
; Entry 4
.LONG ^XC3D13F7F : 0.249770418E+00
.LONG ^X678D3298 : 0.443555459E-08
.LONG ^XA30A3F7A : 0.244762570E+00
; Entry 5
.LONG ^XDB973F9F : 0.312222213E+00
.LONG ^X315D3323 : 0.949907264E-08
.LONG ^XF28D3F9A : 0.302631766E+00
; Entry 6
.LONG ^X9E8E3FC7 : 0.389881551E+00
.LONG ^XF1A6335E : 0.129770452E-07
.LONG ^X56713FBE : 0.371753246E+00
; Entry 7
.LONG ^X33B63FFF : 0.498441398E+00
.LONG ^XC9A0B31E : -.924265464E-08
.LONG ^XBFB03FEC : 0.462399960E+00
; Entry 8
.LONG ^XF8EB4026 : 0.652235687E+00
.LONG ^X4695B38C : -.163302420E-07
.LONG ^XF4394013 : 0.577945292E+00
; Entry 9
.LONG ^X712405E : 0.867295384E+00
.LONG ^X6A34B399 : -.178598398E-07
.LONG ^XE62C4036 : 0.714449644E+00
; Entry 10
.LONG ^XCBD84095 : 0.117028332E+01
.LONG ^X99953108 : 0.496947650E-09

```



```

1B62405D 00BC 219 .LONG ^X1B62405D ; 0.863699079E+00
          00C0 220 ; Entry i1
8DEB40D2 00C0 221 .LONG ^X8DEB40D2 ; 0.164495599E+01
DBF9B3F3 00C4 222 .LONG ^XDBF9B3F3 ; -.283889552E-07
25414083 00C8 223 .LONG ^X25414083 ; 0.102457440E+01
          00CC 224 ; Entry i2
88054124 00CC 225 .LONG ^X88054124 ; 0.257080197E+01
888B3433 00D0 226 .LONG ^X888B3433 ; 0.418008703E-07
93CA4099 00D4 227 .LONG ^X93CA4099 ; 0.119982266E+01
          00D8 228 ; Entry i3
7D0E41AB 00D8 229 .LONG ^X7D0E41AB ; 0.535901546E+01
DF7F33C8 00DC 230 .LONG ^XDF7F33C8 ; 0.233846986E-07
72D240B1 00E0 231 .LONG ^X72D240B1 ; 0.138631654E+01
          00E4 232
          00E4 233 ;
          00E4 234 ; Tables to be used in POLYF for computing ATAN. ATANTAB1 is obtained
          00E4 235 ; from Hart et. al. (No. 4900). ATANTAB2 is the same as ATANTAB1 except
          00E4 236 ; that C0 is set to 0
          00E4 237
          00E4 238 ATANTAB1:
B0AA3F4A 00E4 239 .LONG ^XB0AA3F4A ; C2 = .19793954
A9B0BFAA 00E8 240 .LONG ^XA9B0BFAA ; C1 = -.33332586
00004080 00EC 241 .LONG ^X00004080 ; C0 = 1.00000000
00000003 00F0 242 ATANLEN1 = .- ATANTAB1/4
          00F0 243
          00F0 244 ATANTAB2:
B0AA3F4A 00F0 245 .LONG ^XB0AA3F4A ; C2 = .19793954
A9B0BFAA 00F4 246 .LONG ^XA9B0BFAA ; C1 = -.33332586
00000000 00F8 247 .LONG ^X00000000 ; C0 = .00000000
00000003 00FC 248 ATANLEN2 = .- ATANTAB2/4
          00FC 249
          00FC 250
  
```

```

00FC 252 :
00FC 253 :
00FC 254 : ***** Constants for ATAND *****
00FC 255 :
00FC 256 :
00FC 257 : Each entry of the ATAND_TABLE contains the the values of XHI, ATAND_XHI_LO
00FC 258 : and ATAND_XHI_HI respectively. The table is indexed by a pointer obtained
00FC 259 : from the MTHSSAB_ATAN table. NOTE: for performance reasons it is important
00FC 260 : to have the ATAND_TABLE longword aligned.
00FC 261 :
00FC 262 :
00FC 263 ATAND_TABLE:
00FC 264 ; Entry 0
F87E3ED7 00FC 265 .LONG ^XF87E3ED7 ; 0.105454430E+00
B1EF354F 0100 266 .LONG ^XP1EF354F ; 0.193431092E-06
A29141C0 0104 267 .LONG ^XA29141C0 ; 0.601984453E+01
0108 268 ; Entry 1
FB703F03 0108 269 .LONG ^XFB703F03 ; 0.128888845E+00
FE1BB4C3 010C 270 .LONG ^XFE1BB4C3 ; -.912661662E-07
047B41EB 0110 271 .LONG ^X047B41EB ; 0.734429693E+01
0114 272 ; Entry 2
F63E3F1F 0114 273 .LONG ^XF63E3F1F ; 0.156212777E+00
AF4932FD 0118 274 .LONG ^XAF4932FD ; 0.738319672E-08
0EA7420E 011C 275 .LONG ^X0EA7420E ; 0.887857723E+01
0120 276 ; Entry 3
E4EC3F47 0120 277 .LONG ^XE4EC3F47 ; 0.195209205E+00
3623B5A7 0124 278 .LONG ^X3623B5A7 ; -.311455636E-06
BB6B4230 0128 279 .LONG ^XBB6B4230 ; 0.110457563E+02
012C 280 ; Entry 4
C3D13F7F 012C 281 .LONG ^XC3D13F7F ; 0.249770418E+00
4257B5C1 0130 282 .LONG ^X4257B5C1 ; -.359973200E-06
61BE4260 0134 283 .LONG ^X61BE4260 ; 0.140238628E+02
0138 284 ; Entry 5
DB973F9F 0138 285 .LONG ^XDB973F9F ; 0.312222213E+00
300C351B 013C 286 .LONG ^X300C351B ; 0.144529793E-06
B758428A 0140 287 .LONG ^XB758428A ; 0.173395233E+02
0144 288 ; Entry 6
9E8E3FC7 0144 289 .LONG ^X9E8E3FC7 ; 0.389881551E+00
CFDD35A6 0148 290 .LONG ^XCFDD35A6 ; 0.310711499E-06
662E42AA 014C 291 .LONG ^X662E42AA ; 0.212998924E+02
0150 292 ; Entry 7
33B63FFF 0150 293 .LONG ^X33B63FFF ; 0.498441398E+00
F7DAB674 0154 294 .LONG ^XF7DAB674 ; -.912577548E-06
F2D342D3 0158 295 .LONG ^XF2D342D3 ; 0.264935665E+02
015C 296 ; Entry 8
F8EB4026 015C 297 .LONG ^XF8EB4026 ; 0.652235687E+00
ADBDB6DF 0160 298 .LONG ^XADBDB6DF ; -.166653592E-05
748F4304 0164 299 .LONG ^X748F4304 ; 0.331138268E+02
0168 300 ; Entry 9
0712405E 0168 301 .LONG ^X0712405E ; 0.867295384E+00
BD24359B 016C 302 .LONG ^XBD24359B ; 0.290086177E-06
BD634323 0170 303 .LONG ^XBD634323 ; 0.409349480E+02
0174 304 ; Entry 10
CBD84095 0174 305 .LONG ^XCBD84095 ; 0.117028332E+01
B637B668 0178 306 .LONG ^XB637B668 ; -.866918924E-06
F1FC4345 017C 307 .LONG ^XF1FC4345 ; 0.494863129E+02
0180 308 ; Entry 11

```

```

8DEB40D2 0180 309 .LONG ^X8DEB40D2 ; 0.164495599E+01
9881B6CC 0184 310 .LONG ^X9881B6CC ; -.152435689E-05
DOAE436A 0188 311 .LONG ^XDOAE436A ; 0.587037888E+02
018C 312 ; Entry i2
88054124 018C 313 .LONG ^X88054124 ; 0.257080197E+01
41353761 0190 314 .LONG ^X41353761 ; 0.335655682E-05
7D534389 0194 315 .LONG ^X7D534389 ; 0.687447739E+02
0198 316 ; Entry i3
7D0E41AB 0198 317 .LONG ^X7D0E41AB ; 0.535901546E+01
FEC377E 019C 318 .LONG ^XFEC377E ; 0.379972630E-05
DC34439E 01A0 319 .LONG ^XDC34439E ; 0.794300842E+02
01A4 320
01A4 321 ;
01A4 322 ; Tables to be used in POLYF for computing ATAND. ATANDTAB1 is obtained
01A4 323 ; by multiplying the coefficients given in Hart et. al. (No. 4900) by
01A4 324 ; 180/pi. ATANDTAB2 is the same as ATANDTAB1 except that C0 is set to
01A4 325 ; 180/pi - 64 instead of 180/pi.
01A4 326
01A4 327 ATANDTAB1:
75264235 01A4 328 .LONG ^X75264235 ; C2 = 11.341100693
C90BC298 01A8 329 .LONG ^XC90BC298 ; C1 = -19.098165512
2EE14365 01AC 330 .LONG ^X2EE14365 ; C0 = 57.295780182
00000003 01B0 331 ATANDLEN1 = .- ATANDTAB1/4
01B0 332
01B0 333 ATANDTAB2:
75264235 01B0 334 .LONG ^X75264235 ; C2 = 11.341100693
C90BC298 01B4 335 .LONG ^XC90BC298 ; C1 = -19.098165512
01B8 336 PI_OV_180 M 64:
88F9C1D6 01B8 337 .LONG ^X88F9C1D6 ; C0 = -6.704219818
00000003 01BC 338 ATANDLEN2 = .- ATANDTAB2/4
01BC 339
01BC 340

```

```

01BC 342 .SBTTL MTH$ATAN - Standard Single Precision Floating Arc Tangent
01BC 343
01BC 344
01BC 345 :++
01BC 346 : FUNCTIONAL DESCRIPTION:
01BC 347
01BC 348 : ATAN - single precision floating point function
01BC 349
01BC 350 : ATAN is computed using the following steps:
01BC 351
01BC 352 : 1. If X > 11 then
01BC 353 : a. Let W = 1/X.
01BC 354 : b. Compute ATAN(W) = W*P(W**2), where P is a polynomial of
01BC 355 : degree 2.
01BC 356 : c. Set ATAN(X) = pi/2 - ATAN(W)
01BC 357 : 2. If 3/32 <= X <= 11 then
01BC 358 : a. Obtain XHI by table look-up.
01BC 359 : b. Compute Z = (X - XHI)/(1 + X*XHI).
01BC 360 : c. Compute ATAN(Z) = Z*P(Z**2), where P is a polynomial of
01BC 361 : degree 2.
01BC 362 : d. Obtain ATAN(XHI) by table look-up. ATAN(XHI) will have
01BC 363 : two parts - the high order bits, ATAN_XHI_HI, and the low
01BC 364 : order bits, ATAN_XHI_LO.
01BC 365 : e. Compute ATAN(X) = ATAN_XHI_HI + (ATAN_XHI_LO + ATAN(Z)).
01BC 366 : 3. If 0 <= X < 3/32 then
01BC 367 : a. Compute ATAN(X) = X + X*Q(X**2), where Q is a polynomial
01BC 368 : of degree 2.
01BC 369 : 4. If X < 0 then
01BC 370 : a. Compute Y = ATAN(!X!) using steps 1 to 3.
01BC 371 : b. Set ATAN(X) = -Y.
01BC 372
01BC 373 : CALLING SEQUENCE:
01BC 374 :
01BC 375 : Arctangent.wf.v = MTH$ATAN(x.rf.r)
01BC 376
01BC 377 : INPUT PARAMETERS:
01BC 378
01BC 379 : LONG = 4 ; define longword multiplier
00000004 01BC 380 : x = 1 * LONG ; x is an angle in radians
00000004 01BC 381
01BC 382 : IMPLICIT INPUTS: none
01BC 383
01BC 384 : OUTPUT PARAMETERS:
01BC 385
01BC 386 : VALUE: floating arctangent angle of the argument
01BC 387
01BC 388 : IMPLICIT OUTPUTS: none
01BC 389
01BC 390 : SIDE EFFECTS:
01BC 391
01BC 392 : Signals: none
01BC 393
01BC 394 : NOTE: This procedure disables floating point underflow and integer
01BC 395 : overflow, causes no floating overflow or other arithmetic traps, and
01BC 396 : preserves enables across the call.
01BC 397
01BC 398 :

```



```

01CC 412      .SBTTL MTH$ATAN2 - Standard floating Arctangent With 2 Arguments
01CC 413      :++
01CC 414      : FUNCTIONAL DESCRIPTION:
01CC 415      :
01CC 416      : ATAN2 - single precision floating point function
01CC 417      :
01CC 418      : ATAN2(X,Y) is computed as following:
01CC 419      :
01CC 420      :     If Y = 0 or X/Y > 2**25, ATAN2(X,Y) = PI/2 * (sign X)
01CC 421      :     If Y > 0 and X/Y <= 2**25, ATAN2(X,Y) = ATAN(X/Y)
01CC 422      :     If Y < 0 and X/Y <= 2**25, ATAN2(X,Y) = PI * (sign X) + ATAN(X/Y)
01CC 423      :
01CC 424      :
01CC 425      : CALLING SEQUENCE:
01CC 426      :
01CC 427      :     Arctangent2.wf.v = MTH$ATAN2(x.rf.r, y.rf.r)
01CC 428      :
01CC 429      : INPUT PARAMETERS:
01CC 430      :
00000004 01CC 431      :     x = 1 * LONG           ; x is the first argument
00000008 01CC 432      :     y = 2 * LONG           ; y is the second argument
01CC 433      :
01CC 434      : SIDE EFFECTS: See description of MTH$ATAN
01CC 435      :
01CC 436      :--
01CC 437      :
01CC 438      :
401C 01CC 439      : .ENTRY MTH$ATAN2 ,ACMASK           ; standard call-by-reference entry
01CE 440      :                               ; disable DV (and FU), enable IV
01CE 441      : MTH$FLAG_JACKET             ; flag that this is jacket procedure
6D 00000000'GF 9E 01CE 442      : MOVAB G*MTH$$JACKET_HND, (FP) ; set handler address to jacket
01D5 443      :                               ; handler
01D5 444      :
01D5 445      :                               ; in case of an error in special JSB routine
50 04 BC 50 01D5 446      : MOVF @x(AP), R0             ; R0 = arg1
51 08 BC 50 01D9 447      : MOVF @y(AP), R1             ; R1 = arg2
01DD 448      :
01DD 449      : Test if Y = 0 or X/Y > 2**25
01DD 450      :
52 50 807F 8F 13 01DD 451      : BEQL INF                     ; branch to INF if Y = 0
53 51 807F 8F AB 01DF 452      : BICW3 #^X807F, R0, R2       ; R2 = exponent(X)
0D00 8F 52 53 A2 01E5 453      : BICW3 #^X807F, R1, R3       ; R3 = exponent(Y)
01EB 454      : SUBW R3, R2                  ; R2 = exponent(X) - expcnent(Y)
01EE 455      : CMPW R2, #26*128            ; compare R2 with 26
01F3 456      : BGTR INF                     ; if X/Y > 2**25, branch to INF
01F5 457      :
01F5 458      : Test if Y > 0 or Y < 0
01F5 459      :
51 B5 01F5 460      : TSTW R1                      ; test the sign of Y
18 14 01F7 461      : BGTR A2PLUS                  ; branch to A2PLUS if Y > 0
50 B5 01F9 462      : TSTW R0                      ; test the sign of X
0A 18 01FB 463      : BGEQ A1PLUS                  ; branch to A1PLUS if X >= 0
01FD 464      :
01FD 465      : Y < 0 and X < 0 and X/Y <= 2**25
01FD 466      :
01FD 467      :

```

M  
P  
P  
I  
P  
S  
P  
S  
C  
A  
T  
I  
T  
I  
T  
I  
T  
I  
M  
I  
O  
T  
M

```

50 0FDB4149 3B 10 01FD 464 BSBB MTHSATAN R4D ; R0 = ATAN(X/Y)
      8F 42 01FF 465 SUBF #LF_PI, R0 ; R0 = -PI + ATAN(X/Y)
      04 0206 466 RET ; return
      0207 467 :
      0207 468 : Y < 0 and X > 0 and X/Y =< 2**25
      0207 469 :
      0207 470 A1PLUS:
50 0FDB4149 31 10 0207 471 BSBB MTHSATAN R4D ; R0 = ATAN(X/Y)
      8F 40 0209 472 ADDF #LF_PI, R0 ; R0 = PI + ATAN(X/Y)
      04 0210 473 RET ; return
      0211 474 :
      0211 475 : Y > 0 and X/Y =< 2**25
      0211 476 :
      0211 477 A2PLUS:
      27 10 0211 478 BSBB MTHSATAN_R4D ; R0 = ATAN(X/Y)
      04 0213 479 RET ; return
      0214 480 :
      0214 481 : Y = 0 or X/Y > 2**25
      0214 482 :
      0214 483 INF:
      50 85 0214 484 TSTW R0 ; test the sign of X
      0A 14 0216 485 BGTR 1$ ; branch if X > 0
      10 13 0218 486 BEQL 2$ ; branch if X = 0
50 0FDBC0C9 8F 50 021A 487 MOVF #LF_MPI_OVER_2, R0 ; R0 = ATAN(X/Y) = -PI/2
      04 0221 488 RET ; return
      0222 489
50 0FDB40C9 8F 50 0222 490 1$: MOVF #LF_PI_OVER_2, R0 ; R0 = ATAN(X/Y) = PI/2
      04 0229 491 RET ; return
      022A 492
      022A 493 :+
      022A 494 : Here if X = 0 and Y = 0. Signal INVALID ARG TO MATH LIBRARY
      022A 495 : as a SEVERE error.
      022A 496 :-
      022A 497
      50 01 0F 79 022A 498 2$: ASHQ #15, #1, R0 ; R0/R1 = reserved operand which
      022E 499 ; is copied to CHFSL_MCH_SAVRO/R1
      022E 500 ; so a handler can fixup if wants
      022E 501 ; to continue
      7E 00'8F 9A 022E 502 MOVZBL #MTHSK_INVARGMAT, -(SP) ; code for INVALID ARG TO MATH LIBRARY
00000000'GF 01 FB 0232 503 CALLS #1, G^MTHSSIGNAL ; signal SEVERE error
      04 0239 504 RET ; return if handler continues

```

```

023A 506      .SBTTL MTHSATAN_R4 - Special ATAN routine
023A 507
023A 508      : Special ATAN - used by the standard routine, and directly.
023A 509
023A 510      : CALLING SEQUENCES:
023A 511      :   save anything needed in R0:R4
023A 512      :   MOVF      R0                      ; input in R0
023A 513      :   JSB      MTHSATAN_R4
023A 514      :   return with result in R0
023A 515
023A 516      : Note: This routine is written to avoid causing any integer overflows,
023A 517      : floating overflows, or floating underflows or divide by 0 conditions,
023A 518      : whether enabled or not.
023A 519
023A 520      : REGISTERS USED:
023A 521      :   R0 - Floating argument then result
023A 522      :   R0:R3 - POLYF
023A 523      :   R4 - Pointer into ATAN_TABLE
023A 524
023A 525
023A 526
023A 527      MTHSATAN_R4D:
023A 528      DIVF      R1, R0                      ; for our own use only!
023D 529      MTHSATAN_R4::
023D 530      TSTF      R0                          ; Special ATAN routine
023F 531      BLSS    NEG_ARG                    ; R4 = X = argument
0241 532      :                                     ; Branch to negative argument logic
0241 533      : Argument is positive
0241 534
0241 535      SUBW3    #^X3EC0, R0, R4                ; Argument is less than 3/32,
0247 536      BLSS    SMALL                       ; branch to small argument logic
0249 537      CMPW    #^X036F, R4                 ; Argument is greater than 11,
024E 538      BLSS    LARGE_ARG                    ; branch to large argument logic
0250 539
0250 540      : Logic for positive medium sized arguments. Get pointer into ATAN_TABLE.
0250 541
0250 542      ROTL     #-4, R4, R4                     ; R4 = index into MTH$SAB_ATAN table
0255 543      BICL     #-256, R4                     ; zero high order bits of index
025C 544      MOVB    MTH$SAB_ATAN[R4], R4        ; R4 = offset into ATAN_TABLE
0262 545      MOVAL   ATAN_TABLE[R4], R4         ; R4 = pointer to XHI
0268 546
0268 547      : Compute Z
0268 548
0268 549      MOVL     (R4)+, R1                       ; R1 = XHI
0268 550      MULF3    R1, R0, R2                     ; R2 = X*XHI
026F 551      ADDF    #1, R2                         ; R2 = 1 + X*XHI
0272 552      SUBF    R1, R0                         ; R0 = X - XHI
0275 553      DIVF    R2, R0                         ; R0 = Z = (X - XHI)/(1 + X*XHI)
0278 554
0278 555      : Evaluate Z*P(Z**2)
0278 556
0278 557      MOVL     R0, -(SP)                        ; Push Z onto the stack
0278 558      MULF    R0, R0                          ; R0 = Z**2
027E 559      POLYF   R0, #ATANLEN1-1, ATANTAB1
0284 560      : R0 = P(Z**2)
0284 561      MULF    (SP)+, R0                       ; R0 = ATAN(Z) = Z*P(Z**2)
0287 562      ADDF    (R4)+, R0                       ; R0 = ATAN_XHI_LO + ATAN(Z)

```





```

05 0302 620          RSB          ; Return
    0303 621          ;
    0303 622          ; Logic for large negative arguments
    0303 623          ;
    0303 624          ;
54 0000C080 8F 50 47 0303 625 N_LARGE_ARG:
    50 50 54 54 45 0303 626 DIVF3 R0, #-1, R4          ; R4 = W = 1/|X|
    FDCF CF 02 50 55 030B 627 MULF3 R4, R4, R0          ; R0 = W**2
    50 50 54 54 44 030F 628 POLYF R0, #ATANLEN1-1, ATANTAB1 ; R0 = P(W**2)
    50 BD2EB43B 8F 42 0315 629          ; R0 = ATAN(W) = W*P(W**2)
    50 UFDB40C9 8F 42 0315 630 MULF R4, R0
    50 42 0318 631 SUBF #LF_PI_OVER_2_LO, R0
    50 42 031F 632 SUBF #LF_PI_OVER_2_HI, R0
    05 0326 633          ; R0 = ATAN(X) = ATAN(W) - PI/2
    0327 634          ; Return
    0327 635          ;
    0327 636          ; Small argument logic.
    0327 637          ;
    0327 638          ;
    50 54 50 D0 0327 639 SMALL_ARG:
    50 8000 8F AA 032A 640 MOVL R0, R4          ; R4 = argument = X
    50 3A00 8F B1 032F 641 BICW #^X8000, R0      ; R0 = |X|
    50 04 19 0334 642 CMPW #^X3A00, R0          ; Compare 2^-13 to |X|
    50 54 D0 0336 643 BLSS 1$                  ; Branch to polynomial evaluation
    05 0339 644 MOVL R4, R0                    ; No POLY needed. Answer = X
    033A 645          ;
    033A 646          ;
    FDAD CF 50 50 44 033A 647 1$: MULF R0, R0      ; R0 = X**2
    50 02 50 55 033D 648 POLYF R0, #ATANLEN2-1, ATANTAB2 ; R0 = Q(X**2)
    50 54 44 0343 649          ; R0 = X*Q(X**2)
    50 54 40 0346 650 MULF R4, R0
    05 0349 651 ADDF R4, R0
    034A 652          ; R0 = ATAN(X) = X + X*Q(X**2)
    034A 653          ; Return
    034A 654          ;
    034A 655          ;

```

```
034A 657 .SBTTL MTH$ATAND - Standard Single Precision Floating Arc Tangent
034A 658
034A 659
034A 660 :++
034A 661 : FUNCTIONAL DESCRIPTION:
034A 662 :
034A 663 : ATAND - single precision floating point function
034A 664 :
034A 665 : ATAND is computed using the following steps:
034A 666 :
034A 667 : 1. If X > 11 then
034A 668 : a. Let W = 1/X.
034A 669 : b. Compute ATAND(W) = W*P(W**2), where P is a polynomial of
034A 670 : degree 2.
034A 671 : c. Set ATAND(X) = pi/2 - ATAND(W)
034A 672 : 2. If 3/32 =< X =< 11 then
034A 673 : a. Obtain XHI by table look-up.
034A 674 : b. Compute Z = (X - XHI)/(1 + X*XHI).
034A 675 : c. Compute ATAND(Z) = Z*P(Z**2), where P is a polynomial of
034A 676 : degree 2.
034A 677 : d. Obtain ATAND(XHI) by table look-up. ATAND(XHI) will have
034A 678 : two parts - the high order bits, ATAND_XHI_HI, and the low
034A 679 : order bits, ATAND_XHI_LO.
034A 680 : e. Compute ATAND(X) = ATAND_XHI_HI + (ATAND_XHI_LO + ATAND(Z)).
034A 681 : 3. If 0 =< X < 3/32 then
034A 682 : a. Compute ATAND(X) = 64*X + X*Q(X**2), where Q is a polynomial
034A 683 : of degree 2.
034A 684 : 4. If X < 0 then
034A 685 : a. Compute Y = ATAND(|X|) using steps 1 to 3.
034A 686 : b. Set ATAND(X) = -Y.
034A 687 :
034A 688 :
034A 689 : CALLING SEQUENCE:
034A 690 :
034A 691 : Arctangent.wf.v = MTH$ATAND(x.rf.r)
034A 692 :
034A 693 : INPUT PARAMETERS:
034A 694 :
00000004 034A 695 : LONG = 4 ; define longword multiplier
00000004 034A 696 : x = 1 * LONG ; x is an angle in radians
034A 697 :
034A 698 : IMPLICIT INPUTS: none
034A 699 :
034A 700 : OUTPUT PARAMETERS:
034A 701 :
034A 702 : VALUE: floating arctangent angle of the argument (in degrees)
034A 703 :
034A 704 : IMPLICIT OUTPUTS: none
034A 705 :
034A 706 : SIDE EFFECTS:
034A 707 :
034A 708 : Signals: none
034A 709 :
034A 710 : NOTE: This procedure disables floating point underflow and integer
034A 711 : overflow, causes no floating overflow or other arithmetic traps, and
034A 712 : preserves enables across the call.
034A 713 :
```

```

034A 714 ;---
034A 715
034A 716
401C 034A 717      .ENTRY MTHSATAND, ACMASK      ; standard call-by-reference entry
034C 718          ; disable DV (and FU), enable IV
034C 719          MTH$FLAG_JACKET      ; flag that this is a jacket procedure
034C
6D 00000000'GF 9E 034C      MOVAB G^MTH$$JACKET_HND, (FP) ; set handler address to jacket
0353          ; handler
0353
0353 720          ; in case of an error in special JSB
0353 721          ; routine
50 04 BC 50 0353 722      MOVF @x(AP), R0      ; R0 = arg
72 10 0357 723      BSBB MTHSATAND_R4 ; call special ATAND routine
04 0359 724      RET      ; return - result in R0
035A 725

```

```

035A 727      .SBTTL MTH$ATAND2 - Standard floating Arctangent With 2 Arguments
035A 728      :++
035A 729      : FUNCTIONAL DESCRIPTION:
035A 730      :
035A 731      : ATAND2 - single precision floating point function
035A 732      :
035A 733      : ATAND2(X,Y) is computed as following:
035A 734      :
035A 735      :     If Y = 0 or X/Y > 2**25, ATAND2(X,Y) = 90 * (sign X)
035A 736      :     If Y > 0 and X/Y =< 2**25, ATAND2(X,Y) = ATAND(X/Y)
035A 737      :     If Y < 0 and X/Y =< 2**25, ATAND2(X,Y) = 180 * (sign X) + ATAND(X/Y)
035A 738      :
035A 739      :
035A 740      : CALLING SEQUENCE:
035A 741      :
035A 742      :     Arctangent2.wf.v = MTH$ATAND2(x.rf.r, y.rf.r)
035A 743      :
035A 744      : INPUT PARAMETERS:
035A 745      :
00000004 035A 746      :     x = 1 * LONG           ; x is the first argument
00000008 035A 747      :     y = 2 * LONG           ; y is the second argument
035A 748      :
035A 749      : SIDE EFFECTS: See description of MTH$ATAND
035A 750      :
035A 751      :--
035A 752      :
035A 753      :
401C 035A 754      .ENTRY MTH$ATAND2 ,ACMASK           ; standard call-by-reference entry
035C 755      :                                     ; disable DV (and FU), enable IV
035C 756      MTH$FLAG_JACKET           ; flag that this is jacket procedure
035C
6D 00000000'GF 9E 035C
035C 757      MOVAB G^MTH$$JACKET_HND, (FP)           ; set handler address to jacket
0363 758      :                                     ; handler
0363 759      :
0363 760      : in case of an error in special JSB
0363 761      : routine
50 04 BC 50 0363 762      MOVF @x(AP), R0           ; R0 = arg1
51 08 BC 50 0367 763      MOVF @y(AP), R1           ; R1 = arg2
036B 764      :
036B 765      : Test if Y = 0 or X/Y > 2**25
036B 766      :
52 50 807F 8F AB 036B 767      BEQL INFD           ; branch to INFD if Y = 0
53 51 807F 8F AB 036D 768      BICW3 #^X807F, R0, R2 ; R2 = exponent(X)
52 53 A2 0373 769      BICW3 #^X807F, R1, R3 ; R3 = exponent(Y)
0D00 8F 52 B1 0379 770      SUBW R3, R2           ; R2 = exponent(X) - exponent(Y)
1F 14 037C 771      CMPW R2, #26*128 ; compare R2 with 26
0381 772      BGTR INFD           ; if X/Y > 2**25, branch to INFD
0383 773      :
0383 774      : Test if Y > 0 or Y < 0
0383 775      :
51 B5 0383 776      TSTW R1           ; test the sign of Y
18 14 0385 777      BGTR A2PLUSD ; branch to A2PLUSD if Y > 0
50 B5 0387 778      TSTW R0           ; test the sign of X
0A 18 0389 779      BGTR A1PLUSD ; branch to A1PLUSD if X >= 0
038B 780      :
038B 781      : Y < 0 and X < 0 and X/Y =< 2**25

```

```

50 00004434 3B 10 038B 779 ;
      8F 42 038B 780 ; BSBB MTHSATAND R4D ; R0 = ATAND(X/Y)
      04 038D 781 ; SUBF #LF_180, R0 ; R0 = -180 + ATAND(X/Y)
      0394 782 ; RET ; return
      0395 783 ;
      0395 784 ; Y < 0 and X > 0 and X/Y =< 2**25
      0395 785 ;
      0395 786 A1PLUSD:
50 00004434 31 10 0395 787 ; BSBB MTHSATAND R4D ; R0 = ATAND(X/Y)
      8F 40 0397 788 ; ADDF #LF_180, R0 ; R0 = 180 + ATAND(X/Y)
      04 039E 789 ; RET ; return
      039F 790 ;
      039F 791 ; Y > 0 and X/Y =< 2**25
      039F 792 ;
      039F 793 A2PLUSD:
      27 10 039F 794 ; BSBB MTHSATAND_R4D ; R0 = ATAND(X/Y)
      04 03A1 795 ; RET ; return
      03A2 796 ;
      03A2 797 ; Y = 0 or X/Y > 2**25
      03A2 798 ;
      03A2 799 INF0:
      50 B5 03A2 800 ; TSTW R0 ; test the sign of X
      0A 14 03A4 801 ; BGTR 1$ ; branch if X > 0
      10 13 03A6 802 ; BEQL 2$ ; branch if X = 0
50 0000C3B4 8F 50 03A8 803 ; MOVF #LF_M90, R0 ; R0 = ATAND(X/Y) = -90
      04 03AF 804 ; RET ; return
      03B0 805 ;
50 000043B4 8F 50 03B0 806 1$: MOVF #LF_90, R0 ; R0 = ATAND(X/Y) = 90
      04 03B7 807 ; RET ; return
      03B8 808 ;
      03B8 809 ;+
      03B8 810 ; Here if X = 0 and Y = 0. Signal INVALID ARG TO MATH LIBRARY
      03B8 811 ; as a SEVERE error.
      03B8 812 ;-
      03B8 813 ;
      50 01 0F 79 03B8 814 2$: ASHQ #15, #1, R0 ; R0/R1 = reserved operand which
      03BC 815 ; is co180ed to CHFSL_MCH_SAVRO/R1
      03BC 816 ; so a handler can fixup if wants
      03BC 817 ; to continue
      7E 00'8F 9A 03BC 818 ; MOVZBL #MTH$K_INVARGMAT, -(SP) ; code for INVALID ARG TO MATH LIBRARY
00000000'GF 01 FB 03C0 819 ; CALLS #1, G^MTH$$SIGNAL ; signal SEVERE error
      04 03C7 820 ; RET ; return if handler continues

```

```

03C8 822      .SBTTL MTH$ATAND_R4 - Special ATAND routine
03C8 823
03C8 824      ; Special ATAND - used by the standard routine, and directly.
03C8 825
03C8 826      CALLING SEQUENCES:
03C8 827          save anything needed in R0:R4
03C8 828          MOVF      R0              ; input in R0
03C8 829          JSB      MTH$ATAND_R4
03C8 830          return with result in R0
03C8 831
03C8 832      Note: This routine is written to avoid causing any integer overflows,
03C8 833      floating overflows, or floating underflows or divide by 0 conditions,
03C8 834      whether enabled or not.
03C8 835
03C8 836      REGISTERS USED:
03C8 837          R0 - Floating argument then result
03C8 838          R0:R3 - POLYF
03C8 839          R4 - Pointer into ATAND_TABLE
03C8 840
03C8 841
03C8 842      MTH$ATAND_R4D:
03C8 843          DIVF      R1, R0              ; for our own use only!
03C8 844      MTH$ATAND_R4::
03C8 845          TSTF      R0              ; Special ATAND routine
03C8 846          BLSS     NEG_ARGD        ; R4 = X = argument
03C8 847          ; Branch to negative argument logic
03C8 848          ; Argument is positive
03C8 849
03C8 850          SUBW3     #X3ECO, R0, R4      ; Argument is less than 3/32,
03C8 851          BLSS     SMALLD            ; branch to small argument logic
03C8 852          CMPW     #X036F, R4        ; Argument is greater than 11,
03C8 853          BLSS     LARGE_ARGD       ; branch to large argument logic
03C8 854
03C8 855      Logic for positive medium sized arguments.  Get pointer into ATAND_TABLE.
03C8 856
03C8 857          ROTL      #-4, R4, R4        ; R4 = index into MTH$$AB_ATAN table
03C8 858          BICL     #-256, R4          ; zero high order bits of index
03C8 859          MOVVB   MTH$$AB_ATAN[R4], R4 ; R4 = offset into ATAND_TABLE
03C8 860          MOVAL   ATAND_TABLE[R4], R4 ; R4 = pointer to XHI
03C8 861
03C8 862      Compute z
03C8 863
03C8 864          MOVL     (R4)+, R1          ; R1 = XHI
03C8 865          MULF3   R1, R0, R2        ; R2 = X*XHI
03C8 866          ADDF    #1, R2            ; R2 = 1 + X*XHI
03C8 867          SUBF    R1, R0            ; R0 = X - XHI
03C8 868          DIVF    R2, R0            ; R0 = Z = (X - XHI)/(1 + X*XHI)
03C8 869
03C8 870      Evaluate Z*P(Z**2)
03C8 871
03C8 872          MOVL     R0, -(SP)          ; Push Z onto the stack
03C8 873          MULF    R0, R0              ; R0 = Z**2
03C8 874          POLYF   R0, #ATANDLEN1-1, ATANDTAB1
03C8 875          ; R0 = P(Z**2)
03C8 876          MULF    (SP)+, R0          ; R0 = ATAND(Z) = Z*Q(Z**2)
03C8 877          ADDF    (R4)+, R0          ; R0 = ATAND_XHI_LO + ATAND(Z)
03C8 878          ADDF    (R4), R0            ; R0 = ATAND(X) = ATAND_XHI_HI +

```

```

05 041B 879 : (ATAND_XHI_LO + ATAND(Z))
041B 880 : Return
041C 881
041C 882
0088 31 041C 883 SMALLD: BRW SMALL_ARGD : Dummy label used to avoid adding
041F 884 : an extra insrtuction in the
041F 885 : medium argument logic
041F 886 :
041F 887 : Large positive argument logic.
041F 888 :
041F 889 :
041F 890 LARGE_ARGD:
54 0000C080 8F 50 47 041F 891 DIVF3 R0, #-1, R4 : R4 = -W = -1/X
50 54 54 45 0427 892 MULF3 R4, R4, R0 : R0 = W**2
FD73 CF 02 50 55 042B 893 POLYF R0, #ATANDLEN1-1, ATANDTAB1
0431 894 : R0 = P(W**2)
50 50 54 44 0431 895 MULF R4, R0 : R0 = -ATAND(Z) = -Z*P(W**2)
50 000043B4 8F 40 0434 896 ADDF #LF_90, R0 : R0 = ATAND(X) = 90 - ATAND(Z)
05 043B 897 RSB : Return
043C 898
043C 899 :
043C 900 : Logic for negative arguments
043C 901 :
043C 902 :
043C 903 NEG_ARGD:
54 50 BEC0 8F A3 043C 904 SUBW3 #XBEC0, R0, R4 : Argument is less than 3/32,
63 19 0442 905 BLSS SMALL_ARGD : branch to small argument logic
54 036F 8F B1 0444 906 CMPW #X036F, R4 : Argument is greater than 11,
3F 19 0449 907 BLSS N_LARGE_ARGD : branch to large argument logic
044B 908 :
044B 909 : Logic for negative medium sized arguments. Get index into ATAND_TABLE.
044B 910 :
54 54 FC 8F 9C 044B 911 ROTL #-4, R4, R4 : R4 = index into MTH$$AB ATAN table
54 FFFFFFF0 8F CA 0450 912 BICL #-256, R4 : clear high order (unused) bits of ind
54 FBAB CF44 90 0457 913 MOVW MTH$$AB ATAN[R4], R4 : R4 = offset into ATAN_TABLE
54 FC9A CF44 DE 045D 914 MOVAL ATAND_TABLE[R4], R4 : R4 = pointer to XHI
0463 915 :
0463 916 : Compute Z
0463 917 :
52 51 84 D0 0463 918 MOVL (R4)+, R1 : R1 = XHI
52 50 51 45 0466 919 MULF3 R1, R0, R2 : R2 = X*XHI
52 08 52 43 046A 920 SUBF3 R2, #1, R2 : R2 = 1 - X*XHI = 1 + X*(-XHI)
50 51 40 046E 921 ADDF R1, R0 : R0 = X + XHI = X - (-XHI)
50 52 46 0471 922 DIVF R2, R0 : R0 = Z
0474 923 :
0474 924 : Evaluate Z*P(Z**2)
0474 925 :
7E 50 D0 0474 926 MOVL R0, -(SP) : Push Z onto the stack
50 50 44 0477 927 MULF R0, R0 : R0 = Z**2
FD24 CF 02 50 55 047A 928 POLYF R0, #ATANDLEN1-1, ATANDTAB1
0480 929 : R0 = P(Z**2)
50 8E 44 0480 930 MULF (SP)+, R0 : R0 = ATAND(Z) = Z*P(Z**2)
50 84 42 0483 931 SUBF (R4)+, R0 : R0 = ATAND XHI_LO + ATAND(Z)
50 64 42 0486 932 SUBF (R4), R0 : R0 = ATAND(X) = ATAND XHI_HI +
0489 933 : (ATAND_XHI_LO + ATAND(Z))
05 0489 934 RSB : Return
048A 935 :

```



```

048A 936 ; Logic for large negative arguments
048A 937 ;
048A 938 ;
54 0000C080 8F 50 47 048A 939 N_LARGE_ARGD:
      50 54 54 45 048A 940 DIVF3 R0, #-1, R4 ; R4 = W = 1/!X!
      FD08 CF 02 50 55 0492 941 MULF3 R4, R4, R0 ; R0 = W**2
      50 50 54 44 0496 942 POLYF R0, #ATANDLEN1-1, ATANDTAB1 ; R0 = P(W**2)
      50 000043B4 8F 42 049C 944 MULF R4, R0 ; R0 = ATAND(W) = W*P(W**2)
      05 42 049F 945 SUBF #Lf_90, R0 ; R0 = ATAND(X) = ATAND(W) - 90
      05 04A6 946 RSB ; Return
      04A7 947 ;
      04A7 948 ; Small argument logic.
      04A7 949 ;
      04A7 950 ;
      04A7 951 ;
      04A7 952 SMALL_ARGD:
      54 50 50 04A7 953 MOVF R0, R4 ; R4 = argument = X
      50 8000 8F AA 04AA 954 BEQL 3$ ;
      50 3A00 8F B1 04AC 955 BICW #^X8000, R0 ; R0 = !X!
      54 FCFC CF 45 04B1 956 CMPW #^X3A00, R0 ; Compare 2^-13 to !X!
      54 54 08 19 04B6 957 BLSS 1$ ; Needs POLY
      FCE7 CF 45 04B8 958 MULF3 PI_OV_180_M_64, R4, R0 ; R0 = X*[pi/180 - 64]
      50 50 44 04C0 960 BRB 2$ ;
      50 02 50 55 04C3 962 1$: MULF R0, R0 ; R0 = X**2
      50 54 44 04C9 963 POLYF R0, #ATANDLEN2-1, ATANDTAB2 ; R0 = Q(X**2)
      54 0300 8F A0 04C9 964 MULF R4, R0 ; R0 = X*Q(X**2)
      50 54 40 04CC 965 2$: ADDW #^X300, R4 ; R4 = X*2**6
      05 40 04D1 966 ADDF R4, R0 ; R0 = ATAND(X) = X*2**6 + X*Q(X**2)
      05 04D4 967 3$: RSB ; Return
      04D5 968 ;
      04D5 969 ;
      04D5 970 ;
      04D5 971 .END

```

MTHSATAN  
Symbol table

G 12  
; Floating Point Arc Tangent Functions

16-SEP-1984 01:04:23 VAX/VMS Macro V04-00  
6-SEP-1984 11:20:31 [MTHRTL.SRC]MTHATAN.MAR;1

Page 23  
(11)

A1PLUS	00000207	R	01
A1PLUSD	00000395	R	01
A2PLUS	00000211	R	01
A2PLUSD	0000039F	R	01
ACMASK	= 0000401C		
ATANDLEN1	= 00000003		
ATANDLEN2	= 00000003		
ATANDTAB1	000001A4	R	01
ATANDTAB2	000001B0	R	01
ATAND_TABLE	000000FC	R	01
ATANLEN1	= 00000003		
ATANLEN2	= 00000003		
ATANTAB1	000000E4	R	01
ATANTAB2	000000F0	R	01
ATAN_TABLE	0000003C	R	01
INF	00000211	R	01
INFD	000003A2	R	01
LARGE_ARG	00000291	R	01
LARGE_ARGD	0000041F	R	01
LF_180	= 00004434		
LF_90	= 000043B4		
LF_M90	= 0000C3B4		
LF_MPI_OVER_2	= 0FDBC0C9		
LF_PI	= 0FDB4149		
LF_PI_OVER_2	= 0FDB40C9		
LF_PI_OVER_2_HI	= 0FDB40C9		
LF_PI_OVER_2_LO	= BD2EB43B		
LONG	= 00000004		
MTHSSAB_ATAN	00000004	RG	01
MTHSSAB_ATAN_V	00000000	RG	01
MTHSSJACKET_RND	*****	X	01
MTHSSIGNAL	*****	X	01
MTHSATAN	000001BC	RG	01
MTHSATAN2	000001CC	RG	01
MTHSATAND	0000034A	RG	01
MTHSATAND2	0000035A	RG	01
MTHSATAND_R4	000003CB	RG	01
MTHSATAND_R4D	000003C8	R	01
MTHSATAN_R4	0000023D	RG	01
MTHSATAN_R4D	0000023A	R	01
MTHSK_INVARGMAT	*****	X	01
NEG_ARG	000002B5	R	01
NEG_ARGD	0000043C	R	01
N_LARGE_ARG	00000303	R	01
N_LARGE_ARGD	0000048A	R	01
PI_OV_180_M_64	000001B8	R	01
SMALL	0000028E	R	01
SMALLD	0000041C	R	01
SMALL_ARG	00000327	R	01
SMALL_ARGD	000004A7	R	01
X	= 00000004		
Y	= 00000008		

-----+  
! Psect synopsis !  
-----+

PSECT name	Allocation	PSECT No.	Attributes
ABS	00000000 ( 0.)	00 ( 0.)	NOPIC USR
_MTHSCODE	000004D5 ( 1237.)	01 ( 1.)	PIC USR
			CON ABS LCL NOSHR NOEXE NORD NOWRT NOVEC BYTE
			CON REL LCL SHR EXE RD NOWRT NOVEC LONG

-----+  
! Performance indicators !  
-----+

Phase	Page faults	CPU Time	Elapsed Time
Initialization	29	00:00:00.10	00:00:00.31
Command processing	110	00:00:00.54	00:00:02.86
Pass 1	109	00:00:02.56	00:00:09.46
Symbol table sort	0	00:00:00.02	00:00:00.02
Pass 2	220	00:00:02.00	00:00:09.39
Symbol table output	6	00:00:00.06	00:00:00.22
Psect synopsis output	3	00:00:00.02	00:00:00.06
Cross-reference output	0	00:00:00.00	00:00:00.00
Assembler run totals	479	00:00:05.30	00:00:22.33

The working set limit was 1050 pages.  
15739 bytes (31 pages) of virtual memory were used to buffer the intermediate code.  
There were 10 pages of symbol table space allocated to hold 52 non-local and 8 local symbols.  
1031 source lines were read in Pass 1, producing 21 object records in Pass 2.  
1 page of virtual memory was used to define 1 macro.

-----+  
! Macro library statistics !  
-----+

Macro library name	Macros defined
_\$255\$DUA28:[SYSLIB]STARLET.MLB;2	0

0 GETS were required to define 0 macros.

There were no errors, warnings or information messages.

MACRO/ENABLE=SUPPRESSION/DISABLE=(GLOBAL,TRACEBACK)/LIS=LIS\$:MTHATAN/OBJ=OBJ\$:MTHATAN MSRCS:MTHJACKET/UPDATE=(ENH\$:MTHJACKET)+MSRCS:



0257 AH-BT13A-SE  
VAX/VMS V4.0

# DIGITAL EQUIPMENT CORPORATION CONFIDENTIAL AND PROPRIETARY

This image displays a grid of 140 small terminal window screenshots, arranged in 10 rows and 14 columns. Each window shows a different VAX/VMS utility or command-line interface. The windows are densely packed and contain various text-based outputs, including command prompts, status messages, and data listings. Some windows are clearly labeled with their utility names, such as:

- MTH4OVP LIS
- MTHABS LIS
- MTHINT LIS
- MTHAMOD LIS
- MTHERR SOL
- MTHASIN LIS
- MTHCDABS LIS
- MTHATAN LIS
- MTHATANH LIS
- MTHCDLOG LIS
- MTHBITOPS LIS
- MTHALOG LIS
- MTHJACKET MAR
- MTHDEF FOR
- MTHACOS LIS
- MTHANTNT LIS
- MTHCABS LIS
- MTHCDEXP LIS

The screenshots show various stages of utility execution, including prompts like "MTHABS LIS" and "MTHACOS LIS", and data listings. The overall appearance is that of a comprehensive manual or reference guide for VAX/VMS utilities.