

VVV		MMM		SSSSSSSSSSSS	LLL	IIIIIIIIII	BBBBBBBBBBBB
VVV		MMM		SSSSSSSSSSSS	LLL	IIIIIIIIII	BBBBBBBBBBBB
VVV		MMM		SSSSSSSSSSSS	LLL	IIIIIIIIII	BBBBBBBBBBBB
VVV		MMMMMM	MMMMMM	SSS	LLL	III	BBB
VVV		MMMMMM	MMMMMM	SSS	LLL	III	BBB
VVV		MMMMMM	MMMMMM	SSS	LLL	III	BBB
VVV		MMM	MMM	SSS	LLL	III	BBB
VVV		MMM	MMM	SSS	LLL	III	BBB
VVV		MMM	MMM	SSS	LLL	III	BBB
VVV		MMM	MMM	SSS	LLL	III	BBB
VVV		MMM	MMM	SSSSSSSSSS	LLL	III	BBB
VVV		MMM	MMM	SSSSSSSSSS	LLL	III	BBB
VVV		MMM	MMM	SSSSSSSSSS	LLL	III	BBB
VVV		MMM	MMM	SSS	LLL	III	BBB
VVV		MMM	MMM	SSS	LLL	III	BBB
VVV		MMM	MMM	SSS	LLL	III	BBB
VVV		MMM	MMM	SSS	LLL	III	BBB
VVV		MMM	MMM	SSS	LLL	III	BBB
VVV		MMM	MMM	SSS	LLL	III	BBB
VVV	VVV	MMM	MMM	SSSSSSSSSSSS	LLLLLLLLLLLLLLLL	IIIIIIIIII	BBBBBBBBBBBB
VVV	VVV	MMM	MMM	SSSSSSSSSSSS	LLLLLLLLLLLLLLLL	IIIIIIIIII	BBBBBBBBBBBB
VVV	VVV	MMM	MMM	SSSSSSSSSSSS	LLLLLLLLLLLLLLLL	IIIIIIIIII	BBBBBBBBBBBB

A
.....
.....

```

LL      IIIIII  BBBB8888  CCCCCCCC  LL      IIIIII  CCCCCCCC  AAAAAA  LL
LL      IIIIII  BBBB8888  CCCCCCCC  LL      IIIIII  CCCCCCCC  AAAAAA  LL
LL      II      BB      BB  CC      II      CC      AA      AA  LL
LL      II      BB      BB  CC      II      CC      AA      AA  LL
LL      II      BB      BB  CC      II      CC      AA      AA  LL
LL      II      BB      BB  CC      II      CC      AA      AA  LL
LL      II      BBBB8888  CC      II      CC      AA      AA  LL
LL      II      BBBB8888  CC      II      CC      AA      AA  LL
LL      II      BB      BB  CC      II      CC      AAAAAAAAAA  LL
LL      II      BB      BB  CC      II      CC      AAAAAAAAAA  LL
LL      II      BB      BB  CC      II      CC      AA      AA  LL
LLLLLLLLLLLL  IIIIII  BBBB8888  CCCCCCCC  LLLLLLLLLL  IIIIII  CCCCCCCC  AA      AA  LLLLLLLLLL  ....
LLLLLLLLLLLL  IIIIII  BBBB8888  CCCCCCCC  LLLLLLLLLL  IIIIII  CCCCCCCC  AA      AA  LLLLLLLLLL  ....

```

```

LL      IIIIII  SSSSSSSS
LL      IIIIII  SSSSSSSS
LL      II      SS
LL      II      SS
LL      II      SS
LL      II      SS
LL      II      SSSSSS
LL      II      SSSSSS
LL      II      SS
LL      II      SS
LL      II      SS
LLLLLLLLLLLL  IIIIII  SSSSSSSS
LLLLLLLLLLLL  IIIIII  SSSSSSSS

```

```
1 0001 0 %TITLE 'LIB$CLI_CALLBACK - CLI Callback Interface Procedures'  
2 0002 0 MODULE LIB$CLI_CALLBACK ( ! CLI Callback Procedures  
3 0003 0 IDENT = 'V04-000' ! File: LIBCLICAL.B32 Edit: STAN3009  
4 0004 0 ) =  
5 0005 1 BEGIN  
6 0006 1  
7 0007 1 *****  
8 0008 1 *  
9 0009 1 * COPYRIGHT (c) 1978, 1980, 1982, 1984 BY *  
10 0010 1 * DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS. *  
11 0011 1 * ALL RIGHTS RESERVED. *  
12 0012 1 *  
13 0013 1 * THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED *  
14 0014 1 * ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE *  
15 0015 1 * INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER *  
16 0016 1 * COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY *  
17 0017 1 * OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY *  
18 0018 1 * TRANSFERRED. *  
19 0019 1 *  
20 0020 1 * THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE *  
21 0021 1 * AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT *  
22 0022 1 * CORPORATION. *  
23 0023 1 *  
24 0024 1 * DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS *  
25 0025 1 * SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL. *  
26 0026 1 *  
27 0027 1 *  
28 0028 1 *****  
29 0029 1  
30 0030 1  
31 0031 1 **  
32 0032 1 FACILITY: General Utility Library  
33 0033 1  
34 0034 1 ABSTRACT:  
35 0035 1  
36 0036 1 This module contains callable procedures which allow user programs  
37 0037 1 to access the CLI callback facility. The procedures in this module  
38 0038 1 are:  
39 0039 1 LIB$GET_SYMBOL get value of a CLI symbol  
40 0040 1 LIB$SET_SYMBOL set value of a CLI symbol  
41 0041 1 LIB$DELETE_SYMBOL delete a CLI symbol  
42 0042 1 LIB$SET_LOGICAL set value of a supervisor mode  
43 0043 1 logical name  
44 0044 1 LIB$DELETE_LOGICAL delete a supervisor mode logical name  
45 0045 1 LIB$DISABLE_CTRL disable CLI out-of-band handling  
46 0046 1 LIB$ENABLE_CTRL re-enable CLI out-of-band handling  
47 0047 1  
48 0048 1 ENVIRONMENT: Runs only in USER mode - AST reentrant  
49 0049 1  
50 0050 1 AUTHOR: Ralph O. Weber, CREATION DATE: 19-AUG-1981  
51 0051 1  
52 0052 1 MODIFIED BY:  
53 0053 1  
54 0054 1 1-001 - Original. ROW 19-AUG-1981  
55 0055 1 1-002 - Change symbol name > 255 characters error to LIB$_INVSYMNAM.  
56 0056 1 ROW 3-DEC-1981  
57 0057 1 1-003 - Use CLISC_SRVDESC. Improve code. SBL 18-Dec-1981
```

- .. 58 0058 1 : 1-004 - Correct all references to LIB\$ANALYZE_SDESC. DGP 31-Dec-1981
- .. 59 0059 1 : 1-005 - Correct PSECT definitions. SBL 4-Jan-1981
- .. 60 0060 1 : 1-006 - Fix reference to CLIMSG.B32 to use SHRLIB\$, not LIB\$ TMH 14-Feb-1982
- .. 61 0061 1 : 1-007 - Allow symbol name to start with \$ or . SBL 3-Feb-1983
- .. 62 0062 1 : 1-008 - Use new callbacks to allow itemlists and attributes. STAN 26-Feb-1984.
- .. 63 0063 1 : 1-009 - Fix bug in way pass itemlist to callback. STAN 10-JUL-1984.
- .. 64 0064 1 : --

```
66 0065 1 %SBTTL 'Declarations'
67 0066 1
68 0067 1 | SWITCHES:
69 0068 1 |
70 0069 1 |
71 0070 1 SWITCHES ADDRESSING_MODE (EXTERNAL = GENERAL, NONEXTERNAL = WORD_RELATIVE);
72 0071 1 |
73 0072 1 |
74 0073 1 | LINKAGES:
75 0074 1 |
76 0075 1 |
77 0076 1 LINKAGE LIB$ANALYZE_SDESC JSB LINK = JSB (REGISTER=0; REGISTER=1,REGISTER=2):
78 0077 1     NOTUSED (3,4,5,6,7,8,9,10,11);
79 0078 1 |
80 0079 1 |
81 0080 1 | TABLE OF CONTENTS:
82 0081 1 |
83 0082 1 |
84 0083 1 FORWARD ROUTINE
85 0084 1     LIB$GET_SYMBOL,           ! get value of a CLI symbol
86 0085 1     LIB$SET_SYMBOL,           ! set value of a CLI symbol
87 0086 1     LIB$SET_LOGICAL,         ! set value of a supervisor-mode
88 0087 1     ! logical name
89 0088 1     LIB$DELETE_LOGICAL,       ! delete a supervisor-mode logical
90 0089 1     ! name
91 0090 1     LIB$DISABLE_CTRL,       ! disable CLI out-of-band recognition
92 0091 1     LIB$ENABLE_CTRL,       ! re-enable CLI out-of-band recognition
93 0092 1     LIB$$BUILD_SYMBOL_NAME; ! build a good symbol name
94 0093 1 |
95 0094 1 |
96 0095 1 | INCLUDE FILES:
97 0096 1 |
98 0097 1 |
99 0098 1 LIBRARY 'SYSSLIBRARY:STARLET';           ! System symbol definitions
100 0099 1 |
101 0100 1 REQUIRE 'SHRLIBS:CL!MSG';           ! CLIS_ symbols
102 0380 1 |
103 0381 1 |
104 0382 1 | MACROS:
105 0383 1 |
106 0384 1 |     MACRO MOVEDESC builds a S-type string descriptor at _TO
107 0385 1 |     which points to the same data area as that pointed to by
108 0386 1 |     the string descriptor at FROM. NB: since the _TO
109 0387 1 |     descriptor will be used only by SYSSCLI which ignores the
110 0388 1 |     DTYPE and CLASS fields, only the LENGTH and POINTER fields
111 0389 1 |     are built by MOVEDESC.
112 0390 1 |
113 M 0391 1 |     MACRO MOVEDESC (_FROM, _TO) =
114 M 0392 1 |     BEGIN
115 M 0393 1 |     REGISTER
116 M 0394 1 |     RET STATUS = 0;
117 M 0395 1 |     RET STATUS = LIB$ANALYZE_SDESC R2 ( _FROM;
118 M 0396 1 |     BLOCK [_TO, DSC$W_LENGTH; , BYTE],
119 M 0397 1 |     BLOCK [_TO, DSC$A_POINTER; , BYTE] );
120 M 0398 1 |     IF NOT .RET_STATUS
121 M 0399 1 |     THEN
122 M 0400 1 |     RETURN (.RET_STATUS);
```

```

123 0401 1      ENDX;
124 0402 1
125 0403 1
126 0404 1      EQUATED SYMBOLS:
127 0405 1
128 0406 1      NONE
129 0407 1
130 0408 1      FIELDS:
131 0409 1
132 0410 1      NONE
133 0411 1
134 0412 1      PSECTS:
135 0413 1
136 0414 1
137 0415 1 PSECT
138 0416 1      CODE = _LIB$CODE (READ, NOWRITE, EXECUTE, SHARE, PIC, ADDRESSING_MODE (WORD_RELATIVE)),
139 0417 1      PLIT = _LIB$CODE (READ, NOWRITE, EXECUTE, SHARE, PIC, ADDRESSING_MODE (WORD_RELATIVE)),
140 0418 1      OWN = _LIB$DATA (READ, WRITE, NOEXECUTE, NOSHARE, PIC, ADDRESSING_MODE (LONG_RELATIVE)),
141 0419 1      GLOBAL = _LIB$DATA (READ, WRITE, NOEXECUTE, NOSHARE, PIC, ADDRESSING_MODE (LONG_RELATIVE));
142 0420 1
143 0421 1
144 0422 1      OWN STORAGE:
145 0423 1
146 0424 1      NONE
147 0425 1
148 0426 1      EXTERNAL REFERENCES:
149 0427 1
150 0428 1
151 0429 1 EXTERNAL ROUTINE
152 0430 1      SYS$CLI, ! CLI Callback Routine
153 0431 1      LIB$ANALYZE_SDESC_R2 : LIB$ANALYZE_SDESC_JSB LINK,
154 0432 1      ! Analyze a string descriptor
155 0433 1      LIB$COPY_DXDX, ! Copy strings of any type
156 0434 1      ! to any type
157 0435 1      LIB$GET1_DD, ! Get a dynamic string
158 0436 1      LIB$FREE1_DD; ! Free a dynamic string
159 0437 1
160 0438 1 EXTERNAL
161 0439 1      LIB$AB_UPCASE; ! the string upcase table
162 0440 1
163 0441 1 EXTERNAL LITERAL ! Condition value symbols
164 0442 1      LIB$INVARG, ! Invalid argument
165 0443 1      LIB$WRONUMARG, ! Wrong number of arguments
166 0444 1      LIB$INVSYMNAM, ! Illegal symbol name
167 0445 1      LIB$NOSUCHSYM, ! No such symbol
168 0446 1      LIB$INSCLIMEM, ! Insufficient CLI memory
169 0447 1      LIB$AMBSYMDEF, ! Ambiguous symbol defined
170 0448 1      LIB$NOCLI, ! No CLI present
171 0449 1      LIB$UNECLIERR; ! Unexpected CLI error
  
```

```

173 0450 1 %SBTTL 'LIB$GET_SYMBOL - get value of a CLI symbol'
174 0451 1 GLC$AL ROUTINE [LIB$GET_SYMBOL ( get value of a CLI symbol
175 0452 1 SYMBOL: REF BLOCK [, BYTE], symbol string descriptor
176 0453 1 RETBUF: REF BLOCK [, BYTE], return value string descriptor
177 0454 1 RETLEN: REF VECTOR [, WORD], no. bytes returned (opt.)
178 0455 1 MODE: REF VECTOR [, LONG] symbol table searched (opt.)
179 0456 1 ) =
180 0457 1
181 0458 1 ++
182 0459 1 FUNCTIONAL DESCRIPTION:
183 0460 1
184 0461 1 LIB$GET_SYMBOL gets the value of the specified CLI symbol and returns
185 0462 1 it in the specified buffer. Before the actual search, however, the
186 0463 1 specified symbol name is upcased so that it will better match symbol
187 0464 1 names formed by the CLI. The local-symbol table is scanned first for
188 0465 1 the symbol, and if no matching symbol is found there, the global-
189 0466 1 symbol table is scanned. The length of the returned value and a mode
190 0467 1 value, indicating the table in which the symbol value was found, are
191 0468 1 optionally returned when parameters to receive them are supplied in
192 0469 1 the calling sequence.
193 0470 1
194 0471 1 Numeric values are automatically translated to decimal strings before
195 0472 1 being returned.
196 0473 1
197 0474 1 The optional mode value can be one of:
198 0475 1 LIB$K_CLI_LOCAL_SYM = 1 ==> Local symbol table name
199 0476 1 LIB$K_CLI_GLOBAL_SYM = 2 ==> Global symbol table name
200 0477 1 These symbols are defined in $LIBCLIDEF.
201 0478 1
202 0479 1 CALLING SEQUENCE:
203 0480 1
204 0481 1 ret_status.wlc.v = LIB$GET_SYMBOL (symbol.rt.dx, retbuf.wt.dx
205 0482 1 [, retlen.ww.r [, mode.wl.r]])
206 0483 1
207 0484 1 FORMAL PARAMETERS:
208 0485 1
209 0486 1 symbol.rt.dx - A string, passed by descriptor, which contains the
210 0487 1 symbol to be searched for. An upcased copy of this
211 0488 1 string will actually be used for the search.
212 0489 1
213 0490 1 retbuf.wt.dx - A string, passed by descriptor, into which the value
214 0491 1 of the symbol, if found, will be written.
215 0492 1
216 0493 1 retlen.ww.r - An optional word which, if present, will receive
217 0494 1 the length of the returned symbol value string.
218 0495 1
219 0496 1 mode.wl.r - An optional longword which, if present, will receive a
220 0497 1 value indicating table in which symbol was found.
221 0498 1 Possible values are:
222 0499 1 LIB$K_CLI_LOCAL_SYM ==> Local symbol table name
223 0500 1 LIB$K_CLI_GLOBAL_SYM ==> Global symbol table name
224 0501 1
225 0502 1 IMPLICIT INPUTS:
226 0503 1
227 0504 1 NONE
228 0505 1
229 0506 1 IMPLICIT OUTPUTS:

```

```

230 0507 1 |
231 0508 1 |     NONE
232 0509 1 |
233 0510 1 | COMPLETION STATUS: (or ROUTINE VALUE:)
234 0511 1 |
235 0512 1 |     SSS NORMAL      Normal successful completion
236 0513 1 |     LIB$_INVARG     Invalid argument
237 0514 1 |     LIB$_INVSYMNAM  Invalid symbol name
238 0515 1 |     LIB$_NOSUCHSYM  No such symbol found
239 0516 1 |     LIB$_INSCLIMEM  Insufficient CLI memory
240 0517 1 |     LIB$_NOCLI      No CLI present to perform function
241 0518 1 |     LIB$_UNECLIERR  Unexpected CLI Error
242 0519 1 |
243 0520 1 | SIDE EFFECTS:
244 0521 1 |
245 0522 1 |     WARNING:
246 0523 1 |     Although this procedure performs some checks on the validity of
247 0524 1 |     symbol names passed to it, some symbol name considered valid by
248 0525 1 |     this procedure will be considered invalid by DCL. Callers of this
249 0526 1 |     procedure are responsible for insuring that symbol names passed to
250 0527 1 |     this procedure contain only alphanumeric characters.
251 0528 1 |
252 0529 1 | --
253 0530 1 |
254 0531 2 | BEGIN
255 0532 2 |
256 0533 2 | BUILTIN
257 0534 2 |     NULLPARAMETER;
258 0535 2 |
259 0536 2 | LOCAL
260 0537 2 |     CLI_REQ_BLOCK : BLOCK [CLISC_SRVDESC, BYTE], ! A CLI request block
261 0538 2 |     DYN_STRING : BLOCK [8, BYTE], ! Descriptor for dynamic string
262 0539 2 |     RETURN_STATUS : BLOCK [4, BYTE]; ! A return status value
263 0540 2 |
264 0541 2 |
265 0542 2 |
266 0543 2 | !+
267 0544 2 | Initialize CLI Command request block.
268 0545 2 |
269 0546 2 |     CH$FILL (0, CLISC_SRVDESC, CLI_REQ_BLOCK);
270 0547 2 |     CLI_REQ_BLOCK [CLISB_RQTYPE] = CLISK CLISERV;
271 0548 2 |     CLI_REQ_BLOCK [CLISW_SERVCOD] = CLISK GETSYM;
272 0549 2 |     RETURN_STATUS = LIB$$BUILD_SYMBOL_NAME( .SYMBOL, DYN_STRING,
273 0550 2 |     CLI_REQ_BLOCK[CLISQ_NAMDESC] );
274 0551 2 |     IF NOT .RETURN_STATUS THEN RETURN .RETURN_STATUS;
275 0552 2 |
276 0553 2 | !+
277 0554 2 | Get CLI symbol value.
278 0555 2 |
279 0556 2 |     RETURN_STATUS = SYS$CLI (CLI_REQ_BLOCK);
280 0557 2 |
281 0558 2 | !+
282 0559 2 | Free dynamic string used for upcased symbol name.
283 0560 2 |
284 0561 2 |     LIB$FREE1_DD( DYN_STRING );
285 0562 2 |
286 0563 2 | !+

```



```

287 0564 2 ! Process returned symbol value and requested optional values.
288 0565 2 !-
289 0566 2 IF .RETURN_STATUS
290 0567 2 THEN
291 0568 2 BEGIN
292 0569 2 LOCAL
293 0570 2 CLI_DESC : REF BLOCK [8, BYTE];
294 0571 2 CLI_DESC = CLI_REQ_BLOCK [CLISQ_VALDESC];
295 0572 2 RETURN_STATUS = LIB$SCOPY DXDX (.CLI_DESC, .RETBUF);
296 0573 2 IF NOT NULLPARAMETER (3) AND .RETURN_STATUS
297 0574 2 THEN
298 0575 2 BEGIN
299 0576 2 LOCAL
300 0577 2 ADDRESS,
301 0578 2 LENGTH;
302 0579 2 LIB$ANALYZE_SDESC_R2 (.RETBUF; LENGTH, ADDRESS );
303 0580 2 RETLEN [0] = MINU (.LENGTH, .CLI_DESC [DSC$W_LENGTH]);
304 0581 2 END;
305 0582 2 IF NOT NULLPARAMETER (4)
306 0583 2 THEN
307 0584 2 MODE [0] = .CLI_REQ_BLOCK [CLISB_RQSTAT];
308 0585 2 END
309 0586 2 ELSE IF (.RETURN_STATUS [ST$V_FAC_NO] EQL CLIS_FACILITY)
310 0587 2 THEN
311 0588 2 RETURN_STATUS =
312 0589 2 BEGIN
313 0590 2 SELECTONE .RETURN_STATUS OF
314 0591 2 SET
315 0592 2 [CLIS_UNDSYM] : LIB$NOSUCHSYM;
316 0593 2 [CLIS_BUFOVF] : LIB$INSCLIMEM;
317 0594 2 [CLIS_INVREQTYP] : LIB$NOCLI;
318 0595 2 [OTHERWISE] : LIB$UNECLIERR;
319 0596 2 YES
320 0597 2 END;
321 0598 2
322 0599 2 RETURN (.RETURN_STATUS);
323 0600 2
324 0601 2 END;

```

! End of routine LIB\$GET_SYMBOL

.TITLE LIB\$CLI_CALLBACK LIB\$CLI_CALLBACK - CLI Callbac
k Interface Proce

.IDENT \V04-000\

.EXTRN SY\$CLI, LIB\$ANALYZE_SDESC_R2
.EXTRN LIB\$SCOPY_DXDX, LIB\$GET1_DD
.EXTRN LIB\$FREET_DD, LIB\$AB_UPCASE
.EXTRN LIB\$INVARG, LIB\$WRORUMARG
.EXTRN LIB\$INVSYMNAM, LIB\$NOSUCHSYM
.EXTRN LIB\$INSCLIMEM, LIB\$AMBSYMDEF
.EXTRN LIB\$NOCLI, LIB\$UNECLIERR

.PSECT _LIB\$CODE, NOWRT, SHR, PIC, 2

.ENTRY LIB\$GET_SYMBOL, Save R2,R3,R4,R5
MOVAB -92(SP), SP
MOVCS #0, (SP), #0, #84, CLI_REQ_BLOCK

: 0451
:
: 0546

0054 8F 00 SE A4 AE 003C 0000
6E 00 9E 00002
00 2C 00006

		08	AE	0000D			MOVB	#5, CLI_REQ_BLOCK	0547
	08	AE	05	90	0000F		MOVW	#10, CLI_REQ_BLOCK+1	0548
	09	AE	0A	80	00013		PUSHAB	CLI_REQ_BLOCK+4	0550
			0C	AE	9F	00017	PUSHAB	DYN_STRING	0549
			04	AE	9F	0001A	PUSHL	SYMBOL	0550
			04	AC	DD	0001D	CALLS	#3, LIB\$BUILD_SYMBOL_NAME	
0000V		CF	03	FB	00020		MOVL	R0, RETURN_STATUS	
		53	50	D0	00025		BLBC	RETURN_STATUS, 4\$	0551
		79	53	E9	00028		PUSHAB	CLI_REQ_BLOCK	0556
00000000G		00	08	AE	9F	0002B	CALLS	#1, SYS\$CLI	
		53	01	FB	0002E		MOVL	R0, RETURN_STATUS	
			50	DD	00035		PUSHL	SP	0561
00000000G		00	01	FB	0003A		CALLS	#1, LIB\$FREE1_DD	
		49	53	E9	0C041		BLBC	RETURN_STATUS, -3\$	0566
		54	14	AE	9E	00044	MOVAB	CLI_REQ_BLOCK+12, CLI_DESC	0571
			08	AC	DD	00048	PUSHL	RETBUF	0572
00000000G		00	54	DD	0004B		PUSHL	CLI_DESC	
		53	02	FB	0004D		CALLS	#2, LIB\$COPY_DXD	
		03	50	D0	00054		MOVL	R0, RETURN_STATUS	
			6C	91	00057		CMPB	(AP), #3	0573
			20	1F	0005A		BLSSU	2\$	
			0C	AC	D5	0005C	TSTL	12(AP)	
			1B	13	0005F		BEQL	2\$	
		18	53	E9	00061		BLBC	RETURN_STATUS, 2\$	
		50	08	AC	D0	00064	MOVL	RETBUF, R0	0579
51			00	16	00068		JSB	LIB\$ANALYZE_SDESC_R2	
64		10	00	ED	0006E		CMPZV	#0, #16, (CLI_DESC), R1	0580
			03	1E	00073		BGEQU	1\$	
		51	64	3C	00075		MOVZWL	(CLI_DESC), R1	
		0C	51	B0	00078	1\$:	MOVW	R1, @RETLEN	
		04	6C	91	0007C	2\$:	CMPB	(AP), #4	0582
			50	1F	0007F		BLSSU	8\$	
			10	AC	D5	00081	TSTL	16(AP)	
			4B	13	00084		BEQL	8\$	
		10	08	AE	9A	00086	MOVZBL	CLI_REQ_BLOCK+3, @MODE	0584
			44	11	00088		BRB	8\$	0566
03		53	10	ED	0008D	3\$:	CMPZV	#16, #12, RETURN_STATUS, #3	0586
			3D	12	00092		BNEQ	8\$	
		00038140	8F	D1	00094		CMP	RETURN_STATUS, #229696	0592
			09	12	0009B		BNEQ	5\$	
			53	D0	0009D		MOVL	#LIB\$NOSUCHSYM, RETURN_STATUS	
			2B	11	000A4	4\$:	BRB	8\$	
		00038018	8F	D1	000A6	5\$:	CMP	RETURN_STATUS, #229400	0593
			09	12	000AD		BNEQ	6\$	
			53	D0	000AF		MOVL	#LIB\$INSCLIMEM, RETURN_STATUS	
			19	11	000B6		BRB	8\$	
		00038822	8F	D1	000B8	6\$:	CMP	RETURN_STATUS, #231458	0594
			09	12	000BF		BNEQ	7\$	
			53	D0	000C1		MOVL	#LIB\$NOCLI, RETURN_STATUS	
			07	11	000C8		BRB	8\$	
			53	D0	000CA	7\$:	MOVL	#LIB\$UNECLIERR, RETURN_STATUS	0595
			50	D0	000D1	8\$:	MOVL	RETURN_STATUS, R0	0599
			04	000D4			RET		0601

; Routine Size: 213 bytes, Routine Base: _LIB\$CODE + 0000

LI
VO

LIBSCLI_CALLBAC LIBSCLI_CALLBACK - CLI Callback Interface Proce
V04-000 LIBSGET_SYMBOL - get value of a CLI symbol

M 8
16-Sep-1984 02:22:35
14-Sep-1984 13:27:47

VAX-11 Bliss-32 V4.0-742
[VMSLIB.SRC]LIBCLICAL.B32;1

Page 9
(3)

LI
VO

326
327
328
329
330
331
332
333
334
335
336
337
338
339
340
341
342
343
344
345
346
347
348
349
350
351
352
353
354
355
356
357
358
359
360
361
362
363
364
365
366
367
368
369
370
371
372
373
374
375
376
377
378
379
380
381
382

```

0602 1 %SBTTL 'LIB$SET_SYMBOL - set value of a CLI symbol'
0603 1 GLOBAL ROUTINE LIB$SET_SYMBOL (
0604 1     SYMBOL: REF BLOCK [, BYTE],
0605 1     VALUE: REF BLOCK [, BYTE],
0606 1     MODE: REF VECTOR [, LONG]
0607 1 ) =
0608 1
0609 1 ++
0610 1 FUNCTIONAL DESCRIPTION:
0611 1
0612 1     This routine defines a CLI symbol giving it the value specified by
0613 1     call parameter value. Before the actual definition, however, the
0614 1     specified symbol name is upcased so that it will better match symbol
0615 1     names formed by the CLI. An attempt to define a CLI symbol which
0616 1     already exists results in the value of that symbol being updated to
0617 1     the new value. The optional mode argument specifies a code
0618 1     (LIB$K_CLI_LOCAL_SYM or LIB$K_CLI_GLOBAL_SYM) which names the symbol
0619 1     table on which the define/update operation will be performed. If the
0620 1     mode argument is omitted, the the local symbol table is used.
0621 1
0622 1     The optional mode value can be one of:
0623 1         LIB$K_CLI_LOCAL_SYM = 1 ==> Local symbol table name
0624 1         LIB$K_CLI_GLOBAL_SYM = 2 ==> Global symbol table name
0625 1     These symbols are defined in $LIBCLIDEF.
0626 1
0627 1 CALLING SEQUENCE:
0628 1
0629 1     ret_status.wlc.v = LIB$SET_SYMBOL (symbol.rt.dx, value.rt.dx
0630 1                                     [, mode.rl.r])
0631 1
0632 1 FORMAL PARAMETERS:
0633 1
0634 1     symbol.rt.dx - A string, passed by descriptor, which contains the
0635 1                   symbol to be defined or modified. An upcased copy of
0636 1                   this string will actually be used for the define
0637 1                   or update operation.
0638 1
0639 1     value.rt.dx - A string, passed by descriptor, containing the value
0640 1                   to be given to the symbol.
0641 1
0642 1     mode.rl.r - An optional longword which, if present, contains a
0643 1                  value indicating into which table the symbol is to be
0644 1                  placed. If this parameter is omitted, the local
0645 1                  symbol table is used.
0646 1                  Possible values are:
0647 1                      LIB$K_CLI_LOCAL_SYM ==> Local symbol table name
0648 1                      LIB$K_CLI_GLOBAL_SYM ==> Global symbol table name
0649 1
0650 1 IMPLICIT INPUTS:
0651 1
0652 1     NONE
0653 1
0654 1 IMPLICIT OUTPUTS:
0655 1
0656 1     NONE
0657 1
0658 1 COMPLETION STATUS: (or ROUTINE VALUE:)

```

```

383 0659 1 |
384 0660 1 |      SSS NORMAL      Normal successful completion
385 0661 1 |      LIB$ INVARG     Invalid argument
386 0662 1 |      LIB$ INVSYMNAM  Invalid symbol name
387 0663 1 |      LIB$ INSCLIMEM  Insufficient CLI memory
388 0664 1 |      LIB$ AMBSYMDDEF Ambiguous CLI symbol defined
389 0665 1 |      LIB$ NOCLI      No CLI present to perform function
390 0666 1 |      LIB$ UNECLIERR  Unexpected CLI Error
391 0667 1 |
392 0668 1 | SIDE EFFECTS:
393 0669 1 |
394 0670 1 |      A CLI symbol is created or updated.
395 0671 1 |
396 0672 1 | WARNING:
397 0673 1 | Although this procedure performs some checks on the validity of
398 0674 1 | symbol names passed to it, some symbol name considered valid by
399 0675 1 | this procedure will be considered invalid by DCL. Callers of this
400 0676 1 | procedure are responsible for insuring that symbol names passed to
401 0677 1 | this procedure contain only alphanumeric characters. If this
402 0678 1 | procedure is used to create symbols whose names contain invalid
403 0679 1 | characters, deleting those symbols can be accomplished by logging
404 0680 1 | out and logging back in.
405 0681 1 |
406 0682 1 | --
407 0683 1 |
408 0684 2 | BEGIN
409 0685 2 |
410 0686 2 | BUILTIN
411 0687 2 |     NULLPARAMETER;
412 0688 2 |
413 0689 2 | LOCAL
414 0690 2 |     CLI_REQ_BLOCK : BLOCK [CLISQ_SRVDESC, BYTE], ! A CLI request block
415 0691 2 |     DYN_STRING : BLOCK [8, BYTE], ! Descriptor for dynamic string
416 0692 2 |     RETURN_STATUS : BLOCK [4, BYTE]; ! A return status value
417 0693 2 |
418 0694 2 |
419 0695 2 | !+
420 0696 2 | Initialize CLI Command request block.
421 0697 2 | --
422 0698 2 |     CH$FILL (0, CLISQ_SRVDESC, CLI_REQ_BLOCK);
423 0699 2 |     CLI_REQ_BLOCK [CLISB_RQTYPE] = CLISQ_CLISERV;
424 0700 3 | BEGIN
425 0701 3 |     LOCAL
426 0702 3 |         STRING : REF BLOCK [8, BYTE];
427 0703 3 |         STRING = .VALUE;
428 0704 3 |         IF .STRING [DSC$W_LENGTH] GTRU 255 THEN RETURN LIB$ INVARG;
429 0705 3 |     END;
430 0706 2 |     MOVEDESC ( .VALUE, CLI_REQ_BLOCK [CLISQ_VALDESC] );
431 0707 2 |     RETURN_STATUS = LIB$$BUILD_SYMBOL_NAME ( .SYMBOL, DYN_STRING,
432 0708 2 |         CLI_REQ_BLOCK [CLISQ_NAMDESC] );
433 0709 2 |     IF NOT .RETURN_STATUS THEN RETURN .RETURN_STATUS;
434 0710 2 |
435 0711 2 | !+
436 0712 2 | Setup service code indicating which symbol table.
437 0713 2 | --
438 0714 2 |     CLI_REQ_BLOCK [CLISW_SERVCOD] =
439 0715 3 |     BEGIN

```

```

440 0716 3 IF NOT .LPARAMETER (3)
441 0717 3 THEN
442 0718 3     CLISK_DEFLOCAL
443 0719 3 ELSE
444 0720 3     CASE .MODE [0] FROM LIB$K_CLI_LOCAL_SYM
445 0721 3         TO LIB$K_CLI_GLOBAL_SYM OF
446 0722 3     SET
447 0723 3     [LIB$K_CLI_LOCAL_SYM] : CLISK_DEFLOCAL;
448 0724 3     [LIB$K_CLI_GLOBAL_SYM] : CLISK_DEFGLOBAL;
449 0725 3     [OUTRANGE] : RETURN (LIB$_INVARG);
450 0726 3     TES
451 0727 3     END;
452 0728 3
453 0729 3 + Set CLI symbol.
454 0730 3 -
455 0731 3     RETURN_STATUS = SYS$CLI (CLI_REQ_BLOCK);
456 0732 3
457 0733 3 + Free dynamic string used for upcased symbol name.
458 0734 3 -
459 0735 3     LIB$FREE1_DD( DYN_STRING );
460 0736 3
461 0737 3 + Adjust error return status, if any.
462 0738 3 -
463 0739 3
464 0740 3     IF NOT .RETURN_STATUS AND (.RETURN_STATUS [ST$V_FAC_NO] EQL CLIS_FACILITY)
465 0741 3     THEN
466 0742 3     RETURN_STATUS =
467 0743 3     BEGIN
468 0744 3     SELECTONE .RETURN_STATUS OF
469 0745 3     BEGIN
470 0746 3     SET
471 0747 3     [CLIS_SYMOVF] : LIB$_INSCLIMEM;
472 0748 3     [CLIS_ABSYMD] : LIB$_AMBSYMD;
473 0749 3     [CLIS_INVREQTYP] : LIB$_NOCLI;
474 0750 3     [OTHERWISE] : LIB$_UNECLIERR;
475 0751 3     TES
476 0752 3     END;
477 0753 3
478 0754 3     RETURN (.RETURN_STATUS);
479 0755 3
480 0756 3 END;
481 0757 3
    ! End of routine LIB$SET_SYMBOL
    
```

0054	8F	00	5E	A4	AE	9E	00002	.ENTRY	LIB\$SET_SYMBOL, Save R2,R3,R4,R5	:	0603
			6E		00	2C	00006	MOVAB	-92(SP), SP	:	
				08	AE		0000D	MOVCS	#0, (SP), #0, #84, CLI_REQ_BLOCK	:	0698
		08	AE		05	90	0000F	MOVB	#5, CLI_REQ_BLOCK	:	0699
			50	08	AC	D0	00013	MOVL	VALUE, STRING	:	0703
		00FF	8F		60	B1	00017	CMPW	(STRING), #255	:	0704
					3D	1A	0001C	BGTRU	3\$:	
			50	08	AC	D0	0001E	MOVL	VALUE, R0	:	0706
				00000000G	00	16	00022	JSB	LIB\$ANALYZE_SDESC_R2	:	

14	AE		51	B0	00028	MOVW	R1, CLI_REQ_BLOCK+12		
18	AE		52	D0	0002C	MOVL	R2, CLI_REQ_BLOCK+16		
	01		50	E8	00030	BLBS	RET_STATUS, 1\$		
				04	00033	RET			
			0C	AE	9F	00034	1\$: PUSHAB	CLI_REQ_BLOCK+4	0708
			04	AE	9F	00037	PUSHAB	DYN_STRING	0707
			04	AC	DD	0003A	PUSHL	SYMBOL	0708
0000V	CF		03	FB	0003D	CALLS	#3, LIB\$\$BUILD_SYMBOL_NAME		
	52		50	D0	00042	MOVL	R0, RETURN_STATUS		
	7B		52	E9	00045	BLBC	RET_STATUS, 9\$	0709	
	03		6C	91	00048	CMPB	(AP), #3	0716	
			16	1F	0004B	BLSSU	4\$		
			0C	AC	D5	0004D	TSTL	12(AP)	
			11	13	00050	BEQL	4\$		
01	01		0C	BC	CF	00052	CASEL	@MODE, #1, #1	0720
	0011		000C	CF	00057	2\$: .WORD	4\$-2\$, -		
							5\$-2\$		
	50	00000000G	8F	D0	0005B	3\$: MOVL	#LIB\$_INVARG, R0	0725	
				04	00062	RET			
	50		02	D0	00063	4\$: MOVL	#2, R0	0720	
			03	11	00066	BRB	6\$		
	50		03	D0	00068	5\$: MOVL	#3, R0		
09	AE		50	B0	0006B	6\$: MOVW	R0, CLI_REQ_BLOCK+1	0715	
			08	AE	9F	0006F	PUSHAB	CLI_REQ_BLOCK	0732
00000000G	00		01	FB	00072	CALLS	#1, SYS\$CLI		
	52		50	D0	00079	MOVL	R0, RETURN_STATUS		
			5E	DD	0007C	PUSHL	SP	0737	
00000000G	00		01	FB	0007E	CALLS	#1, LIB\$FREE1_DD		
	44		52	E8	00085	BLBS	RET_STATUS, 11\$	0742	
03	52		10	ED	00088	CMPZV	#16, #T2, RETURN_STATUS, #3		
			3D	12	0008D	BNEQ	11\$		
00038138	8F		52	D1	0008F	CMP	RETURN_STATUS, #229688	0748	
			09	12	00096	BNEQ	7\$		
	52	00000000G	8F	D0	00098	MOVL	#LIB\$_INSCLIMEM, RETURN_STATUS		
			2B	11	0009F	BRB	11\$		
000381A0	8F		52	D1	000A1	7\$: Cmpl	RETURN_STATUS, #229792	0749	
			09	12	000A8	BNEQ	8\$		
	52	00000000G	8F	D0	000AA	MOVL	#LIB\$_AMBSYMDDEF, RETURN_STATUS		
			19	11	000B1	BRB	11\$		
00038822	8F		52	D1	000B3	8\$: Cmpl	RETURN_STATUS, #231458	0750	
			09	12	000BA	BNEQ	10\$		
	52	00000000G	8F	D0	000BC	MOVL	#LIB\$_NOCLI, RETURN_STATUS		
			07	11	000C3	9\$: BRB	11\$		
	52	00000000G	8F	D0	000C5	10\$: MOVL	#LIB\$_UNECLIERR, RETURN_STATUS	0751	
	50		52	D0	000CC	11\$: MOVL	RETURN_STATUS, R0	0755	
				04	000CF	RET		0757	

: Routine Size: 208 bytes, Routine Base: _LIB\$CODE + 00D5

```

483 0758 1 %SBTTL 'LIB$DELETE_SYMBOL - delete a CLI symbol'
484 0759 1 GLOBAL ROUTINE LIB$DELETE_SYMBOL ( : set value of a CLI symbol
485 0760 1     SYMBOL: REF BLOCK [, BYTE], : symbol string descriptor
486 0761 1     MODE: REF VECTOR [, LONG] : desired symbol table (opt.)
487 0762 1 ) =
488 0763 1
489 0764 1 ++
490 0765 1 FUNCTIONAL DESCRIPTION:
491 0766 1
492 0767 1     This routine deletes a CLI symbol. Before the actual deletion,
493 0768 1     however, the specified symbol name is upcased so that it will better
494 0769 1     match symbol names formed by the CLI. The optional mode argument
495 0770 1     specifies a code (LIB$K_CLI_LOCAL_SYM or LIB$K_CLI_GLOBAL_SYM) which
496 0771 1     names the symbol table on which the delete operation will be performed.
497 0772 1     If the mode argument is omitted, the the local symbol table is used.
498 0773 1
499 0774 1     The optional mode value can be one of:
500 0775 1         LIB$K_CLI_LOCAL_SYM = 1 ==> Local symbol table name
501 0776 1         LIB$K_CLI_GLOBAL_SYM = 2 ==> Global symbol table name
502 0777 1     These symbols are defined in $LIBCLIDEF.
503 0778 1
504 0779 1 CALLING SEQUENCE:
505 0780 1
506 0781 1     ret_status.wlc.v = LIB$DELETE_SYMBOL (symbol.rt.dx [, mode.rl.r])
507 0782 1
508 0783 1 FORMAL PARAMETERS:
509 0784 1
510 0785 1     symbol.rt.dx - A string, passed by descriptor, which contains the
511 0786 1                   symbol to be defined or modified. An upcased copy of
512 0787 1                   this string will actually be used for the deletion.
513 0788 1
514 0789 1     mode.rl.r - An optional longword which, if present, contains a
515 0790 1                   value indicating from which table the symbol is to be
516 0791 1                   deleted. If this parameter is omitted, the local
517 0792 1                   symbol table is used.
518 0793 1                   Possible values are:
519 0794 1                       LIB$K_CLI_LOCAL_SYM ==> Local symbol table name
520 0795 1                       LIB$K_CLI_GLOBAL_SYM ==> Global symbol table name
521 0796 1
522 0797 1 IMPLICIT INPUTS:
523 0798 1
524 0799 1     NONE
525 0800 1
526 0801 1 IMPLICIT OUTPUTS:
527 0802 1
528 0803 1     NONE
529 0804 1
530 0805 1 COMPLETION STATUS: (or ROUTINE VALUE:)
531 0806 1
532 0807 1     $$$ NORMAL      Normal successful completion
533 0808 1     LIB$INVARG      Invalid argument
534 0809 1     LIB$INVSYMNAM   Invalid symbol name
535 0810 1     LIB$NOSUCHSYM   No such symbol found
536 0811 1     LIB$NOCLI       No CLI present to perform function
537 0812 1     LIB$UNECLIERR   Unexpected CLI Error
538 0813 1
539 0814 1 SIDE EFFECTS:
    
```



```
540 0815 1 |
541 0816 1 | A CLI symbol is deleted.
542 0817 1 |
543 0818 1 | WARNING:
544 0819 1 | Although this procedure performs some checks on the validity of
545 0820 1 | symbol names passed to it, some symbol name considered valid by
546 0821 1 | this procedure will be considered invalid by DCL. Callers of this
547 0822 1 | procedure are responsible for insuring that symbol names passed to
548 0823 1 | this procedure contain only alphanumeric characters.
549 0824 1 |
550 0825 1 | --
551 0826 1 |
552 0827 2 | BEGIN
553 0828 2 |
554 0829 2 | BUILTIN
555 0830 2 | NULLPARAMETER;
556 0831 2 |
557 0832 2 | LOCAL
558 0833 2 | CLI_REQ_BLOCK : BLOCK [CLISC_SRVDESC, BYTE], ! A CLI request block
559 0834 2 | DYN_STRING : BLOCK [8, BYTE], ! Descriptor for dynamic string
560 0835 2 | RETURN_STATUS : BLOCK [4, BYTE]; ! A return status value
561 0836 2 |
562 0837 2 |
563 0838 2 | +
564 0839 2 | Initialize CLI Command request block.
565 0840 2 | -
566 0841 2 | CH$FILL (0, CLISC_SRVDESC, CLI_REQ_BLOCK);
567 0842 2 | RETURN_STATUS = LIB$$BUILD_SYMBOL_NAME( .SYMBOL, DYN_STRING,
568 0843 2 | CLI_REQ_BLOCK[CLISQ_NAMDESC] );
569 0844 2 | IF NOT .RETURN_STATUS THEN RETURN .RETURN_STATUS;
570 0845 2 | CLI_REQ_BLOCK [CLISB_RQTYPE] = CLISK_CLISERV;
571 0846 2 |
572 0847 2 | +
573 0848 2 | Setup service code indicating which symbol table.
574 0849 2 | -
575 0850 2 | CLI_REQ_BLOCK [CLISW_SERVCOD] =
576 0851 2 | BEGIN
577 0852 2 | IF NULLPARAMETER (2)
578 0853 2 | THEN
579 0854 2 | CLISK_DELELCL
580 0855 2 | ELSE
581 0856 2 | CASE .MODE [0] FROM LIB$K_CLI_LOCAL_SYM
582 0857 2 | TO LIB$K_CLI_GLOBAL_SYM OF
583 0858 2 | SET
584 0859 2 | [LIB$K_CLI_LOCAL_SYM] : CLISK_DELELCL;
585 0860 2 | [LIB$K_CLI_GLOBAL_SYM] : CLISK_DELEGLB;
586 0861 2 | [OUTRANGE] : RETURN (LIB$_INVARG);
587 0862 2 |
588 0863 2 | TES
589 0864 2 | END;
590 0865 2 | +
591 0866 2 | Delete CLI symbol.
592 0867 2 | -
593 0868 2 | RETURN_STATUS = SYSSCLI (CLI_REQ_BLOCK);
594 0869 2 |
595 0870 2 | +
596 0871 2 | Free dynamic string used for upcased symbol name.
```

```

597 0872 2 !-
598 0873 2 LIB$FREE1_DD( DYN_STRING );
599 0874 2
600 0875 2 !+
601 0876 2 Adjust error return status, if any.
602 0877 2
603 0878 2 IF NOT .RETURN_STATUS AND (.RETURN_STATUS [ST$V_FAC_NO] EQL CLI$FACILITY)
604 0879 2 THEN
605 0880 2     RETURN_STATUS =
606 0881 2     BEGIN
607 0882 2         SELECTONE .RETURN_STATUS OF
608 0883 2         SET
609 0884 2         [CLI$UNDSYM] : LIB$NOSUCHSYM;
610 0885 2         [CLI$INVREQTYP] : LIB$NOCLI;
611 0886 2         [OTHERWISE] : LIB$UNECLIERR;
612 0887 2         TES
613 0888 2         END;
614 0889 2
615 0890 2 RETURN (.RETURN_STATUS);
616 0891 2
617 0892 2 END;
    
```

! End of routine LIB\$DELETE_SYMBOL

				003C 00000	.ENTRY LIB\$DELETE_SYMBOL, Save R2,R3,R4,R5	: 0759
		SE	A4	AE 9E 00002	MOVAB -92(SP), SP	
0054	8F	6E		00 2C 00006	MOVCS #0, (SP), #0, #84, CLI_REQ_BLOCK	: 0841
				08 AE 0000D		
				0C AE 9F 0000F	PUSHAB CLI_REQ_BLOCK+4	: 0843
				04 AE 9F 00012	PUSHAB DYN_STRING	: 0842
				04 AC DD 00015	PUSHL SYMBOL	: 0843
		0000V		03 FB 00018	CALLS #3, LIB\$BUILD_SYMBOL_NAME	
		52		50 D0 0001D	MOVL R0, RETURN_STATUS	
		76		52 E9 00020	BLBC RETURN_STATUS, 7\$: 0844
		08		05 90 00023	MOVB #5, CLI_REQ_BLOCK	: 0845
		02		6C 91 00027	CMPB (AP), #2	: 0852
				16 1F 0002A	BLSSU 2\$	
			08	AC D5 0002C	TSTL 8(AP)	
				11 13 0002F	BEQL 2\$	
		01		08 BC CF 00031	CASEL @MODE, #1, #1	: 0856
		0011		000C 00036 1\$:	.WORD 2\$-1\$,-	
					3\$-1\$	
		50	00000000G	8F D0 0003A	MOVL #LIB\$INVARG, R0	: 0861
				04 00041	RET	
		50		08 D0 00042 2\$:	MOVL #11, R0	: 0856
				03 11 00045	BRG 4\$	
		50		0C D0 00047 3\$:	MOVL #12, R0	
		09		50 B0 0004A 4\$:	MOVW R0, CLI_REQ_BLOCK+1	: 0851
			08	AE 9F 0004E	PUSHAB CLI_REQ_BLOCK	: 0868
		00000000G		01 FB 00051	CALLS #1, SYS\$CLI	
		52		50 D0 00058	MOVL R0, RETURN_STATUS	
				5E DD 0005B	PUSHL SP	: 0873
		00000000G		01 FB 0005D	CALLS #1, LIB\$FREE1_DD	
		32		52 E8 00064	BLBS RETURN_STATUS, -7\$: 0878
03		52		10 ED 00067	CMPZV #16, #12, RETURN_STATUS, #3	

00038140	8F	28	12	0006C	BNEQ	7\$:	
		52	D1	0006E	CMPL	RETURN_STATUS, #229696	:	0884
		09	12	00075	BNEQ	5\$:	
	52 00000000G	8F	D0	00077	MOVL	#LIB\$_NOSUCHSYM, RETURN_STATUS	:	
		19	11	0007E	BRB	7\$:	
00038822	8F	52	D1	00080	CMPL	RETURN_STATUS, #231458	:	0885
		09	12	00087	BNEQ	6\$:	
	52 00000000G	8F	D0	00089	MOVL	#LIB\$_NOCLI, RETURN_STATUS	:	
		07	11	00090	BRB	7\$:	
	52 00000000G	8F	D0	00092	MOVL	#LIB\$_UNECLIERR, RETURN_STATUS	:	0886
	50	52	D0	00099	MOVL	RETURN_STATUS, R0	:	0890
			04	0009C	RET		:	0892

; Routine Size: 157 bytes, Routine Base: _LIB\$CODE + 01A5

```
0893 1 %SBTTL 'LIB$SET LOGICAL - set supervisor mode logical name'
0894 1 GLOBAL ROUTINE [LIB$SET LOGICAL ( set supervisor mode logical name
0895 1 LOGNAME : REF $BBLOCK, : logical name string descriptor
0896 1 VALUE : REF $BBLOCK, : equivalence name string descriptor
0897 1 TABNAM : REF $BBLOCK, : logical name table
0898 1 ATTR : REF $BBLOCK[4], : attributes
0899 1 ITMLST : REF $BBLOCK : Address of itemlist
0900 1 ) =
```

```
0901 1
0902 1 ++
0903 1 FUNCTIONAL DESCRIPTION:
```

```
0904 1
0905 1 This routine provides a method by which a non-privileged program can
0906 1 create/modify supervisor mode logical names. The logical name given
0907 1 by logname is created or modified to have the equivalence name
0908 1 specified by value.
0909 1 The user may specify attributes for the logical name and may
0910 1 specify which logical name table is to be used.
0911 1 Instead of specifying a single equivalence string, via VALUE,
0912 1 the caller may specify an item list to give multiple equivalence strings.
```

```
0913 1
0914 1 The STRNLNM system service can be used to obtain the value of
0915 1 supervisor mode logical names. The routine is equivalent to the ASSIGN
0916 1 or DEFINE DCL command.
```

```
0917 1
0918 1 CALLING SEQUENCE:
```

```
0919 1
0920 1 ret_status.wlc.v = LIB$SET_LOGICAL (
0921 1 logname.rt.dx
0922 1 [, value.rt.dx]
0923 1 [, tabnam.rt.dx]
0924 1 [, attr.rlu.r]
0925 1 [, itmlst.ra.r])
```

```
0926 1
0927 1 FORMAL PARAMETERS:
```

```
0928 1
0929 1 logname.rt.dx - A string, passed by descriptor, which contains the
0930 1 supervisor mode logical name to be created or modified.
0931 1
0932 1 value.rt.dx - A string, passed by descriptor, specifying the value
0933 1 to be given to the supervisor mode logical name.
0934 1 If omitted, an itemlist must be present to specify the
0935 1 value(s) of the logical name.
0936 1
0937 1 tabnam.rt.dx - Name of the table in which to create the logical name.
0938 1 If omitted, the LNMS$PROCESS table is used.
0939 1
0940 1 attr.rlu.r - Logical name attributes. See the description of
0941 1 the system service $CRELNM for more details.
0942 1 Currently available attributes are
0943 1 LNMSM CONFINED and LNMSM NO ALIAS.
0944 1 If omitted, no special attributes are established.
0945 1 However, if no table or itemlist is specified,
0946 1 then the attribute LNMSM_CRELOG is defaulted in.
0947 1
0948 1 If no itemlist is specified, then the translation
0949 1 attributes LNMSM_CONCEALED and LNMSM_TERMINAL may
```

```
676 0950 1 | also be specified here. They apply to the
677 0951 1 | equivalence string string specified by the VALUE
678 0952 1 | parameter.
679 0953 1 |
680 0954 1 | If an itemlist is specified, then the itemlist will
681 0955 1 | contain the translation attributes for each
682 0956 1 | equivalence string in the itemlist.
683 0957 1 |
684 0958 1 | itmlst.ra.r The address of an item list describing the
685 0959 1 | equivalence name(s) for this logical name.
686 0960 1 | See the description of the $CRELNM system service
687 0961 1 | for the format and meaning of the item list.
688 0962 1 |
689 0963 1 | If omitted, the logical name will have just one
690 0964 1 | value, as specified by the VALUE parameter.
691 0965 1 |
692 0966 1 | Either VALUE or ITMLST must be specified.
693 0967 1 | If neither are specified, the LIB$_INVARG
694 0968 1 | error is produced.
695 0969 1 |
696 0970 1 | If both are specified, then the VALUE parameter
697 0971 1 | is ignored. In this case, logical name
698 0972 1 | attributes are permitted, but translation
699 0973 1 | attributes specified in the ATTR parameter
700 0974 1 | will be ignored (since these will appear in the
701 0975 1 | itemlist).
702 0976 1 |
703 0977 1 | The ITMLST parameter is only needed in the case where
704 0978 1 | you wish to create multiple equivalence strings
705 0979 1 | for a single logical name (i.e. a search list).
706 0980 1 |
707 0981 1 | IMPLICIT INPUTS:
708 0982 1 |
709 0983 1 | It is assumed that the logical name table specified already exists.
710 0984 1 |
711 0985 1 | IMPLICIT OUTPUTS:
712 0986 1 |
713 0987 1 | NONE
714 0988 1 |
715 0989 1 | COMPLETION STATUS: (or ROUTINE VALUE:)
716 0990 1 |
717 0991 1 | S$$_NORMAL Normal successful completion
718 0992 1 | S$$_SUPERSEDE Previous logical name replaced (success)
719 0993 1 | S$$_ACCVIO logname or value cannot be read
720 0994 1 | S$$_IVLOGNAM logname or value contains more than 255 characters
721 0995 1 | S$$_BADPARAM One or more arguments had a bad value.
722 0996 1 | For example, an unknown bit was specified in
723 0997 1 | the attributes parameter.
724 0998 1 | Note that if an item list is specified,
725 0999 1 | then translation attributes (if any) must
726 1000 1 | appear in the item list and may not appear
727 1001 1 | in the ATTR parameter. Only logical name
728 1002 1 | attributes may appear in the ATTR parameter
729 1003 1 | in that case.
730 1004 1 | S$$_NOLOGNAM The specified logical name table does not exist.
731 1005 1 | S$$_NOPRIV The caller lacks the necessary privileges
732 1006 1 | to create the logical name.
```

```

733 1007 1 | SSS_TOOMANYLNAM Logical name translation of the table name exceeded
734 1008 1 | the allowable depth (10 translations).
735 1009 1 | SSS_DUPLNAM Attempt to create a logical name that conflicts
736 1010 1 | with a logical name created at a higher access mode
737 1011 1 | and which had the LN$M_NO_ALIAS attribute.
738 1012 1 | SSS_EXLNMQOTA Exceeded logical name space quota.
739 1013 1 | SSS_INSMEM Insufficient dynamic memory.
740 1014 1 | LIB$_INVARG Invalid argument. Neither a VALUE nor an ITMLST
741 1015 1 | was specified.
742 1016 1 | Or LOGNAME was omitted.
743 1017 1 | LIB$_NOCLI No CLI present to perform function
744 1018 1 | LIB$_UNECLIERR Unexpected CLI Error
745 1019 1 | LIB$_WRONUMARG Wrong number of arguments. Either fewer than two
746 1020 1 | arguments or more than 5 arguments were specified.
747 1021 1 |
748 1022 1 | SIDE EFFECTS:
749 1023 1 |
750 1024 1 | A supervisor mode logical name is created or modified.
751 1025 1 |
752 1026 1 | --
753 1027 1 |
754 1028 2 | BEGIN
755 1029 2 |
756 1030 2 | BUILTIN
757 1031 2 |
758 1032 2 | ACTUALCOUNT,
759 1033 2 | NULLPARAMETER;
760 1034 2 |
761 1035 2 | LOCAL
762 1036 2 |
763 1037 2 | CLI_REQ_BLOCK : BLOCK [CLISC_SRVDESC, BYTE], ! A CLI request block
764 1038 2 | RETURN STATUS : BLOCK [4, BYTE],
765 1039 2 | TRANSLATION_ATTRIBUTES,
766 1040 2 | LOGICAL_NAME_ATTRIBUTES,
767 1041 2 | SPECIAL_ITEM_LIST : VECTOR [7]; ! Special item list
768 1042 2 |
769 1043 2 | +
770 1044 2 | Check for proper number of arguments.
771 1045 2 | -
772 1046 2 |
773 1047 2 | IF ACTUALCOUNT() LEQU 1
774 1048 2 | OR ACTUALCOUNT() GTRU 5
775 1049 2 | THEN
776 1050 2 | RETURN LIB$_WRONUMARG;
777 1051 2 |
778 1052 2 | +
779 1053 2 | Initialize CLI Command request block accounting for the differences
780 1054 2 | between creating/modifying a logical name and deleting one.
781 1055 2 | -
782 1056 2 |
783 1057 2 | CH$FILL (0, CLISC_SRVDESC, CLI_REQ_BLOCK);
784 1058 2 | CLI_REQ_BLOCK [CLISB_RQTYPE] = CLISK_CLISERV;
785 1059 2 | CLI_REQ_BLOCK [CLISW_SERVCOD] = CLISK_CREALOG;
786 1060 2 |
787 1061 2 | +
788 1062 2 | Move in the logical name, the equivalence string, and the logical
789 1063 2 | name table name.

```

```
790      1064 2 ! Give an error if the logical name is omitted.
791      1065 2 ! Give an error if neither VALUE nor ITMLST is supplied.
792      1066 2 !
793      1067 2
794      1068 2 IF .LOGNAME EQL 0
795      1069 2 THEN
796      1070 2     RETURN LIB$INVARG;
797      1071 2
798      1072 2 MOVEDESC ( .LOGNAME, CLI_REQ_BLOCK [CLISQ_NAMDESC] );
799      1073 2
800      1074 2 IF NULLPARAMETER(VALUE) AND NULLPARAMETER(ITMLST)
801      1075 2 THEN
802      1076 2     RETURN LIB$INVARG;
803      1077 2
804      1078 2 IF NOT NULLPARAMETER(VALUE)
805      1079 2 THEN
806      1080 2     MOVEDESC ( .VALUE, CLI_REQ_BLOCK [CLISQ_VALDESC] );
807      1081 2
808      1082 2 !+
809      1083 2 ! NOTE:
810      1084 2 ! If both VALDESC and ITMLST are specified, DCL will ignore VALUE.
811      1085 2 !
812      1086 2 !
813      1087 2 !+
814      1088 2 ! Move in the table name if present.
815      1089 2 ! If not present, DCL defaults to LNMSPROCESS.
816      1090 2 !
817      1091 2 !
818      1092 2 IF NOT NULLPARAMETER(TABNAM)
819      1093 2 THEN
820      1094 2     MOVEDESC ( .TABNAM, CLI_REQ_BLOCK [CLISQ_TABDESC] );
821      1095 2
822      1096 2 !+
823      1097 2 ! Move in the address of the item list (if present).
824      1098 2 ! If not present, DCL will create an itemlist from CLISQ_VALDESC.
825      1099 2 !
826      1100 2 !
827      1101 2 IF NOT NULLPARAMETER(ITMLST)
828      1102 2 THEN
829      1103 2     CLI_REQ_BLOCK [CLISL_ITMLST] = .ITMLST;
830      1104 2
831      1105 2 !+
832      1106 2 ! Move in the address of the attributes (if present).
833      1107 2 !
834      1108 2 !
835      1109 2 IF NOT NULLPARAMETER(ATTR)
836      1110 2 THEN
837      1111 2     CLI_REQ_BLOCK [CLISL_ATTR] = .ATTR;
838      1112 2
839      1113 2 !+
840      1114 2 ! NOTE:
841      1115 2 ! If CLISQ_TABDESC, CLISL_ITMLST, and CLISL_ATTR are all 0,
842      1116 2 ! then DCL defaults in the attribute LNMSM_CRELOG, i.e.
843      1117 2 ! the call back looks like a V3 call back.
844      1118 2 !
845      1119 2 !
846      1120 2 !+
```

```
847 1121 2 | If the caller has specified translation attributes in ATTR
848 1122 2 | (as opposed to just logical name attributes), this is normally
849 1123 2 | an error. That is because translation attributes should go in
850 1124 2 | the itemlist. However, as a convenience to RTL users who find
851 1125 2 | it hard to build itemlists, we allow translation attributes to
852 1126 2 | occur if no itemlist is specified. In that case, we have to go
853 1127 2 | through the trouble of building an itemlist for him.
854 1128 2 |
855 1129 2 |
856 1130 2 | IF NULLPARAMETER(ITMLST) AND NOT NULLPARAMETER(ATTR)
857 1131 2 | THEN
858 1132 2 | BEGIN ! Check for translation attributes
859 1133 2 | BIND ATTR_VECTOR = .ATTR : VECTOR[4,BYTE],
860 1134 2 | ATTR_VALUE = .ATTR : LONG;
861 1135 2 |
862 1136 2 |
863 1137 2 | +
864 1138 2 | The first byte of attributes are logical name attributes.
865 1139 2 | The second byte of attributes are translation attributes.
866 1140 2 | The other 2 bytes are reserved for VMS use.
867 1141 2 |
868 1142 2 | IF .ATTR_VECTOR[1] NEQ 0
869 1143 2 | THEN
870 1144 4 | BEGIN ! Build special itemlist
871 1145 4 | BIND EQUIV_STRING_DESC = CLI_REQ_BLOCK[CLISQ_VALDESC] : $BLOCK;
872 1146 4 |
873 1147 4 | +
874 1148 4 | Create translation attributes from the specified attributes.
875 1149 4 |
876 1150 4 |
877 1151 4 | TRANSLATION_ATTRIBUTES=.ATTR_VALUE AND %X'FF00';
878 1152 4 |
879 1153 4 | +
880 1154 4 | Create logical name attributes from the specified attributes.
881 1155 4 |
882 1156 4 |
883 1157 4 | LOGICAL_NAME_ATTRIBUTES=.ATTR_VALUE AND %X'FF';
884 1158 4 |
885 1159 4 | SPECIAL_ITEM_LIST[0]=LNMS_ATTRIBUTES^16+4;
886 1160 4 | SPECIAL_ITEM_LIST[1]=TRANSLATION_ATTRIBUTES;
887 1161 4 | SPECIAL_ITEM_LIST[2]=0;
888 1162 4 | SPECIAL_ITEM_LIST[3]=LNMS_STRING^16+.EQUIV_STRING_DESC[DSC$W_LENGTH];
889 1163 4 | SPECIAL_ITEM_LIST[4]=.EQUIV_STRING_DESC[DSC$A_POINTER];
890 1164 4 | SPECIAL_ITEM_LIST[5]=0;
891 1165 4 | SPECIAL_ITEM_LIST[6]=0; ! no more entries
892 1166 4 |
893 1167 4 | +
894 1168 4 | Store specially revised attributes and item list in
895 1169 4 | the request block.
896 1170 4 |
897 1171 4 |
898 1172 4 | CLI_REQ_BLOCK[CLISL_ATTR]=LOGICAL_NAME_ATTRIBUTES;
899 1173 4 | CLI_REQ_BLOCK[CLISL_ITMLST]=SPECIAL_ITEM_LIST
900 1174 4 |
901 1175 4 | END ! Build special itemlist
902 1176 4 |
903 1177 2 | END; ! Check for translation attributes
```



```

904 1178
905 1179
906 1180
907 1181
908 1182
909 1183
910 1184
911 1185
912 1186
913 1187
914 1188
915 1189
916 1190
917 1191
918 1192
919 1193
920 1194
921 1195
922 1196
923 1197
924 1198
925 1199
926 1200
  
```

```

+ Create or modify the supervisor mode logical name.
- RETURN_STATUS = SYSSCLI (CLI_REQ_BLOCK);

+ Adjust error return status, if any.
- IF NOT .RETURN_STATUS AND (.RETURN_STATUS [STSSV_FAC_NO] EQL CLIS_FACILITY)
  THEN
    RETURN_STATUS =
    BEGIN
      SELECTONE .RETURN_STATUS OF
      SET
      [CLIS_INVREQTYP] : LIB$NOCLI;
      [OTHERWISE] : LIB$UNECLIERR;
      TES
    END;

  RETURN .RETURN_STATUS
END;
  
```

! End of LIB\$SET_LOGICAL

				007C 00000	.ENTRY LIB\$SET_LOGICAL, Save R2,R3,R4,R5,R6	0894
	56	00000000G	00	9E 00002	MOVAB LIB_NALYZE_SDESC_R2, R6	
	5E	88	AE	9E 00009	MOVAB -120(SP), SP	
	01		6C	91 0000D	CMPB (AP), #1	1047
			05	1B 00010	BLEQU 1\$	
	05		6C	91 00012	CMPB (AP), #5	1048
			08	1B 00015	BLEQU 2\$	
	50	00000000G	8F	D0 00017 1\$:	MOVL #LIB\$WRONUMARG, R0	1050
				04 0001E	RET	
0054	8F	00	6E	2C 0001F 2\$:	MOVCS #0, (SP), #0, #84, CLI_REQ_BLOCK	1057
				AE 00026		
	24		AE	05 90 00028	MOVW #5, CLI_REQ_BLOCK	1058
	25		AE	06 B0 0002C	MOVW #6, CLI_REQ_BLOCK+1	1059
			04	AC D5 00030	TSTL LOGNAME	1068
			25	13 00033	BEQL 4\$	
	50		AC	D0 00035	MOVL LOGNAME, R0	1072
			06	16 00039	JSB LIB\$ANALYZE_SDESC_R2	
	28		AE	51 B0 0003B	MOVW R1, CLI_REQ_BLOCK+4	
	2C		AE	52 D0 0003F	MOVL R2, CLI_REQ_BLOCK+8	
			4F	50 E9 00043	BLBC RET STATUS, 7\$	
			02	6C 91 00046	CMPB (AP), #2	1074
			05	1F 00049	BLSSU 3\$	
			08	AC D5 0004B	TSTL 8(AP)	
			12	12 0004E	BNEQ 5\$	
	05		6C	91 00050 3\$:	CMPB (AP), #5	
			05	1F 00053	BLSSU 4\$	
			14	AC D5 00055	TSTL 20(AP)	
			08	12 00058	BNEQ 5\$	
	50	00000000G	8F	D0 0005A 4\$:	MOVL #LIB\$INVARG, R0	1076

				04	00061			RET				
		02		6C	91	00062	5\$:	CMPB	(AP), #2			1078
				16	1F	00065		BLSSU	6\$			
			08	AC	D5	00067		TSTL	8(AP)			
				11	13	0006A		BEQL	6\$			
		50		08	AC	D0	0006C	MOVL	VALUE, R0			1080
				66	16	00070		JSB	LIB\$ANALYZE_SDESC_R2			
30	AE			51	B0	00072		MOVW	R1, CLI_REQ_BLOCK+12			
34	AE			52	D0	00076		MOVL	R2, CLI_REQ_BLOCK+16			
	18			50	E9	0007A		BLBC	RET STATUS, -7\$			
	03			6C	91	0007D	6\$:	CMPB	(APT, #3			1092
				17	1F	00080		BLSSU	8\$			
			0C	AC	D5	00082		TSTL	12(AP)			
				12	13	00085		BEQL	8\$			
		50		0C	AC	D0	00087	MOVL	TABNAM, R0			1094
				66	16	0008B		JSB	LIB\$ANALYZE_SDESC_R2			
38	AE			51	B0	0008D		MOVW	R1, CLI_REQ_BLOCK+20			
3C	AE			52	D0	00091		MOVL	R2, CLI_REQ_BLOCK+24			
	01			50	E8	00095	7\$:	BLBS	RET STATUS, -8\$			
					04	00098		RET				
	05			6C	91	00099	8\$:	CMPB	(AP), #5			1101
				0A	1F	0009C		BLSSU	9\$			
			14	AC	D5	0009E		TSTL	20(AP)			
				05	13	000A1		BEQL	9\$			
40	AE		14	AC	D0	000A3		MOVL	ITMLST, CLI_REQ_BLOCK+28			1103
	04			6C	91	000A8	9\$:	CMPB	(AP), #4			1109
				0A	1F	000AB		BLSSU	10\$			
			10	AC	D5	000AD		TSTL	16(AP)			
				05	13	000B0		BEQL	10\$			
44	AE		10	AC	D0	000B2		MOVL	ATTR, CLI_REQ_BLOCK+32			1111
	05			6C	91	000B7	10\$:	CMPB	(AP), #5			1130
				05	1F	000BA		BLSSU	11\$			
			14	AC	D5	000BC		TSTL	20(AP)			
				4B	12	000BF		BNEQ	12\$			
	04			6C	91	000C1	11\$:	CMPB	(AP), #4			
				46	1F	000C4		BLSSU	12\$			
			10	AC	D5	000C6		TSTL	16(AP)			
				41	13	000C9		BEQL	12\$			
	50		10	AC	D0	000CB		MOVL	ATTR, R0			1133
			01	A0	95	000CF		TSTB	1(R0)			1142
				38	13	000D2		BEQL	12\$			
6E	10	BC	FFFF00FF	8F	CB	000D4		BICL3	#-65281, @ATTR, TRANSLATION_ATTRIBUTES			1151
	04	AE		10	BC	9A	000DD	MOVZBL	@ATTR, LOGICAL_NAME_ATTRIBUTES			1157
	08	AE	00030004	8F	D0	000E2		MOVL	#196612, SPECIAL_ITEM_LIST			1159
	0C	AE		6E	9E	000EA		MOVAB	TRANSLATION_ATTRIBUTES, SPECIAL_ITEM_LIST+4			1160
				10	AE	D4	000EE	CLRL	SPECIAL_ITEM_LIST+8			1161
	14	AE		30	AE	3C	000F1	MOVZWL	EQUIV_STRING_DESC, SPECIAL_ITEM_LIST+12			1162
	16	AE		02	A0	000F6		ADDW2	#2, SPECIAL_ITEM_LIST+12			
	18	AE		34	AE	D0	000FA	MOVL	EQUIV_STRING_DESC+4, SPECIAL_ITEM_LIST+16			1163
				1C	AE	7C	000FF	CLRQ	SPECIAL_ITEM_LIST+20			1164
	44	AE		04	AE	9E	00102	MOVAB	LOGICAL_NAME_ATTRIBUTES, CLI_REQ_BLOCK+32			1172
	40	AE		08	AE	9E	00107	MOVAB	SPECIAL_ITEM_LIST, CLI_REQ_BLOCK+28			1173
				24	AE	9F	0010C	PUSHAB	CLI_REQ_BLOCK			1182
	00000000G	00		01	FB	0010F		CALLS	#1, SY\$CLI			
03		50		50	E8	00116		BLBS	RETURN STATUS, 14\$			1187
				10	ED	00119		CMPZV	#16, #T2, RETURN_STATUS, #3			
				18	12	0011E		BNEQ	14\$			


```

928 1201 1 %SBTTL 'LIB$DELETE LOGICAL - delete supervisor mode logical name'
929 1202 1 GLOBAL ROUTINE LIB$DELETE LOGICAL (      ! delete supervisor mode logical name
930 1203 1      LOGNAME : REF $BBLOCK,      ! logical name string descriptor
931 1204 1      TABNAM  : REF $BBLOCK      ! table name
932 1205 1      ) =
933 1206 1
934 1207 1 ++
935 1208 1 FUNCTIONAL DESCRIPTION:
936 1209 1
937 1210 1 This routine provides a method by which a non-privileged program can
938 1211 1 delete a supervisor mode logical name. The logical name given by
939 1212 1 logname is deleted from the specified or implied logical name table.
940 1213 1
941 1214 1 The $STRNLOG system service can be used to obtain the value of
942 1215 1 supervisor mode logical names. The routine is equivalent to the
943 1216 1 DEASSIGN DCL command.
944 1217 1
945 1218 1 CALLING SEQUENCE:
946 1219 1
947 1220 1      ret_status.wlc.v = LIB$DELETE_LOGICAL (logname.rt.dx [,tabnam.rt.dx])
948 1221 1
949 1222 1 FORMAL PARAMETERS:
950 1223 1
951 1224 1      logname.rt.dx - A string, passed by descriptor, which contains the
952 1225 1 supervisor mode logical name to be deleted.
953 1226 1      Must be present.
954 1227 1
955 1228 1      tabnam.rt.dx - A string, passed by descriptor, that contains the
956 1229 1 name of the logical name table from which the
957 1230 1 logical name is to be deleted.
958 1231 1      If omitted, the logical name is removed from
959 1232 1 the LNM$PROCESS logical name table.
960 1233 1
961 1234 1 IMPLICIT INPUTS:
962 1235 1
963 1236 1      It is assumed that the logical name table specified already exists.
964 1237 1
965 1238 1 IMPLICIT OUTPUTS:
966 1239 1
967 1240 1      NONE
968 1241 1
969 1242 1 COMPLETION STATUS: (or ROUTINE VALUE:)
970 1243 1
971 1244 1      $$$_NORMAL      Normal successful completion
972 1245 1      $$$_ACCVIO      logname cannot be read
973 1246 1      $$$_IVLOGNAM     logname contains more than 63 characters
974 1247 1      $$$_NOLOGNAM     No such logical name defined or logical name specified
975 1248 1                      was declared in executative or kernel mode
976 1249 1      $$$_IVLOGTAB     Invalid logical name table specified
977 1250 1      $$$_NOPRIV       Caller lacks the necessary privilege to delete
978 1251 1                      the logical name
979 1252 1      $$$_TOOMANYLNAM Logical name translation of the table name exceeded
980 1253 1                      the allowable depth (10 translations)
981 1254 1      LIB$_INVARG       Invalid argument
982 1255 1      LIB$_NOCLI        No CLI present to perform function
983 1256 1      LIB$_UNECLIERR    Unexpected CLI Error
984 1257 1      LIB$_WRONUMARG    No arguments specified or more than two specified.
  
```

```

1258 1
1259 1 1 SIDE EFFECTS:
1260 1 1
1261 1 1 A supervisor mode logical name is deleted from the specified or
1262 1 1 implied logical name table.
1263 1 1
1264 1 1 --
1265 1 1
1266 1 1 BEGIN
1267 1 1
1268 1 1 BUILTIN
1269 1 1 ACTUALCOUNT,
1270 1 1 NULLPARAMETER;
1271 1 1
1272 1 1 LOCAL
1273 1 1 CLI_REQ_BLOCK : BLOCK [CLISC_SRVDESC, BYTE], ! A CLI request block
1274 1 1 RETURN_STATUS : BLOCK [4, BYTE];
1275 1 1
1276 1 1 +
1277 1 1 - Check for proper number of arguments.
1278 1 1 -
1279 1 1
1280 1 1 IF ACTUALCOUNT() EQLU 0
1281 1 1 OR ACTUALCOUNT() GTRU 2
1282 1 1 THEN
1283 1 1 RETURN LIB$WRONUMARG;
1284 1 1 +
1285 1 1 - Initialize CLI Command request block.
1286 1 1 -
1287 1 1 CHSFILL (0, CLISC_SRVDESC, CLI_REQ_BLOCK);
1288 1 1 CLI_REQ_BLOCK [CLISB_RQTYPE] = CLISK_CLISERV;
1289 1 1 CLI_REQ_BLOCK [CLISW_SERVCOD] = CLISR_DELELOG;
1290 1 1
1291 1 1 +
1292 1 1 - Move in the logical name.
1293 1 1 -
1294 1 1
1295 1 1 MOVEDESC ( .LOGNAME, CLI_REQ_BLOCK [CLISQ_NAMDESC] ),
1296 1 1
1297 1 1 +
1298 1 1 - Move in the table name, if specified.
1299 1 1 - If not specified, DCL will default in LNM$PROCESS.
1300 1 1 -
1301 1 1
1302 1 1 IF NOT NULLPARAMETER(TABNAM)
1303 1 1 THEN
1304 1 1 MOVEDESC ( .TABNAM, CLI_REQ_BLOCK [CLISQ_TABDESC] );
1305 1 1
1306 1 1 +
1307 1 1 - Delete the supervisor mode logical name.
1308 1 1 -
1309 1 1 RETURN_STATUS = SYS$CLI (CLI_REQ_BLOCK);
1310 1 1
1311 1 1 +
1312 1 1 - Adjust error return status, if any.
1313 1 1 -
1314 1 1 IF NOT .RETURN_STATUS AND (.RETURN_STATUS [ST$SV_FAC_NO] EQL CLIS_FACILITY)

```

```

: 1042      1315 2      THEN
: 1043      1316      RETURN_STATUS =
: 1044      1317      BEGIN
: 1045      1318      SELECTONE .RETURN_STATUS OF
: 1046      1319      SET
: 1047      1320      [CLIS INVREQTYP] : LIB$NOCLI;
: 1048      1321      [OTHERWISE] : LIB$UNECLIERR;
: 1049      1322      TES
: 1050      1323      END;
: 1051      1324
: 1052      1325      RETURN .RETURN_STATUS
: 1053      1326
: 1054      1327      END;
  
```

! End of LIB\$DELETE_LOGICAL

				007C 00000	.ENTRY LIB\$DELETE LOGICAL, Save R2,R3,R4,R5,R6	: 1202
		56	00000000G	00 9E 00002	MOVAB LIB\$ANALYZE_SDESC_R2, R6	
		5E	AC	AE 9E 00009	MOVAB -84(SP), SP	
				6C 95 0000D	TSTB (AP)	: 1280
				05 13 0000F	BEQL 1\$	
		02		6C 91 00011	CMPB (AP), #2	: 1281
				08 1B 00014	BLEQU 2\$	
		50	00000000G	8F D0 00016 1\$:	MOVL #LIB\$WRONUMARG, R0	: 1283
				04 0001D	RET	
0054	8F		00	6E 2C 0001E 2\$:	MOVCS #0, (SP), #0, #84, CLI_REQ_BLOCK	: 1287
				6E 00025		
		01		6E 05 90 00026	MOVW #5, CLI_REQ_BLOCK	: 1288
				07 B0 00029	MOVW #7, CLI_REQ_BLOCK+1	: 1289
			04	AC D0 0002D	MOVL LOGNAME, R0	: 1295
				66 16 00031	JSB LIB\$ANALYZE_SDESC_R2	
		04		AE 51 B0 00033	MOVW R1, CLI_REQ_BLOCK+4	
		08		AE 52 D0 00037	MOVL R2, CLI_REQ_BLOCK+8	
				46 50 E9 0003B	BLBC RET STATUS, 5\$	
				02 6C 91 0003E	CMPB (APT), #2	: 1302
				16 1F 00041	BLSSU 3\$	
				08 AC D5 00043	TSTL 8(AP)	
				11 13 00046	BEQL 3\$	
		50	08	AC D0 00048	MOVL TABNAM, R0	: 1304
				66 16 0004C	JSB LIB\$ANALYZE_SDESC_R2	
		14		AE 51 B0 0004E	MOVW R1, CLI_REQ_BLOCK+20	
		18		AE 52 D0 00052	MOVL R2, CLI_REQ_BLOCK+24	
				2B 50 E9 00056	BLBC RET STATUS, 5\$	
				5E DD 00059 3\$:	PUSHL SP	: 1309
			00000000G	00 01 FB 0005B	CALLS #1, SYSSCLI	
				1F 50 E8 00062	BLBS RETURN STATUS, 5\$: 1314
03		50		0C 1C ED 00065	CMPZV #16, #T2, RETURN_STATUS, #3	
				18 12 0006A	BNEQ 5\$	
			00038822	8F 50 D1 0006C	CMPB RETURN_STATUS, #231458	: 1320
				08 12 00073	BNEQ 4\$	
				50 0000000G 8F D0 00075	MOVL #LIB\$NOCLI, RETURN_STATUS	
				04 0007C	RET	
				50 0000000G 8F D0 0007D 4\$:	MOVL #LIB\$UNECLIERR, RETURN_STATUS	: 1321
				04 00084 5\$:	RET	: 1327

LIB\$CLI_CALLBAC LIB\$CLI_CALLBACK - CLI Callback Interface Proce 6 10
V04-000 LIB\$DELETE_LOGICAL - delete supervisor mode log 16-Sep-1984 02:22:35
14-Sep-1984 13:27:47

VAX-11 Bliss-32 V4.0-742
[VMSLIB.SRC]LIBCLICAL.B32;1

: Routine Size: 133 bytes, Routine Base: _LIB\$CODE + 037B

```

: 1056 1328 1 %SBTTL 'LIB$DISABLE_CTRL - disable CLI out-of-band character(s) handler'
: 1057 1329 1 GLOBAL ROUTINE LIB$DISABLE_CTRL (          ! disable CLI out-of-band
: 1058 1330 1     DISABLE_MASK : REF VECTOR [ , LONG]      ! disable bit mask
: 1059 1331 1     PREVIOUS_MASK : REF VECTOR [ , LONG]    ! previous enable bit mask
: 1060 1332 1 ) =
: 1061 1333 1
: 1062 1334 1 ++
: 1063 1335 1 FUNCTIONAL DESCRIPTION:
: 1064 1336 1
: 1065 1337 1     This routine disables CLI processing for out-of-band the characters
: 1066 1338 1     identified by DISABLE_MASK.  When normal CLI processing for one or
: 1067 1339 1     more out-of-band characters is disabled, a user program can intercept
: 1068 1340 1     and respond to them.  There are no privilege requirements for calling
: 1069 1341 1     this routine.
: 1070 1342 1
: 1071 1343 1     Currently, this routine supports disabling of CLI out-of-band
: 1072 1344 1     processing for CTRL-T and CTRL-Y when the DCL CLI is in use, and for
: 1073 1345 1     CTRL-Y when the MCR CLI is in use.  The macro $LIBCLIDEF defines the
: 1074 1346 1     two masks used for disabling processing for these two out-of-band
: 1075 1347 1     characters as follows:
: 1076 1348 1         LIBSM_CLI_CTRLT      mask for CTRL-T
: 1077 1349 1         LIBSM_CLI_CTRLY      mask for CTRL-Y
: 1078 1350 1     If the masks are logically or'd together, processing for both
: 1079 1351 1     out-of-band characters will be effected.
: 1080 1352 1
: 1081 1353 1 CALLING SEQUENCE:
: 1082 1354 1
: 1083 1355 1     ret_status.wlc.v = LIB$DISABLE_CTRL (disable_mask.rl.r
: 1084 1356 1                                     [ , previous_mask.wl.r ] )
: 1085 1357 1
: 1086 1358 1 FORMAL PARAMETERS:
: 1087 1359 1
: 1088 1360 1     disable_mask.rl.r      - the mask controlling which out-of-band
: 1089 1361 1     characters the CLI should ignore.  Values
: 1090 1362 1     should be selected from one of, or the logical
: 1091 1363 1     OR of more than one of:
: 1092 1364 1         LIBSM_CLI_CTRLT
: 1093 1365 1         LIBSM_CLI_CTRLY
: 1094 1366 1     These symbols are defined in $LIBCLIDEF.
: 1095 1367 1
: 1096 1368 1     previous_mask.wl.r     - a longword into which will be stored a mask
: 1097 1369 1     having the same format as disable_mask, but
: 1098 1370 1     which represents the enabled state for all
: 1099 1371 1     out-of-band character processing before
: 1100 1372 1     disable_mask is applied.
: 1101 1373 1
: 1102 1374 1 IMPLICIT INPUTS:
: 1103 1375 1
: 1104 1376 1     NONE
: 1105 1377 1
: 1106 1378 1 IMPLICIT OUTPUTS:
: 1107 1379 1
: 1108 1380 1     NONE
: 1109 1381 1
: 1110 1382 1 COMPLETION STATUS: (or ROUTINE VALUE:)
: 1111 1383 1
: 1112 1384 1     $$$_NORMAL      Normal successful completion

```



```

1113 1385 1 | LIB$_INVARG Disable_mask has an unrecognized bit set
1114 1386 1 | LIB$_NOCLI No CLI present to perform function
1115 1387 1 | LIB$_UNECLIERR Unexpected CLI Error
1116 1388 1 |
1117 1389 1 | SIDE EFFECTS:
1118 1390 1 |
1119 1391 1 | CLI out-of-band processing of one or more characters is disabled.
1120 1392 1 |
1121 1393 1 | --
1122 1394 1 |
1123 1395 1 | BEGIN
1124 1396 1 |
1125 1397 1 | BUILTIN
1126 1398 1 | NULLPARAMETER;
1127 1399 1 |
1128 1400 1 | LOCAL
1129 1401 1 | CLI_REQ_BLOCK : BLOCK [CLIS$ SRVDESC, BYTE], ! A CLI request block
1130 1402 1 | RETURN_STATUS : BLOCK [4, BYTE];
1131 1403 1 |
1132 1404 1 |
1133 1405 1 | +
1134 1406 1 | Initialize CLI Command request block.
1135 1407 1 | -
1136 1408 1 | CH$FILL (0, CLIS$ SRVDESC, CLI_REQ_BLOCK);
1137 1409 1 | CLI_REQ_BLOCK [CLIS$ RQTYPE] = CLIS$ CLISERV;
1138 1410 1 | CLI_REQ_BLOCK [CLIS$ SERVCOD] = CLIS$ DISAOOB;
1139 1411 1 | CLI_REQ_BLOCK [CLIS$ NEW_MASK] = .DISABLE_MASK [0];
1140 1412 1 |
1141 1413 1 | +
1142 1414 1 | Request CLI out-of-band processing be disabled.
1143 1415 1 | -
1144 1416 1 | RETURN_STATUS = SYSS$CLI (CLI_REQ_BLOCK);
1145 1417 1 |
1146 1418 1 | +
1147 1419 1 | If requested, return previous out-of-band enabled mask.
1148 1420 1 | It may be good.
1149 1421 1 | -
1150 1422 1 | IF NOT NULLPARAMETER (2)
1151 1423 1 | THEN
1152 1424 1 | PREVIOUS_MASK [0] = .CLI_REQ_BLOCK [CLIS$ OLD_MASK];
1153 1425 1 |
1154 1426 1 | +
1155 1427 1 | Adjust error return status, if any.
1156 1428 1 | -
1157 1429 1 | IF NOT .RETURN_STATUS AND (.RETURN_STATUS [STSS$V_FAC_NO] EQL CLIS$ FACILITY)
1158 1430 1 | THEN
1159 1431 1 | RETURN_STATUS =
1160 1432 1 | BEGIN
1161 1433 1 | SELECT ONE .RETURN_STATUS OF
1162 1434 1 | SET
1163 1435 1 | [CLIS$ BADCTLMSK] : LIB$ INVARG;
1164 1436 1 | [CLIS$ INVREQTYP] : LIB$ NOCLI;
1165 1437 1 | [OTHERWISE] : LIB$ UNECLIERR;
1166 1438 1 | TES
1167 1439 1 | END;
1168 1440 1 |
1169 1441 1 | RETURN (.RETURN_STATUS);

```

: 1170 1442 2
 : 1171 1443 1 END;

: End of LIB\$DISABLE_CTRL

0054	8F	00	5E	AC	AE	003C	00000	.ENTRY	LIB\$DISABLE_CTRL, Save R2,R3,R4,R5	:	1329
			6E		00	9E	00002	MOVAB	-84(SP), SP	:	
					00	2C	00006	MOVCS	#0, (SP), #0, #84, CLI_REQ_BLOCK	:	1408
					6E		0000D			:	
			6E		05	90	0000E	MOVAB	#5, CLI_REQ_BLOCK	:	1409
		01	AE		0D	B0	00011	MOVW	#13, CLI_REQ_BLOCK+1	:	1410
		04	AE	04	BC	D0	00015	MOVL	@DISABLE_MASR, CLI_REQ_BLOCK+4	:	1411
					5E	DD	0001A	PUSHL	SP	:	1416
		00000000G	00		01	FB	0001C	CALLS	#1, SYS\$CLI	:	
			02		6C	91	00023	CMPB	(AP), #2	:	1422
					0A	1F	00026	BLSSU	1\$:	
				08	AC	D5	00028	TSTL	8(AP)	:	
					05	13	0002B	BEQL	1\$:	
		08	BC	08	AE	D0	0002D	MOVL	CLI_REQ_BLOCK+8, @PREVIOUS_MASK	:	1424
			30		50	E8	00032	BLBS	RETURN_STATUS, 4\$:	1429
03		50	0C		10	ED	00035	CMPZV	#16, #12, RETURN_STATUS, #3	:	
		000388CA	8F		29	12	0003A	BNEQ	4\$:	
					50	D1	0003C	CML	RETURN_STATUS, #231626	:	1435
					08	12	00043	BNEQ	2\$:	
		50 00000000G	8F		D0	00045		MOV	#LIB\$_INVARG, RETURN_STATUS	:	
					04	0004C		RET		:	
		00038822	8F		50	D1	0004D	CML	RETURN_STATUS, #231458	:	1436
					08	12	00054	BNEQ	3\$:	
		50 00000000G	8F		D0	00056		MOVL	#LIB\$_NOCLI, RETURN_STATUS	:	
					04	0005D		RET		:	
		50 00000000G	8F		D0	0005E		MOVL	#LIB\$_UNECLIERR, RETURN_STATUS	:	1437
					04	00065		RET		:	1443

: Routine Size: 102 bytes, Routine Base: _LIB\$CODE + 0400

```

1173 1444 1 %SBTTL 'LIBSENABLE_CTRL - re-enable CLI out-of-band character(s) handler'
1174 1445 1 GLOBAL ROUTINE LIBSENABLE_CTRL ( re-enable CLI out-of-band
1175 1446 1 ENABLE_MASK : REF VECTOR [, LONG], enable bit mask
1176 1447 1 PREVIOUS_MASK : REF VECTOR [, LONG] previous enable bit mask
1177 1448 1 ) =
1178 1449 1
1179 1450 1 ++
1180 1451 1 FUNCTIONAL DESCRIPTION:
1181 1452 1
1182 1453 1 This routine re-enables CLI processing for out-of-band the characters
1183 1454 1 identified by ENABLE_MASK, presumably after such processing has been
1184 1455 1 disabled by a call to LIB$DISABLE_CTRL. There are no privilege
1185 1456 1 requirements for calling this routine.
1186 1457 1
1187 1458 1 Currently, this routine supports re-enabling of CLI out-of-band
1188 1459 1 processing for CTRL-T and CTRL-Y when the DCL CLI is in use, and for
1189 1460 1 CTRL-Y when the MCR CLI is in use. The macro $LIBCLIDEF defines the
1190 1461 1 two masks used for enabling processing for these two out-of-band
1191 1462 1 characters as follows:
1192 1463 1 LIBSM_CLI_CTRLT mask for CTRL-T
1193 1464 1 LIBSM_CLI_CTRLY mask for CTRL-Y
1194 1465 1 If the masks are logically or'd together, processing for both
1195 1466 1 out-of-band characters will be effected.
1196 1467 1
1197 1468 1 CALLING SEQUENCE:
1198 1469 1
1199 1470 1 ret_status.wlc.v = LIBSENABLE_CTRL (enable_mask.rl.r
1200 1471 1 [, previous_mask.wl.r ] )
1201 1472 1
1202 1473 1 FORMAL PARAMETERS:
1203 1474 1
1204 1475 1 enable_mask.rl.r - the mask controlling which out-of-band
1205 1476 1 characters the CLI should process. Values
1206 1477 1 should be selected from one of, or the logical
1207 1478 1 OR of more than one of:
1208 1479 1 LIBSM_CLI_CTRLT
1209 1480 1 LIBSM_CLI_CTRLY
1210 1481 1 These symbols are defined in $LIBCLIDEF.
1211 1482 1
1212 1483 1 previous_mask.wl.r - a longword into which will be stored a mask
1213 1484 1 having the same format as enable_mask, but
1214 1485 1 which represents the enabled state for all
1215 1486 1 out-of-band character processing before
1216 1487 1 enable_mask is applied.
1217 1488 1
1218 1489 1 IMPLICIT INPUTS:
1219 1490 1
1220 1491 1 NONE
1221 1492 1
1222 1493 1 IMPLICIT OUTPUTS:
1223 1494 1
1224 1495 1 NONE
1225 1496 1
1226 1497 1 COMPLETION STATUS: (or ROUTINE VALUE:)
1227 1498 1
1228 1499 1 $$$ NORMAL Normal successful completion
1229 1500 1 LIB$INVARG Enable_mask has an unrecognized bit set
    
```

```

1230 1501 1 LIB$ NOCLI No CLI present to perform function
1231 1502 1 LIB$ UNECLIERR Unexpected CLI Error
1232 1503 1
1233 1504 1 SIDE EFFECTS:
1234 1505 1
1235 1506 1 CLI out-of-band processing of one or more characters is enabled.
1236 1507 1
1237 1508 1
1238 1509 1
1239 1510 2 BEGIN
1240 1511 2
1241 1512 2 BUILTIN
1242 1513 2 NULLPARAMETER;
1243 1514 2
1244 1515 2 LOCAL
1245 1516 2 CLI_REQ_BLOCK : BLOCK [CLISC_SRVDESC, BYTE], ! A CLI request block
1246 1517 2 RETURN_STATUS : BLOCK [4, BYTE];
1247 1518 2
1248 1519 2
1249 1520 2 + Initialize CLI Command request block.
1250 1521 2
1251 1522 2
1252 1523 2 CH$FILL (0, CLISC_SRVDESC, CLI_REQ_BLOCK);
1253 1524 2 CLI_REQ_BLOCK [CLISB_RQTYPE] = CLISK CLISERV;
1254 1525 2 CLI_REQ_BLOCK [CLISW_SERVCOD] = CLISK ENABOOB;
1255 1526 2 CLI_REQ_BLOCK [CLISL_NEW_MASK] = .ENABLE_MASK [0];
1256 1527 2
1257 1528 2 + Request CLI out-of-band processing be enabled.
1258 1529 2
1259 1530 2
1260 1531 2 RETURN_STATUS = SYS$CLI (CLI_REQ_BLOCK);
1261 1532 2
1262 1533 2 +
1263 1534 2 If requested, return previous out-of-band enabled mask.
1264 1535 2 It may be good.
1265 1536 2
1266 1537 2 IF NOT NULLPARAMETER (2)
1267 1538 2 THEN
1268 1539 2 PREVIOUS_MASK [0] = .CLI_REQ_BLOCK [CLISL_OLD_MASK];
1269 1540 2
1270 1541 2 + Adjust error return status, if any.
1271 1542 2
1272 1543 2
1273 1544 2 IF NOT .RETURN_STATUS AND (.RETURN_STATUS [STSSV_FAC_NO] EQL CLIS_FACILITY)
1274 1545 2 THEN
1275 1546 2 RETURN_STATUS =
1276 1547 2 BEGIN
1277 1548 2 SELECTONE .RETURN_STATUS OF
1278 1549 2 SET
1279 1550 2 [CLIS_BADCTLMSK] : LIB$ INVARG;
1280 1551 2 [CLIS_INVREQTYP] : LIB$ NOCLI;
1281 1552 2 [OTHERWISE] : LIB$ UNECLIERR;
1282 1553 2 YES
1283 1554 2 END;
1284 1555 2
1285 1556 2 RETURN (.RETURN_STATUS);
1286 1557 2
  
```

! End of LIBSENABLE_CTRL

0054	8F	00	5E	AC	AE	003C	00000	.ENTRY	LIBSENABLE_CTRL, Save R2,R3,R4,R5	:	1445
			6E		00	9E	00002	MOVAB	-84(SP), SP	:	1523
					00	2C	00006	MOVCS	#0, (SP), #0, #84, CLI_REQ_BLOCK	:	1524
					05	90	0000E	MOVW	#5, CLI_REQ_BLOCK	:	1525
		01	6E		0E	B0	00011	MOVW	#14, CLI_REQ_BLOCK+1	:	1526
		04	AE	04	BC	D0	00015	MOVL	@ENABLE_MASK, CLI_REQ_BLOCK+4	:	1531
					5E	DD	0001A	PUSHL	SP	:	1537
		00000000G	00		01	FB	0001C	CALLS	#1, SYSSCLI	:	1539
			02		6C	91	00023	CMPB	(AP), #2	:	1544
					0A	1F	00026	BLSSU	1\$:	1550
				08	AC	D5	00028	TSTL	8(AP)	:	1551
		08	BC	08	05	13	0002B	BEQL	1\$:	1552
			30		AE	D0	0002D	MOVL	CLI_REQ_BLOCK+8, @PREVIOUS_MASK	:	1558
03		50	0C		50	E8	00032	BLBS	RETURN_STATUS, 4\$:	1559
					10	ED	00035	CMPZV	#16, #T2, RETURN_STATUS, #3	:	1550
		000388CA	8F		29	12	0003A	BNEQ	4\$:	1551
					50	D1	0003C	CML	RETURN_STATUS, #231626	:	1552
			50	00000000G	08	12	00043	BNEQ	2\$:	1558
					8F	D0	00045	MOVL	#LIB\$_INVARG, RETURN_STATUS	:	1551
		00038822	8F		04	0004C		RET		:	1552
					50	D1	0004D	CML	RETURN_STATUS, #231458	:	1558
			50	00000000G	08	12	00054	BNEQ	3\$:	1559
					8F	D0	00056	MOVL	#LIB\$_NOCLI, RETURN_STATUS	:	1552
					04	0005D		RET		:	1558
			50	00000000G	8F	D0	0005E	MOVL	#LIB\$_UNECLIERR, RETURN_STATUS	:	1559
					04	00065		RET		:	1558

; Routine Size: 102 bytes, Routine Base: _LIB\$CODE + 0466

```

: 1289      1559 1 %SBTTL 'LIB$$BUILD_SYMBOL_NAME - Build a symbol name string'
: 1290      1560 1 ROUTINE LIB$$BUILD_SYMBOL_NAME (
: 1291      1561 1     SYMBOL: REF BLOCK [, BYTE],
: 1292      1562 1     DYNSTR: REF BLOCK [, BYTE],
: 1293      1563 1     CLI_SYMBOL: REF BLOCK [, BYTE]
: 1294      1564 1 ) =
: 1295      1565 1
: 1296      1566 1
: 1297      1567 1
: 1298      1568 1
: 1299      1569 1
: 1300      1570 1
: 1301      1571 1
: 1302      1572 1
: 1303      1573 1
: 1304      1574 1
: 1305      1575 1
: 1306      1576 1
: 1307      1577 1
: 1308      1578 1
: 1309      1579 1
: 1310      1580 1
: 1311      1581 1
: 1312      1582 1
: 1313      1583 1
: 1314      1584 1
: 1315      1585 1
: 1316      1586 1
: 1317      1587 1
: 1318      1588 1
: 1319      1589 1
: 1320      1590 1
: 1321      1591 1
: 1322      1592 1
: 1323      1593 1
: 1324      1594 1
: 1325      1595 1
: 1326      1596 1
: 1327      1597 1
: 1328      1598 1
: 1329      1599 1
: 1330      1600 1
: 1331      1601 1
: 1332      1602 1
: 1333      1603 1
: 1334      1604 1
: 1335      1605 1
: 1336      1606 1
: 1337      1607 1
: 1338      1608 1
: 1339      1609 1
: 1340      1610 1
: 1341      1611 1
: 1342      1612 1
: 1343      1613 1
: 1344      1614 1
: 1345      1615 1

```

FUNCTIONAL DESCRIPTION:
 Using the string pointed to by SYMBOL, LIB\$\$BUILD_SYMBOL_NAME builds a dynamic string, pointed to by CLI_SYMBOL, which has been upcased and has trailing blanks deleted. The string pointed to by SYMBOL is also tested for validity as a symbol name; the first character must be alphabetic or \$ or _, there must be less than 255 characters in the name (trailing blanks excluded), and there must be at least one non-blank character in the name.
 SCRATCH is a string descriptor into which the actual descriptor for the dynamic string will be written. The calling procedure must use this descriptor to deallocate the dynamic string.
 If this routine detects an error after it has allocated the dynamic string, it will deallocate the dynamic string thus freeing its caller from that responsibility.

CALLING SEQUENCE:
 ret_status.wlc.v - LIB\$\$BUILD_SYMBOL_NAME (symbol.rt.dx,
 dynstr.wt.dx,
 cli_symbol.wt.dx)

FORMAL PARAMETERS:
 symbol.rt.dx - A string, passed by descriptor, which contains the original symbol name.
 dynstr.wt.dx - A string descriptor into which the descriptor for the actual dynamic string used to contain the converted symbol name will be written. The calling procedure must use this descriptor to deallocate the dynamic string.
 cli_symbol.wt.dx - A string, passed by descriptor, into which the processed symbol name will be placed. This routine creates a new dynamic string in this descriptor: the contents of the descriptor upon entry are overwritten.

IMPLICIT INPUTS:
 LIB\$AB_UPCASE the address of an upcase translation table.

IMPLICIT OUTPUTS:
 NONE

COMPLETION STATUS: (or ROUTINE VALUE:)

```

1346 1616 1 |
1347 1617 1 |      SSS NORMAL      Normal successful completion
1348 1618 1 |      LIB$_INVARG     Symbol name contains more than 255 characters or is
1349 1619 1 |                      all blanks
1350 1620 1 |      LIB$_INVSYMNAM  Symbol name does not begin with a letter
1351 1621 1 |      LIB$_INSVIRMEM  Insufficient virtual memory for dynamic string
1352 1622 1 |      Other completion stati from LIB$ANALYZE_SDESC.
1353 1623 1 |
1354 1624 1 |
1355 1625 1 | SIDE EFFECTS:
1356 1626 1 |
1357 1627 1 |      WARNING:
1358 1628 1 |      Although this procedure performs some checks on the validity of
1359 1629 1 |      symbol names passed to it, some symbol name considered valid by
1360 1630 1 |      this procedure will be considered invalid by DCL.
1361 1631 1 |
1362 1632 1 | --
1363 1633 1 |
1364 1634 2 | BEGIN
1365 1635 2 |
1366 1636 2 | LOCAL
1367 1637 2 |     ADDRESS,          | a string address
1368 1638 2 |     LENGTH : WORD,   | a string length
1369 1639 2 |     IN_PTR, OUT_PTR, | two pointer variables
1370 1640 2 |     STATUS;          | a return status value
1371 1641 2 |
1372 1642 2 |
1373 1643 2 |
1374 1644 2 | +
1375 1645 2 | Gather information about input symbol name string
1376 1646 2 | and build pointer input symbol name string.
1377 1647 2 | -
1378 1648 2 |
1379 1649 2 |     STATUS = LIB$ANALYZE_SDESC_R2 (.SYMBOL; LENGTH, ADDRESS );
1380 1650 2 |     IF NOT .STATUS THEN RETURN .STATUS;
1381 1651 2 |     IN_PTR = CH$PTR( .ADDRESS, .LENGTH - 1 );
1382 1652 2 |
1383 1653 2 | +
1384 1654 2 | Work backwards from the end of the string to locate
1385 1655 2 | the first non-blank character; i.e. locate beginning
1386 1656 2 | of the trailing blanks.
1387 1657 2 | -
1388 1658 2 |     LENGTH = 1 +
1389 1659 2 |     BEGIN
1390 1660 3 |         DECR J FROM .LENGTH - 1 TO 0 DO
1391 1661 4 |         BEGIN
1392 1662 4 |             IF CH$RCHAR( .IN_PTR ) NEQU %C' ' THEN EXITLOOP .J;
1393 1663 4 |             IN_PTR = CH$PLUST( .IN_PTR, -1 );
1394 1664 4 |         END
1395 1665 2 |     END;
1396 1666 2 |     IF .LENGTH EQLU 0 OR .LENGTH GTRU 255 THEN RETURN LIB$_INVSYMNAM;
1397 1667 2 |
1398 1668 2 | +
1399 1669 2 | Allocate a dynamic string and setup CLI symbol name
1400 1670 2 | string descriptor.
1401 1671 2 | -
1402 1672 2 |     DYNSTR [DSC$B_CLASS] = DSC$K_CLASS_D;

```

```

: 1403      1673  2      DYNSTR [DSC$B_DTYPE] = DSC$K_DTYPE_T;
: 1404      1674  2      DYNSTR [DSC$W_LENGTH] = 0;
: 1405      1675  2      DYNSTR [DSC$A_POINTER] = 0;
: 1406      1676  2      STATUS = LIB$$GET1_DD( LENGTH, .DYNSTR );
: 1407      1677  2      IF NOT .STATUS THEN RETURN .STATUS;
: 1408      1678  2      CLI_SYMBOL [DSC$A_POINTER] = .DYNSTR [DSC$A_POINTER];
: 1409      1679  2      CLI_SYMBOL [DSC$W_LENGTH] = .LENGTH;
: 1410      1680  2
: 1411      1681  2      +
: 1412      1682  2      - Uppcase the symbol name.
: 1413      1683  2
: 1414      1684  2      IN_PTR = CH$PTR( .ADDRESS );
: 1415      1685  2      OUT_PTR = CH$PTR( .CLI_SYMBOL [DSC$A_POINTER] );
: 1416      1686  2      CH$TRANSLATE( LIB$AB_UPCASE, .LENGTH, .IN_PTR, %C' ', .LENGTH, .OUT_PTR );
: 1417      1687  2
: 1418      1688  2      +
: 1419      1689  2      - Check for reasonable first character in symbol name.
: 1420      1690  2
: 1421      1691  2      IF (CH$RCHAR( .OUT_PTR ) LSSU %C'A' OR CH$RCHAR( .OUT_PTR ) GTRU %C'Z') AND
: 1422      1692  2      (CH$RCHAR( .OUT_PTR ) NEQU %C'$' OR CH$RCHAR( .OUT_PTR ) NEQU %C'_')
: 1423      1693  3      THEN
: 1424      1694  3      BEGIN
: 1425      1695  3      LIB$$FREE1_DD( .DYNSTR );
: 1426      1696  3      RETURN LIB$_INVSYMNAM;
: 1427      1697  3      END
: 1428      1698  2      ELSE
: 1429      1699  2      RETURN S$$NORMAL;
: 1430      1700  2
: 1431      1701  1      END;

```

! End of routine LIB\$\$BUILD_SYMBOL_NAME

00FC 0000 LIB\$\$BUILD_SYMBOL_NAME:

					.WORD	Save R2,R3,R4,R5,R6,R7	: 1560
					SUBL2	#4, SP	
					MOVL	SYMBOL, R0	: 1649
					JSB	LIB\$ANALYZE_SDESC_R2	
					MOVL	R2, R3	
					MOVL	R1, LENGTH	
					BLBC	STATUS, 4\$: 1650
					MOVZWL	LENGTH, R2	: 1651
					ADDL2	ADDRESS, R2	
					DECL	IN_PTR	
					MOVZWL	LENGTH, J	: 1660
					BRB	2\$	
					CMPB	(IN_PTR), #32	: 1662
					BNEQ	3\$	
					DECL	IN_PTR	: 1663
					SOBGEQ	J, 1\$: 1660
					MNEGL	#1, R1	
					ADDW3	#1, R1, LENGTH	: 1658
					BEQL	7\$: 1666
					CMPW	LENGTH, #255	
					BGTRU	7\$	
					MOVL	DYNSTR, R6	: 1672

00000000G	00	04	00	04	00	00043	MOVL	#34471936, (R6)	1674
						0004A	(LRL	4(R6)	1675
						0004D	PUSHL	R6	1676
						0004F	PUSHAB	LENGTH	
00000000G	00					00052	CALLS	#2, LIB\$SGET1_DD	
						00059	BLBC	STATUS, 9\$	1677
						0005C	MOVL	CLI_SYMBOL, R0	1678
00000000G	00	04				00060	MOVL	4(R6), 4(R0)	
						00065	MOVW	LENGTH, (R0)	1679
						00068	MOVL	ADDRESS, IN PTR	1684
						0006B	MOVL	4(R0), OUT PTR	1685
00000000G	00					0006F	MOVTC	LENGTH, (IN PTR), #32, LIB\$AB_UPCASE, -	1686
						00078		LENGTH, (OUT PTR)	
						0007A	CMPB	(OUT_PTR), #85	1691
						0007E	BLSSU	5\$	
						00080	CMPB	(OUT_PTR), #90	
						00084	BLEQU	8\$	
						00086	CMPB	(OUT_PTR), #36	1692
						00089	BNEQ	6\$	
						0008B	CMPB	(OUT_PTR), #95	
						0008F	BEQL	8\$	
						00091	PUSHL	R6	1695
00000000G	00					00093	CALLS	#1, LIB\$FREE1_DD	
						0009A	MOVL	#LIB\$_INVSYMMAN, R0	1699
						000A1	RET		
						000A2	MOVL	#1, R0	
						000A5	RET		1701

; Routine Size: 166 bytes, Routine Base: _LIB\$CODE + 04CC

: 1433 1702 1 END . End of module LIB\$CLI_CALLBACK
 : 1434 1703 0 ELUDOM

PSECT SUMMARY

Name	Bytes	Attributes
_LIB\$CODE	1394	NOVEC,NOWRT, RD , EXE, SHR, LCL, REL, CON, PIC,ALIGN(2)

Library Statistics

File	Symbols		Pages Mapped	Processing Time
	Total	Loaded Percent		
_\$255\$DUA28:[SYSLIB]STARLET.L32;1	9776	38 0	581	00:01.0

COMMAND QUALIFIERS

BLISS/CHECK=(FIELD,INITIAL,OPTIMIZE)/NOTRACE/LIS=LISS:LIBCLICAL/OBJ=OBJ\$:LIBCLICAL MSRC\$:LIBCLICAL/UPDATE=(ENHS:LIBCLICAL)

: Size: 1394 code + 0 data bytes
 : Run Time: 00:34.2
 : Elapsed Time: 01:07.4
 : Lines/CPU Min: 2990
 : Lexemes/CPU-Min: 37106
 : Memory Used: 171 pages
 : Compilation Complete

