

DDDDDDDDDDDD		CCCCCCCCCCCC	LLL
DDDDDDDDDDDD		CCCCCCCCCCCC	LLL
DDDDDDDDDDDD		CCCCCCCCCCCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDDDDDDDDDDD		CCCCCCCCCCCC	LLLLLLLLLLLLLLLL
DDDDDDDDDDDD		CCCCCCCCCCCC	LLLLLLLLLLLLLLLL
DDDDDDDDDDDD		CCCCCCCCCCCC	LLLLLLLLLLLLLLLL

```

KK      KK  EEEEEEEEE  YY      YY  PPPPPPP  AAAAAA  DDDDDDD  DD
KK      KK  EEEEEEEEE  YY      YY  PPPPPPP  AAAAAA  DDDDDDD  DD
KK      KK  EE          YY      YY  PP      PP  AA      AA  DD      DD
KK      KK  EE          YY      YY  PP      PP  AA      AA  DD      DD
KK      KK  EE          YY      YY  PP      PP  AA      AA  DD      DD
KK      KK  EE          YY      YY  PP      PP  AA      AA  DD      DD
KK      KK  EE          YY      YY  PP      PP  AA      AA  DD      DD
KK      KK  EE          YY      YY  PP      PP  AA      AA  DD      DD
KK      KK  EE          YY      YY  PP      PP  AA      AA  DD      DD
KK      KK  EE          YY      YY  PP      PP  AA      AA  DD      DD
KK      KK  EE          YY      YY  PP      PP  AA      AA  DD      DD
KK      KK  EEEEEEEEE  YY      YY  PPPPPPP  AAAAAA  DDDDDDD  DD
KK      KK  EEEEEEEEE  YY      YY  PPPPPPP  AAAAAA  DDDDDDD  DD
KK      KK  EEEEEEEEE  YY      YY  PPPPPPP  AAAAAA  DDDDDDD  DD
KK      KK  EEEEEEEEE  YY      YY  PPPPPPP  AAAAAA  DDDDDDD  DD
KK      KK  EEEEEEEEE  YY      YY  PPPPPPP  AAAAAA  DDDDDDD  DD
KK      KK  EEEEEEEEE  YY      YY  PPPPPPP  AAAAAA  DDDDDDD  DD
KK      KK  EEEEEEEEE  YY      YY  PPPPPPP  AAAAAA  DDDDDDD  DD
KK      KK  EEEEEEEEE  YY      YY  PPPPPPP  AAAAAA  DDDDDDD  DD
KK      KK  EEEEEEEEE  YY      YY  PPPPPPP  AAAAAA  DDDDDDD  DD
KK      KK  EEEEEEEEE  YY      YY  PPPPPPP  AAAAAA  DDDDDDD  DD

```

```

LL      LL  IIIIII  SSSSSSS
LL      LL  IIIIII  SSSSSSS
LL      LL  II      SS
LL      LL  II      SS
LL      LL  II      SS
LL      LL  II      SS
LL      LL  II      SSSSS
LL      LL  II      SSSSS
LL      LL  II      SS
LL      LL  II      SS
LL      LL  II      SS
LL      LL  II      SS
LL      LL  IIIIII  SSSSSSS
LL      LL  IIIIII  SSSSSSS

```

KEYPAD
Table of contents

(3)	147	DEFINE KEYPAD SYMBOL
(4)	295	DELETE KEYPAD SYMBOL
(7)	465	SHOW KEYPAD SYMBOL TABLE ENTRIES
(10)	815	ALLOCATE AND INSERT ENTRY IN KEYPAD SYMBOL TABLE
(11)	920	CHECK FOR SYNONYM KEY NAMES
(12)	998	SEARCH FOR SYMBOL ENTRY IN KEYPAD SYMBOL TABLE
(13)	1035	SEARCH KEYPAD SYMBOL TABLE FOR ENTRY
(14)	1110	SET KEYPAD STATE
(15)	1184	ALLOCATE AND INIT A KEYPAD STATE SYMBOL
(16)	1223	DEALLOCATE A KEYPAD STATE SYMBOL

```
0000 1 .TITLE KEYPAD - KEYPAD SYMBOL TABLE MANIPULATION ROUTINES
0000 2 .IDENT 'V04-000'
0000 3
0000 4 *****
0000 5 *
0000 6 * COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
0000 7 * DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
0000 8 * ALL RIGHTS RESERVED.
0000 9 *
0000 10 * THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
0000 11 * ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
0000 12 * INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
0000 13 * COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
0000 14 * OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
0000 15 * TRANSFERRED.
0000 16 *
0000 17 * THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
0000 18 * AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
0000 19 * CORPORATION.
0000 20 *
0000 21 * DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
0000 22 * SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
0000 23 *
0000 24 *
0000 25 *****
0000 26
0000 27 KEYPAD SYMBOL TABLE MANIPULATION ROUTINES
0000 28
0000 29 AUTHOR: Peter George 15-March-1983
0000 30
0000 31 These routines all assume the structure of a keypad symbol
0000 32 block, starting with the symbol name (SYM_T_SYMBOL), is as follows:
0000 33
0000 34 Byte - length of symbol name
0000 35 ASCII symbol name
0000 36 Word - combined lengths of next three strings + 4
0000 37 Byte - length of if_state string
0000 38 ASCII if_state string
0000 39 Word - length of symbol value
0000 40 ASCII symbol value
0000 41 Byte - length of set_state string
0000 42 ASCII set_state string
0000 43
0000 44 MODIFIED BY:
0000 45
0000 46 V03-006 HWS0058 Harold Schultz 18-Apr-1984
0000 47 Use DCL$ALLOC STATE when setting temporary key states
0000 48 and DCL$LOCKED_STATE to restore original state.
0000 49 Exchange the synonym keypad names with the common key names.
0000 50 (i.e. translate "FIND" to "E1" instead of "E1" to "FIND")
0000 51
0000 52 V03-006 HWS0052 Harold Schultz 09-Apr-1984
0000 53 Translate synonym keypad names to a common key name.
0000 54 (i.e. Translate "E1" to "FIND")
0000 55 Add SHOW KEY/LOG.
0000 56
0000 57 V03-005 PCG0005 Peter George 09-Feb-1984
```

0000	58	:			
0000	59	:			Change format of SHOW KEY display.
0000	60	:			Add SHOW KEY/FULL.
0000	61	:			Zero the input buffer at the end of DCL\$DEFKEY.
0000	62	:	V03-004	PCG0004	Peter George
0000	63	:			Add /ERASE.
0000	64	:			
0000	65	:	V03-003	PCG0003	Peter George
0000	66	:			Move PSECT declaration.
0000	67	:			
0000	68	:	V03-002	PCG0002	Peter George
0000	69	:			Validate key names before defining them.
0000	70	:			
0000	71	:	V03-001	PCG0001	Peter George
0000	72	:			Tolerate omission of SET KEY qualifiers.
0000	73	:			Add SHOW KEY/BRIEF/DIRECTORY.
0000	74	:			---

```

0000 76 :
0000 77 : MACRO LIBRARY CALLS
0000 78 :
0000 79 : PRCDEF ;DEFINE PROCESS DATA STRUCTURE
0000 80 : WRKDEF ;DEFINE COMMAND DATA STRUCTURE
0000 81 : PTRDEF ;DEFINE TOKEN DESCRIPTORS
0000 82 : SYMDEF ;DEFINE SYMBOL ENTRY OFFSETS
0000 83 : $CLMSGDEF ;DEFINE ERROR/STATUS VALUES
0000 84 : $STSDEF ;DEFINE STATUS LONGWORD
0000 85 :
0000 86 : .PSECT DCL$ZCODE, BYTE, RD, NOWRT
0000 87 :
0000 88 :
0000 89 : ASCII TEXT STRINGS FOR SHOW KEYS DISPLAY.
0000 90 :
0000 91 SHOWHDR:
20 64 61 70 79 65 6B 20 43 41 21 00' 0000 92 .ASCII '!AC keypad definitions:'
3A 73 6E 6F 69 74 69 6E 69 66 65 64 000C
17 0000
0018 93 BRIEFFAO:
41 21 22 20 3D 20 53 41 21 20 20 00' 0018 94 .ASCII ' !AS = '!AS''
22 53 0024
0D 0018
0026 95 FULLFAO:
41 21 22 20 3D 20 53 41 21 20 20 00' 0026 96 .ASCII ' !AS = '!AS'' (!ACecho,!ACterminate,!ACerase,!AClock!AC!AC!AS)'
6F 68 63 65 43 41 21 28 20 20 22 53 0032
74 61 6E 69 6D 72 65 74 43 41 21 2C 003E
21 2C 65 73 61 72 65 43 41 21 2C 65 004A
43 41 21 43 41 21 6B 63 6F 6C 43 41 0056
29 53 41 21 0062
3F 0026
6F 6E 00' 0066 97 NO: .ASCII 'no'
02 0066
3D 65 74 61 74 73 00' 0069 98 STATE: .ASCII 'state='
06 0069
00 0070
2C 00' 0071 99 NI.LL: .BYTE 0
01 0071 100 COMMA: .ASCII ', '
0073
0073 101 :
0073 102 : SYNONYM KEY NAME TABLES
0073 103 :
0073 104 :
0073 105 : DEFINE SYNONYM KEY NAMES
0073 106 :
0073 107 : SYNONYM NAME SETS UP THE RELATIONSHIP BETWEEN THE SYNONYM (NAME1) AND
0073 108 : THE COMMON KEY NAME (NAME2) THAT THE SYNONYM IS TRANSLATED TO. IF A NEW
0073 109 : SYNONYM IS CREATED THAT TRANSLATES TO AN EXISTING COMMON KEY NAME (IN
0073 110 : SYNDEF_TAB), ONLY AN ENTRY IN SYNNAME_TAB NEEDS TO BE ADDED. IF A NEW
0073 111 : COMMON KEY NAME IS NEEDED, THEN ADD IT TO SYNDEF_TAB.
0073 112 :
0073 113 : .MACRO SYNONYM_NAME NAME1,NAME2
0073 114 : .ASCII 'NAME1'
0073 115 : .WORD 'NAME2'_ADR - SYNDEF_TAB
0073 116 : .ENDM
0073 117 :
0073 118 :
0073 119 SYNNAME_TAB:

```

```
0073 120      SYNONYM_NAME  FIND,E1      ;DEFINE SYNONYM KEY NAMES
007A 121      SYNONYM_NAME  INSERT_HERE,E2
0088 122      SYNONYM_NAME  REMOVE,E3
0091 123      SYNONYM_NAME  SELECT,E4
009A 124      SYNONYM_NAME  PREV_SCREEN,E5
00A8 125      SYNONYM_NAME  NEXT_SCREEN,E6
00B6 126      .BYTE        0      ;END OF TABLE MARKER
00B7 127      :
00B7 128      : DEFINE COMMON SYNONYM KEY NAMES
00B7 129      :
00B7 130      : NAME = COMMON TRANSLATED NAME (I.E. 'FIND')
00B7 131      :
00B7 132      : .MACRO  SYNONYM_TRN  NAME
00B7 133      'NAME' _ADR:
00B7 134      .ASCIC  'NAME'
00B7 135      .ENDM
00B7 136
00B7 137
00B7 138      SYNDEF _TAB:
00B7 139      SYNONYM_TRN  E1
00BA 140      SYNONYM_TRN  E2
00BD 141      SYNONYM_TRN  E3
00C0 142      SYNONYM_TRN  E4
00C3 143      SYNONYM_TRN  E5
00C6 144      SYNONYM_TRN  E6
00C9 145
```

```

00C9 147 .SBTTL DEFINE KEYPAD SYMBOL
00C9 148 :+
00C9 149 : DCL$DEFKEY - DEFINE KEYPAD SYMBOL
00C9 150 :
00C9 151 : THIS ROUTINE IS CALLED AS AN INTERNAL COMMAND TO EXECUTE THE DEFINE/KEY
00C9 152 : COMMAND.
00C9 153 :
00C9 154 : INPUTS:
00C9 155 :
00C9 156 : R8 = ADDRESS OF SCRATCH BUFFER DESCRIPTOR.
00C9 157 : R9 = ADDRESS OF SCRATCH STACK.
00C9 158 : R10 = BASE ADDRESS OF COMMAND WORK AREA.
00C9 159 : R11 = BASE ADDRESS OF PROCESS WORK AREA.
00C9 160 :
00C9 161 : OUTPUTS:
00C9 162 :
00C9 163 : THE SPECIFIED META-KEY IS ASSIGNED TO THE SPECIFIED EQUIVALENCE
00C9 164 : STRING.
00C9 165 :-
00C9 166
00C9 167 DCL$DEFKEY:: ;DEFINE META-KEY EQUIVALENCE
00C9 168
00C9 169
00C9 170 : SET INITIAL PARSE STATE.
00C9 171 :
56 01 D0 00C9 172 MOVL #SYM_M_ECHO,R6 ;INITIALIZE KEYPAD FLAGS
57 01 D0 00C9 173 MOVL #1,R7 ;INITIALIZE LOCAL FLAGS (/LOG)
58 D4 00CF 174 CLRL R8 ;CLEAR IF_STATE TOKEN PTR
79 7C 00D1 175 CLRQ -(R9) ;ALLOCATE SET_STATE DESCRIPTOR
00D3 176
00D3 177 :
00D3 178 : PROCESS THE TOKENS ON THE COMMAND LINE.
00D3 179 :
FF2A' 30 00D3 180 BSBW DCL$GETDVAL ;SKIP PAST /KEY DESCRIPTOR
FF27' 30 00D6 181 10$: BSBW DCL$GETDVAL ;GET NEXT DESCRIPTOR VALUES
55 04 91 00D9 182 CMPB #PTR_K_ENDLINE,R5 ;EOL?
03 12 00DC 183 BNEQ 15$ ;NO, CONTINUE PARSING
00AF 31 00DE 184 BRW 70$ ;YES, THEN DONE PARSING
55 03 91 00E1 185 15$: CMPB #PTR_K_PARAMETR,R5 ;ITEM TYPE PARAMETER?
05 12 00E4 186 BNEQ 20$ ;NO, THEN PROCESS QUALIFIER
79 51 7D 00E6 187 MOVQ R1, -(R9) ;SAVE PARAMETER DESCRIPTOR
EB 11 00E9 188 BRB 10$ ;GET NEXT TOKEN
FF12' 30 00EB 189 20$: BSBW DCL$GETNVAL ;GET QUALIFIER NUMBER
00000000'8F 51 D1 00EE 190 CMPL R1,#CLISK_DEFK_TERM ;QUALIFIER MATCH?
38 13 00F5 191 BEQL 30$ ;YES, THEN PROCESS
00000000'8F 51 D1 00F7 192 CMPL R1,#CLISK_DEFK_ECHO ;QUALIFIER MATCH?
38 13 00FE 193 BEQL 35$ ;YES, THEN PROCESS
00000000'8F 51 D1 0100 194 CMPL R1,#CLISK_DEFK_LOCK ;QUALIFIER MATCH?
3E 13 0107 195 BEQL 40$ ;YES, THEN PROCESS
00000000'8F 51 D1 0109 196 CMPL R1,#CLISK_DEFK_LOG ;QUALIFIER MATCH?
41 13 0110 197 BEQL 43$ ;YES, THEN PROCESS
00000000'8F 51 D1 0112 198 CMPL R1,#CLISK_DEFK_SET_ ;QUALIFIER MATCH?
4F 13 0119 199 BEQL 45$ ;YES, THEN PROCESS
00000000'8F 51 D1 011B 200 CMPL R1,#CLISK_DEFK_IF_S ;QUALIFIER MATCH?
58 13 0122 201 BEQL 50$ ;YES, THEN PROCESS
00000000'8F 51 D1 0124 202 CMPL R1,#CLISK_DEFK_ERAS ;QUALIFIER MATCH?
31 13 012B 203 BEQL 55$ ;YES, THEN PROCESS
    
```



```

A7 11 012D 204 25$: BRB 10$ ;GET NEXT
      012F 205
F7 53 00 E1 012F 206 30$: SETBIT SYM V TERMINATE,R6 ;ASSUME /TERMINATE
      0132 207 BBC #PTR V NEGATE-PTR_V_FLAGS,R3,25$ ;IGNORE IF NOT /NOTERMINATE
      0136 208 CLRBIT SYM V TERMINATE,R6 ;CLEAR TERMINATE FLAG
      F2 11 0139 209 BRB 25$ ;GET NEXT
EB 53 00 E1 013B 210 35$: SETBIT SYM V ECHO,R6 ;ASSUME /ECHO
      013E 211 BBC #PTR V NEGATE-PTR_V_FLAGS,R3,25$ ;IGNORE IF NOT /NOECHO
      E6 11 0142 212 CLRBIT SYM V ECHO,R6 ;CLEAR ECHO FLAG
      0145 213 BRB 25$ ;GET NEXT
DF 53 00 E1 0147 214 40$: SETBIT SYM V LOCK,R6 ;ASSUME /LOCK
      014A 215 BBC #PTR V NEGATE-PTR_V_FLAGS,R3,25$ ;IGNORE IF NOT /NOLOCK
      014E 216 CLRBIT SYM V LOCK,R6 ;CLEAR LOCK FLAG
      DA 11 0151 217 BRB 25$ ;GET NEXT
      57 01 D0 0153 218 43$: MOVL #1,R7 ;ASSUME /LOG
D3 53 00 E1 0156 219 BBC #PTR V NEGATE-PTR_V_FLAGS,R3,25$ ;IGNORE IF NOT /NOLOG
      57 D4 015A 220 CLRL R7 ;CLEAR FLAG
      CF 11 015C 221 BRB 25$ ;GET NEXT
      015E 222 55$: SETBIT SYM V ERASE,R6 ;ASSUME /ERASE
C8 53 00 E1 0161 223 BBC #PTR V NEGATE-PTR_V_FLAGS,R3,25$ ;IGNORE IF NOT /NOERASE
      0165 224 CLRBIT SYM V ERASE,R6 ;CLEAR ERASE FLAG
      C3 11 0168 225 BRB 25$ ;GET NEXT
      016A 226
BC 53 00 E0 016A 227 45$: CLRBIT SYM V STATE,R6 ;ASSUME /NOSET_STATE
      016D 228 BBS #PTR V NEGATE-PTR_V_FLAGS,R3,25$ ;IGNORE IF NOT /SET_STATE
      0171 229 SETBIT SYM V STATE,R6 ;SET STATE FLAG
      FE89' 30 0174 230 BSBW DCL$GETDVAL ;GET THE ASSOCIATED VALUE
      69 51 7D 0177 231 MOVQ R1,(R9) ;SAVE THAT VALUE
      B1 11 017A 232 BRB 25$ ;GET NEXT
      017C 233
      58 D4 017C 234 50$: CLRL R8 ;ASSUME /NOIF STATE
AB 53 00 E0 017E 235 BBS #PTR V NEGATE-PTR_V_FLAGS,R3,25$ ;IGNORE IF NOT /IF STATE
      58 BA AA D0 0182 236 MOVL WRK [RSLNXT(R10)],R8 ;SAVE VALUE TOKEN PTR
      FE77' 30 0186 237 52$: BSBW DCL$GETDVAL ;GET NEXT DESCRIPTOR VALUE
      54 05 D1 0189 238 CMPL #PTR_K_COMMA,R4 ;TERMINATOR A COMMA?
      F8 13 018C 239 BEQL 52$ ;GET NEXT VALUE
      9D 11 018E 240 BRB 25$ ;GET NEXT
      0190 241
      0190 242
      0190 243 : INSERT THE META-KEY SYMBOL IN THE SPECIFIED KEYPAD SYMBOL TABLES.
      0190 244
      0190 245 : SCRATCH STACK LOOKS LIKE:
      0190 246 : (R9) EQUIVALENCE STRING DESCRIPTOR
      0190 247 : 8(R9) META-KEY NAME DESCRIPTOR
      0190 248 : 16(R9) SET STATE DESCRIPTOR
      0190 249 : R6 CONTAINS SYMBOL FLAGS
      0190 250
      08 A9 7F 0190 251 70$: PUSHQ 8(R9) ;PUSH THE DESCRIPTOR ADDRESS
00000000'EF 01 FB 0193 252 CALLS #1,VALIDATE_KEY_NAME ;IS IT VALID?
      5F 50 E9 019A 253 BLBC R0,97$ ;NO, THEN RETURN ERROR
      50 57 D0 019D 254 MOVL R7,R0 ;GET /LOG FLAG
      51 08 A9 7D 01A0 255 MOVQ 8(R9),R1 ;GET KEY NAME DESCRIPTOR
      04AA 30 01A4 256 BSBW DCL$SYNONYM ;CHECK FOR SYNONYMS
      08 A9 51 7D 01A7 257 MOVQ R1,8(R9) ;SAVE RETURNED KEYPAD NAME
      03 56 01 E0 01AB 258 BBS #SYM_V_TERMINATE,R6,71$ ;BRANCH IF /TERMINATE
      56 01 CA 01AF 259 BICL #SYM_M_ECHO,R6 ;IGNORE THE ECHO FLAG
      01B2 260 71$: ASSUME PTR_K_COMMA NE 0
    
```

```

BA AA 58 DO 01B2 261      MOVL  R8,WRK_L_RSLNXT(R10)      ;RESET FOR FIRST IF_STATE VALUE
          09 13 01B6 262      BEQL  75$      ;SKIP IF NONE
          FE45' 30 01B8 263 72$: BSBW  DCL$GETDVAL      ;GET NEXT DESCRIPTOR VALUE
58 54 DO 01BB 264      MOVL  R4,R8      ;SAVE THE TERMINATOR
          05D3 30 01BE 265      BSBW  DCL$ALLOC_STATE      ;SET NEW STATE
          03F9 30 01C1 266 75$: BSBW  DCL$ALLOCKEY      ;ALLOCATE THE KEYPAD SYMBOL
          31 50 E9 01C4 267      BLBC  R0,95$      ;BRANCH IF ERROR
          01C7 268
          01C7 269
          01C7 270      ; OUTPUT /LOG MESSAGE.
          01C7 271
          13 57 E9 :7 272      BLBC  R7,80$      ;SKIP IF /NOLOG
          08 A9 9F U CA 273      PUSHAB 8(R9)      ;SET ADDRESS OF META-KEY NAME DESCR
          48 AB DD 01CD 274      PUSHL  PRC_L_CURRKEY(R11)      ;SET ADDRESS OF ASCII STATE NAME
          51 02 DO 01D0 275      MOVL  #2,R1      ;SET ARGUMENT COUNT
50 0003DDC3 8F DO 01D3 276      MOVL  #CLIS_DEFKEY,R0      ;SET STATUS
          FE23' 30 01DA 277      BSBW  DCL$FORMMSG      ;OUTPUT THE LOG MESSAGE
          58 05 D1 01DD 278 80$: CML  #PTR_K_COMMA,R8      ;TERMINATOR A COMMA?
          05 12 01E0 279      BNEQ  90$      ;NO, TIME TO EXIT
          FE1B' 30 01E2 280      BSBW  DCL$LOCKED_STATE      ;YES, RESTORE LOCKED KEY STATE
          01E5 281
          D1 11 01E5 282      BRB  72$      ; BEFORE GETTING NEXT STATE
          01E7 283
          01E7 284      ; RESTORE KEYPAD STATE AND RETURN.
          01E7 285
          01E7 286
0100 8F 00 6E 00 2C 01E7 287 90$: MOVCS #0,(SP),#0,#WRK_C_INPBUFSIZ,- ;RESET THE INPUT BUFFER
          F896 CA 01EE 288      WRK_G_INPBUF(R10)
          01F1 289      STATUS NORMAL      ;SET NORMAL COMPLETION
          FE05' 30 01F8 290 95$: BSBW  DCL$LOCKED_STATE      ;RESTORE KEY STATE
          05 01FB 291      RSB
50 00038280 8F DO 01FC 292 97$: MOVL  #CLIS_IVKEYNAM,R0      ;SET STATUS
          F3 11 0203 293      BRB  95$      ;RETURN

```

```

0205 295 .SBTTL DELETE KEYPAD SYMBOL
0205 296 :
0205 297 : DCL$DELKEY - DELETE KEYPAD SYMBOL
0205 298 :
0205 299 : THIS ROUTINE IS CALLED AS AN INTERNAL COMMAND TO EXECUTE THE DELETE/KEY
0205 300 : COMMAND.
0205 301 :
0205 302 : INPUTS:
0205 303 :
0205 304 : R8 = ADDRESS OF SCRATCH BUFFER DESCRIPTOR.
0205 305 : R9 = ADDRESS OF SCRATCH STACK.
0205 306 : R10 = BASE ADDRESS OF COMMAND WORK AREA.
0205 307 : R11 = BASE ADDRESS OF PROCESS WORK AREA.
0205 308 :
0205 309 : OUTPUTS:
0205 310 :
0205 311 : THE SPECIFIED META-KEY IS DELETED FROM THE SYMBOL TABLE.
0205 312 :
0205 313 :
0205 314 DCL$DELKEY:: ;DELETE KEYPAD DEFINITION
0205 315 :
0205 316 : SET INITIAL PARSE STATE.
0205 317 :
0205 318 CLRL R8 ;CLEAR STATE TOKEN PTR
0207 319 PUSHL #3 ;INITIALIZE LOCAL FLAGS
0209 320 :
0209 321 : /LOG, /ALL, NO UNDEFINED SYMBOLS
0209 322 :
0209 323 : PROCESS THE TOKENS ON THE COMMAND LINE.
0209 324 :
0209 325 :
0209 326 10$: BSBW DCL$GETDVAL ;SKIP PAST /KEY DESCRIPTOR
020F 327 CMPB #PTR_K_ENDLINE,R5 ;GET NEXT DESCRIPTOR VALUES
0212 328 BNEQ 15$ ;EOL?
0214 329 BRW 50$ ;NO, CONTINUE PARSING
0217 330 15$: CMPB #PTR_K_PARAMETR,R5 ;YES, THEN DONE PARSING
021A 331 BNEQ 20$ ;ITEM TYPE PARAMETER?
021C 332 MOVQ R1,R6 ;NO, THEN PROCESS QUALIFIER
021F 333 BICL #2,(SP) ;SAVE PARAMETER DESCRIPTOR
0222 334 BRB 10$ ;CLEAR /ALL FLAG
0224 335 20$: BSBW DCL$GETNVAL ;GET NEXT TOKEN
0227 336 CMPL R1,#CLISK_DELK_LOG ;GET QUALIFIER NUMBER
022E 337 BEQL 25$ ;QUALIFIER MATCH?
0230 338 CMPL R1,#CLISK_DELK_STAT ;YES, THEN PROCESS
0237 339 BEQL 30$ ;QUALIFIER MATCH?
0239 340 BRB 10$ ;YES, THEN PROCESS
023B 341 : ;GET NEXT
023B 342 25$: BISL #1,(SP) ;ASSUME /LOG
023E 343 BBC #PTR_V_NEGATE-PTR_V_FLAGS,R3,10$ ;IGNORE IF NOT /NOLOG
0242 344 BICL #1,(SP) ;CLEAR FLAG
0245 345 BRB 10$ ;GET NEXT
0247 346 :
0247 347 30$: CLRL R8 ;ASSUME /NOSTATE
0249 348 BBS #PTR_V_NEGATE-PTR_V_FLAGS,R3,10$ ;IGNORE IF NOT /STATE
024D 349 MOVL WRK_C_RSLNXT(R10),R8 ;SAVE VALUE TOKEN PTR
0251 350 32$: BSBW DCL$GETDVAL ;GET NEXT DESCRIPTOR VALUE
0254 351 CMPL #PTR_K_COMMA,R4 ;TERMINATOR A COMMA?

```

```

F8 13 0257 352          BEQL 32$          :GET NEXT VALUE
B1 11 0259 353          BRB 10$          :GET NEXT
      025B 354
      025B 355
      025B 356 : SET KEYPAD STATE.
      025B 357
      025B 358 50$: ASSUME PTR K COMMA NE 0
BA AA 58 D0 025B 359      MOVL R8,RRR_L_RSLNXT(R10) :RESET FOR FIRST STATE VALUE
      09 13 025F 360      BEQL 53$          :SKIP IF NONE
      FD9C' 30 0261 361 52$: BSBW DCL$GETDVAL :GET NEXT DESCRIPTOR VALUE
      58 54 D0 0264 362      MOVL R4,R8 :SAVE THE TERMINATOR
      052A 30 0267 363      BSBW DCL$ALLOC_STATE :SET NEW STATE
      026A 364
      026A 365 : DETERMINE WHETHER DELETING ONE SYMBOL OR /ALL SYMBOLS.
      026A 366
      40 6E 01 E0 026A 367 53$: BBS #1,(SP),60$ :BRANCH IF /ALL
      026E 368
      026E 369
      026E 370 : FIND SPECIFIED SINGLE SYMBOL VALUE.
      026E 371
      51 56 7D 026E 372 54$: MOVQ R6,R1 :GET DESCRIPTOR OF SYMBOL NAME
      50 6E D0 0271 373      MOVL (SP),R0 :GET /LOG FLAG
      03DA 30 0274 374      BSBW DCL$SYNONYM :CHECK FOR SYNONYM KEY NAME
      56 51 7D 0277 375      MOVQ R1,R6 :SAVE DESCRIPTOR IN CASE OF UNDKY
      0461 30 027A 376      BSBW DCL$FIND_KEYPAD :SEARCH FOR SYMBOL
      08 50 E8 027D 377      BLBS R0,55$ :BRANCH IF SUCCESSFUL
      0280 378
      0280 379
      0280 380 : OUTPUT WARNING MESSAGE.
      0280 381
      6E 04 C8 0280 382      BISL #4,(SP) :SET UNDEFINED SYMBOL FLAG
      0078 30 0283 383      BSBW UNDKY :OUTPUT UNDEFINED KEY MSG
      03 11 0286 384      BRB 58$ :GET NEXT TABLE
      0288 385
      0288 386
      0288 387 : OUTPUT LOG MESSAGE IF REQUESTED. DELETE THE SYMBOL.
      0288 388
      0057 30 0288 389 55$: BSBW DELKEY :OUTPUT DELKEY MSG AND DELETE THE KEY
      58 05 D1 028B 390 58$: CMPL #PTR_K_COMMA,R8 :TERMINATOR A COMMA?
      05 12 028E 391      BNEQ 90$ :NO, TIME TO EXIT
      FD6D' 30 0290 392      BSBW DCL$LOCKED_STATE :YES, RESTORE LOCKED KEY STATE
      CC 11 0293 393      BRB 52$ :BEFORE GETTING NEXT STATE
      0295 394 :GET NEXT STATE
      0295 395
      0295 396
      0295 397 : RESTORE KEYPAD STATE, SET STATUS, AND EXIT.
      0295 398
      0295 399 90$: STATUS NORMAL :ASSUME SUCCESSFUL COMPLETION
      51 8E D0 029C 400      MOVL (SP)+,R1 :GET FLAGS
      07 51 02 E1 029F 401      BBC #2,R1,95$ :BRANCH IF NO UNDEFINED SYMBOLS
      50 10038260 8F D0 02A3 402      MOVL #CLIS_UNDKY!STSM_INHIB MSG,R0 ;SET STATUS, INHIBIT RESIGNAL
      FD53' 30 02AA 403 95$: BSBW DCL$LOCKED_STATE :RESTORE KEY STATE
      U5 02AD 404      RSB
      02AE 405
      02AE 406
      02AE 407 : DELETE ALL SYMBOL ENTRIES FOR THE SPECIFIED OR CURRENT STATE.
      02AE 408

```

```

56 40 AB 7E 02AE 409 60$: MOVAB PRC_Q_KEYPAD(R11),R6 ;GET ADDRESS OF KEYPAD SYMBOL TABLE
5C 56 56 D0 02B2 410 MOVBL R6,AP ;COPY ADDRESS OF TABLE LISTHEAD
02B5 411
02B5 412
02B5 413 : GET NEXT SYMBOL.
02B5 414
56 66 D0 02B5 415 70$: MOVBL (R6),R6 ;GET ADDRESS OF NEXT ENTRY
5C 56 D1 02B8 416 CMPL R6,AP ;END OF TABLE?
CE 13 02BB 417 BEQL 58$ ;IF EQL YES
02BD 418
02BD 419
02BD 420 : IF STATE DOES NOT MATCH, THEN SKIP THIS SYMBOL.
02BD 421
54 0C A6 9E 02BD 422 MOVAB SYM_T_SYMBOL(R6),R4 ;GET ADDRESS OF SYMBOL NAME
51 84 9A 02C1 423 MOVZBL (R4)+,R1 ;GET LENGTH OF SYMBOL NAME
54 02 A441 9E 02C4 424 MOVAB 2(R4)[R1],R4 ;GET ADDRESS OF IF_STATE
52 48 AB D0 02C9 425 MOVBL PRC_L_CURRKEY(R11),R2 ;GET CURRENT STATE LENGTH/ADDRESS
51 82 9A 02CD 426 MOVZBL (R2)+,R1
84 51 91 02D0 427 CMPB R1,(R4)+ ;STATE LENGTH THE SAME?
E0 12 02D3 428 BNEQ 70$ ;IF DIFF THEN GET NEXT
64 62 51 29 02D5 429 CMPC R1,(R2),(R4) ;STATES MATCH?
DA 12 02D9 430 BNEQ 70$ ;NO, THEN GET NEXT
02DB 431
02DB 432
02DB 433 : STATE DID MATCH. OUTPUT LOG MESSAGE IF REQUESTED. DELETE THE SYMBOL.
02DB 434
53 56 D0 02DB 435 MOVBL R6,R3 ;COPY SYMBOL ADDRESS
02 10 02DE 436 BSBB DELKEY ;OUTPUT LOG MESSAGE AND DELETE THE KEY
CC 11 02E0 437 BRB 60$ ;GET NEXT

```

```

02E2 439 :+
02E2 440 : DELKEY - OUTPUT THE DELKEY /LOG MESSAGE AND DELETE THE SPECIFIED KEY.
02E2 441 :-
02E2 442 DELKEY:
14 04 AE E9 02E2 443 BLBC 4(SP),80$ ;OUTPUT DELKEY MSG AND DELETE THE KEY
7E 0C A3 9E 02E2 444 MOVAB SYM_T_SYMBOL(R3),-(SP) ;SKIP IF /NOLOG SPECIFIED
48 AB DD 02EA 445 PUSHL PRC_L_CURRKEY(R11) ;SET ADDR OF ASCIC STRING
51 02 DO 02ED 446 MOVL #2,R1 ;SET ADDRESS OF ASCIC STATE NAME
50 0003DDCB 8F DO 02F0 447 MOVL #CLIS$ DELKEY,R0 ;SET FAO COUNT
FD06' 30 02F7 448 MOVL DCL$FORMMSG ;SET STATUS
FD03' 30 02FA 449 80$: BSBW DCL$FORMMSG ;OUTPUT THE MESSAGE
05 02FD 450 RSB DCL$DEALLOCESYM ;DEALLOCATE KEYPAD ENTRY
;RETURN
  
```

```
02FE 452 :+
02FE 453 : UNDKEY - OUTPUT THE UNDKEY WARNING MESSAGE.
02FE 454 :-
02FE 455 UNDKEY:
7E 56 7D 02FE 456 MOVQ R6,-(SP) ;OUTPUT UNDKEY WARNING
5E DD 0301 457 PUSHL SP ;PUSH DESC OF SYMBOL NAME
48 AB DD 0303 458 PUSHL PRC L_CURRKEY(R11) ;PUSH DESCR ADDRESS
51 02 DO 0306 459 MOVL #2,R1- ;PUSH ADDR OF ASCII STATE
50 00038260 8F DO 0309 460 MOVL #CLIS UNDKEY,R0 ;SET FAO COUNT
FCED' 30 0310 461 BSBW DCL$FORMMSG ;SET UNDEFINED SYMBOL STATUS
5E 08 CO 0313 462 ADDL #8,SP ;OUTPUT THE MESSAGE
OS 0316 463 RSB ;RESTORE THE STACK
;RETURN
```

```

0317 465 .SBTTL SHOW KEYPAD SYMBOL TABLE ENTRIES
0317 466 :+
0317 467 : DCL$SHOWKEY - SHOW KEYPAD SYMBOL TABLE ENTRIES
0317 468 :
0317 469 : THIS ROUTINE IS CALLED AS AN INTERNAL COMMAND TO EXECUTE THE SHOW KEYS
0317 470 : COMMAND.
0317 471 :
0317 472 : INPUTS:
0317 473 :
0317 474 : R8 = ADDRESS OF SCRATCH BUFFER DESCRIPTOR.
0317 475 : R9 = ADDRESS OF SCRATCH STACK.
0317 476 : R10 = BASE ADDRESS OF COMMAND WORK AREA.
0317 477 : R11 = BASE ADDRESS OF PROCESS WORK AREA.
0317 478 :
0317 479 : OUTPUTS:
0317 480 :
0317 481 : THE SPECIFIED KEYPAD SYMBOL TABLE ENTRY OR ALL KEYPAD SYMBOL TABLE
0317 482 : ENTRIES FOR THE CURRENT OR SPECIFIED STATE ARE WRITTEN TO THE OUTPUT
0317 483 : STREAM.
0317 484 :-
0317 485
0317 486 DCL$SHOWKEY:: ;SHOW KEYPAD SYMBOL TABLE ENTRIES
0317 487 :
0317 488 : INIT PARSE STATE.
0317 489 : FLAG BITS ARE: 0 = /ALL, 1 = /BRIEF, 2 = FIRST STATE,
0317 490 : 3 = UNDKY, 4 = /DIRECTORY.
0317 491 :
0317 492 : PUSHL #1 ;INIT MESSAGE FLAG (ASSUME /LOG)
0317 493 : CLRL -(SP) ;CLEAR STATE TOKEN PTR
0317 494 : MOVL #2,-(SP) ;INIT FLAGS (ASSUME /ALL /BRIEF)
0317 495 : CLRQ R6 ;ZERO DESCRIPTOR OF SYMBOL NAME
0317 496
0317 497 :
0317 498 : PROCESS THE TOKENS ON THE COMMAND LINE.
0317 499 :
0317 500 10$: BSBW DCL$GETDVAL ;GET NEXT DESCRIPTOR VALUE
0317 501 : CMPB #PTR_K_ENDLINE,R5 ;END OF LINE?
0317 502 : BEQL 11$ ;BRANCH IF SO
0317 503 : CMPB #PTR_K_PARAMETR,R5 ;PARAMETER?
0317 504 : BNEQ 12$ ;BRANCH IF QUALIFIER
0317 505 : ASSUME PTR_V_KEYWORD EQ 21
0317 506 : BBS #1,R3,10$ ;SKIP IF OPTION KEYWORD
0317 507 : MOVQ R1,R6 ;SAVE DESCRIPTOR OF SYMBOL NAME
0317 508 : BISL #1,(SP) ;INDICATE NOT /ALL
0317 509 : BRB 10$ ;GET NEXT TOKEN
0317 510 11$: BRW 20$ ;AT END OF LINE. EXECUTE COMMAND
0317 511 :
0317 512 :
0317 513 : PROCESS QUALIFIERS.
0317 514 :
0317 515 12$: BSBW DCL$GETNVAL ;GET QUALIFIER NUMBER
0317 516 : CMPL R1,#CLISK_SHKY_FULL ;/FULL QUALIFIER?
0317 517 : BEQL 16$ ;YES, THEN PROCESS
0317 518 : CMPL R1,#CLISK_SHKY_BRIE ;/BRIEF QUALIFIER?
0317 519 : BEQL 18$ ;YES, THEN PROCESS
0317 520 : CMPL R1,#CLISK_SHKY_DIRE ;/DIRECTORY QUALIFIER?
0317 521 : BEQL 19$ ;YES, THEN PROCESS

```

01 DD
7E 02 D0
56 7C

FCDD' 30
55 04 91
11 13
55 03 91
OF 12

EF 53 01 E0
56 51 7D
6E 01 C8
E7 11
007A 31

FCC1' 30
0000000'8F 51 D1
48 13
0000000'8F 51 D1
48 13
0000000'8F 51 D1
4F 13


```

00000000'8F 51 D1 035A 522      CMPL  R1,#CLISK_SHKY_LOG      ;/LOG QUALIFIER?
                1F 13 0361 523      BEQL  14$                      ;YES, THEN PROCESS
00000000'8F 51 D1 0363 524      CMPL  R1,#CLISK_SHKY_STAT    ;/STATE QUALIFIER?
                B4 12 036A 525      BNEQ  10$                      ;NO, THEN IGNORE
                036C 526
                036C 527
                036C 528      : PROCESS /STATE=state QUALIFIER.
                036C 529
                04 AE D4 036C 530      CLRL  4(SP)                      ;ASSUME /NOSTATE
AD 53 00 E0 036F 531      BBS   #PTR_V_NEGATE-PTR_V_FLAGS,R3,10$ ;IGNORE IF NOT /STATE
04 AE BA AA D0 0373 532      MOVL  WRK [RSLNXT(R10),4(SP) ;SAVE VALUE TOKEN PTR
                FC85' 30 0378 533 13$: BSBW  DCL$GETDVAL ;GET NEXT DESCRIPTOR VALUE
                54 05 D1 037B 534      CMPL  #PTR_K_COMMA,R4 ;TERMINATOR A COMMA?
                F8 13 037E 535      BEQL  13$                      ;GET NEXT VALUE
                9E 11 0380 536      BRB   10$                      ;GET NEXT
                0382 537
                0382 538      : PROCESS /LOG QUALIFIER
                0382 539
                0382 540
                08 AE 01 C8 0382 541 14$: BISL  #1,8(SP) ;ASSUME /LOG
                96 53 00 E1 0386 542      BBC   #PTR_V_NEGATE-PTR_V_FLAGS,R3,10$ ;IGNORE IF /NOLOG
                08 AE 01 CA 038A 543      BICL  #1,8(SP) ;SET FLAG TO /NOLOG
                90 11 038E 544      BRB   10$                      ;GET NEXT TOKEN
                0390 545
                0390 546      : PROCESS /FULL /BRIEF AND /DIRECTORY QUALIFIERS.
                0390 547
                6E 02 CA 0390 548 16$: BICL  #2,(SP) ;ASSUME /FULL
                89 53 00 E1 0393 549      BBC   #PTR_V_NEGATE-PTR_V_FLAGS,R3,10$ ;IGNORE IF NOT /NOBRIEF
                6E 02 C8 0397 550      BISL  #2,(SP) ;SET FLAG
                84 11 039A 551      BRB   10$                      ;GET NEXT
                6E 02 C8 039C 552 18$: BISL  #2,(SP) ;ASSUME /BRIEF
                10 53 00 E1 039F 553      BBC   #PTR_V_NEGATE-PTR_V_FLAGS,R3,190$ ;IGNORE IF NOT /NOBRIEF
                6E 02 CA 03A3 554      BICL  #2,(SP) ;CLEAR FLAG
                FF77 31 03A6 555      BRW   10$                      ;GET NEXT
                6E 10 C8 03A9 556 19$: BISL  #16,(SP) ;ASSUME /DIRECTORY
                03 53 00 E1 03AC 557      BBC   #PTR_V_NEGATE-PTR_V_FLAGS,R3,190$ ;IGNORE IF NOT /NODIRECTORY
                6E 10 CA 03B0 558      BICL  #16,(SP) ;CLEAR FLAG
                FF6A 31 03B3 559 190$: BRW   10$                      ;GET NEXT
                03B6 560
                03B6 561      : EXECUTE /DIRECTORY.
                03B6 562
                03B6 563
                3E 6E 04 E1 03B6 564 20$: BBC   #4,(SP),21$ ;BRANCH IF /NODIRECTORY
                5C 40 AB 7E 03BA 565      MOVAQ PRC_Q_KEYPAD(R11),AP ;GET ADDRESS OF KEYPAD SYMBOL TABLE
                5C 56 7C 03C0 566      PUSHL AP ;SAVE R6
                5C 6C D0 03C2 568 210$: CLRQ  R6 ;SET INITIAL STATE DESCRIPTOR
                6E 5C D1 03C5 569      MOVL  (AP),AP ;GET ADDRESS OF NEXT ENTRY
                2A 13 03C8 570      CMPL  AP,(SP) ;END OF TABLE?
                51 0C AC 9A 03CA 571      BEQL  230$ ;IF EQL, THEN DONE
                52 0F AC41 9E 03CE 572      MOVZBL SYM_T_SYMBOL(AP),R1 ;GET LENGTH OF SYMBOL
                51 82 9A 03D3 573      MOVAB SYM_T_SYMBOL+3(AP)[R1],R2 ;GET ADDRESS OF IF STATE LENGTH
                56 51 D1 03D6 574      MOVZBL (R2)+,R1 ;GET IF STATE LENGTH
                11 12 03D9 575      CMPL  R1,R6 ;STATES MATCH
                7E 51 7D 03DB 576      BNEQ  220$ ;NO, LIST IT
                67 62 51 29 03DE 577      MOVQ  R1,-(SP) ;SAVE STATE DESCRIPTOR
                05 12 03E2 578      CMPC3 R1,(R2),(R7) ;STATES MATCH?
                BNEQ  215$ ;NO, THEN OUTPUT THE STATE

```

```

51 8E 7D 03E4 579      MOVQ   (SP)+,R1      ;RESTORE STATE DESCRIPTOR
   D9 11 03E7 580      BRB    210$          ;YES, THEN SKIP
51 8E 7D 03E9 581 215$: MOVQ   (SP)+,R1      ;RESTORE STATE DESCRIPTOR
56 51 7D 03EC 582 220$: MOVQ   R1,R6        ;SAVE NEW STATE
   FCOE' 30 03EF 583      BSBW   DCL$MSGOUT    ;OUTPUT THE STATE
   CE 11 03F2 584      BRB    210$          ;GET NEXT STATE
   8E D5 03F4 585 230$: TSTL   (SP)+        ;RESTORE THE STACK
   49 11 03F6 586      BRB    90$           ;EXIT
   03F8 587
   03F8 588 :
   03F8 589 : SET KEYPAD STATE.
   03F8 590 :
   03F8 591 :
BA AA 04 AE D0 03F8 592 21$: ASSUME PTR_K_COMMA NE 0
   OA 13 03FD 593      MOVL   4(SP),WRK_/_RSLNXT(R10) ;RESET FOR FIRST STATE VALUE
   FBFE' 30 03FF 594 22$: BSBW   DCL$GETDVAL    ;SKIP IF NONE
04 AE 54 D0 0402 595      MOVL   R4,4(SP)      ;GET NEXT DESCRIPTOR VALUE
   038B 30 0406 596      BSBW   DCL$ALLOC_STATE ;SAVE THE TERMINATOR
   0409 597 :           ;SET NEW STATE
   0409 598 : DETERMINE WHETHER DISPLAYING ONE SYMBOL OR /ALL SYMBOLS.
   0409 599 :
   51 6E E9 0409 600 23$: BLBC   (SP),40$      ;BRANCH IF /ALL
   040C 601 :
   040C 602 :
   040C 603 : DISPLAY SPECIFIED SINGLE SYMBOL VALUE.
   040C 604 :
50 51 56 7D 040C 605      MOVQ   R6,R1        ;GET DESCRIPTOR OF SYMBOL NAME
   08 AE D0 040F 606      MOVL   8(SP),R0      ;GET /LOG FLAG
   023B 30 0413 607      BSBW   DCL$SYNONYM    ;CHECK FOR SYNONYM KEY NAMES
56 51 7D 0416 608      MOVQ   R1,R6        ;SAVE DESCRIPTOR IN CASE OF UNDKY
   02C2 30 0419 609      BSBW   DCL$FIND_KEYPAD ;FIND SPECIFIED SYMBOL
   11 50 E8 041C 610      BLBS   R0,35$      ;BRANCH IF FOUND
   041F 611 :
   041F 612 :
   041F 613 : OUTPUT WARNING MESSAGE.
   041F 614 :
05 6E 02 E3 041F 615      BBCS   #2,(SP),33$      ;SKIP BLANK LINE IF FIRST LINE
   51 7C 0423 616      CLRQ   R1           ;SET NULL STRING
   FBDB' 30 0425 617      BSBW   DCL$MSGOUT    ;OUTPUT THE BLANK LINE
6E 08 C8 0428 618 33$: BISL   #8,(SP)      ;SET UNDEFINED SYMBOL FLAG
   FED0 30 042B 619      BSBW   UNDKY        ;OUTPUT UNDEFINED KEY MSG
   06 11 042E 620      BRB    38$           ;GET NEXT TABLE
   0430 621 :
   0430 622 :
   0430 623 : DISPLAY THE SYMBOL DATA.
   0430 624 :
   0150 30 0430 625 35$: BSBW   DISPHDR      ;DISPLAY KEYPAD TABLE NAME
   0060 30 0433 626      BSBW   DISPSYMB     ;DISPLAY THE SYMBOL DATA
04 AE 05 D1 0436 627 38$: CMPL   #PTR_K_COMMA,4(SP) ;TERMINATOR A COMMA?
   05 12 043A 628      BNEQ   90$           ;NO, TIME TO EXIT
   FBC1' 30 043C 629      BSBW   DCL$LOCKED_STATE ;YES, RESTORE LOCKED KEY STATE
   BE 11 043F 630      BSBW   DCL$LOCKED_STATE ;BEFORE GETTING NEXT STATE
   0441 631      BRB    22$           ;GET NEXT STATE
   0441 632 :
   0441 633 :
   0441 634 : RESTORE KEYPAD STATE, SET NORMAL STATUS, AND EXIT.
   0441 635 :

```

```

0441 636 90$: STATUS NORMAL ;ASSUME SUCCESSFUL COMPLETION
0448 637 MOVL (SP)+,R1 ;GET FLAGS
044B 638 BBC #3,R1,95$ ;BRANCH IF NO UNDEFINED SYMBOLS
044F 639 MOVL #CLIS_UNDKEY!STSM_INHIB_MSG,R0 ;SET STATUS, INHIBIT RESIGNAL
0456 640 95$: ADDL #8,SP ;RESTORE THE STACK
0459 641 BSBW DCL$LOCKED_STATE ;RESTORE KEY STATE
045C 642 RSB
045D 643
045D 644
045D 645 ; DISPLAY ALL SYMBOL ENTRIES FOR THE SPECIFIED OR CURRENT STATE.
045D 646
045D 647 40$: BSBW DISPHDR ;DISPLAY KEYPAD TABLE NAME
0460 648 MOVAQ PRC_Q_KEYPAD(R11),R6 ;GET ADDRESS OF KEYPAD SYMBOL TABLE
0464 649 MOVL R6,AP ;COPY ADDRESS OF TABLE LISTHEAD
0467 650
0467 651 ; GET NEXT SYMBOL.
0467 652
0467 653
0467 654 50$: MOVL (R6),R6 ;GET ADDRESS OF NEXT ENTRY
046A 655 CMPL R6,AP ;END OF TABLE?
046D 656 BEQL 38$ ;IF EQL YES
046F 657
046F 658
046F 659 ; IF STATE DOES NOT MATCH, THEN SKIP THIS SYMBOL.
046F 660
046F 661 MOVAB SYM_T_SYMBOL(R6),R4 ;GET ADDRESS OF SYMBOL NAME
0473 662 MOVZBL (R4)+,R1 ;GET LENGTH OF SYMBOL NAME
0476 663 MOVAB 2(R4)[R1],R4 ;GET ADDRESS OF IF STATE
047B 664 MOVZBL (R4)+,R0 ;GET IF STATE LENGTH
047E 665 MOVL PRC_L_CURRKEY(R11),R2 ;GET CURRENT STATE LENGTH/ADDRESS
0482 666 MOVZBL (R2)+,R1
0485 667 CMPCS R1,(R2),#0,R0,(R4) ;STATES MATCH?
048B 668 65$: BLSS 38$ ;NO, GET NEXT STATE
048D 669 BGTR 50$ ;NO, GET NEXT SYMBOL
048F 670
048F 671
048F 672 ; STATE DID MATCH. DISPLAY THE SYMBOL.
048F 673
048F 674 70$: MOVL R6,R3 ;SET ADDRESS OF SYMBOL
0492 675 BSBB DISPSYMB ;FORMAT AND OUTPUT ENTRY
0494 676 BRB 50$ ;GET NEXT

```

```

0496 678 :+
0496 679 : DISPSYMB - DISPLAY THE VALUE AND ATTRIBUTES OF A GIVEN KEYPAD SYMBOL.
0496 680 :
0496 681 : INPUTS:
0496 682 :
0496 683 : 4(SP) = FLAGS LONGWORD - BIT 1 IS SET IF /BRIEF
0496 684 : R3 = ADDRESS OF SYMBOL TABLE ENTRY
0496 685 : R8 = ADDRESS OF SCRATCH BUFFER DESCRIPTOR.
0496 686 : R9 = ADDRESS OF SCRATCH STACK.
0496 687 : -
0496 688 DISPSYMB: ;FORMAT A SYMBOL
50 04 AE DO 0496 689 MOVL 4(SP),R0 ;GET THE FLAGS
02C0 8F BB 049A 690 PUSHR #*M<R6,R7,R9> ;SAVE REGISTERS
68 DD 049E 691 PUSHL (R8) ;SAVE SCRATCH DESCR LENGTH
58 58 DD 04A0 692 PUSHL R8 ;SAVE ADDR OF SCRATCH DESCR
50 DO 04A2 693 MOVL R0,R8 ;COPY THE FLAGS
04A5 694
04A5 695 :
04A5 696 : GET AND SAVE DESCRIPTOR OF SYMBOL NAME.
04A5 697 :
52 0C A3 9E 04A5 698 MOVAB SYM_T_SYMBOL(R3),R2 ;POINT TO SYMBOL NAME
51 82 9A 04A9 699 MOVZBL (R2)+,R1 ;GET NAME LENGTH
79 51 7D 04AC 700 MOVQ R1,-(R9) ;BUILD NAME DESCRIPTOR
57 59 DO 04AF 701 MOVL R9,R7 ;COPY SCRATCH STACK POINTER
04B2 702
04B2 703 :
04B2 704 : GET AND SAVE DESCRIPTOR OF SYMBOL VALUE.
04B2 705 :
52 02 A241 9E 04B2 706 MOVAB 2(R2)[R1],R2 ;GET ADDRESS OF IF STATE LENGTH
51 82 9A 04B7 707 MOVZBL (R2)+,R1 ;GET LENGTH OF IF STATE
52 6241 9E 04BA 708 MOVAB (R2)[R1],R2 ;GET ADDRESS OF SYMBOL VALUE LENGTH
51 82 3C 04BE 709 MOVZWL (R2)+,R1 ;GET LENGTH/ADDRESS OF VALUE
79 51 7D 04C1 710 MOVQ R1,-(R9) ;SAVE VALUE DESCRIPTOR
56 59 DO 04C4 711 MOVL R9,R6 ;COPY SCRATCH STACK POINTER
04C7 712
04C7 713 :
04C7 714 : GET AND SAVE DESCRIPTOR OF SET_STATE STRING.
04C7 715 :
52 6241 9E 04C7 716 MOVAB (R2)[R1],R2 ;GET ADDRESS OF SET_STATE LENGTH
51 82 9A 04CB 717 MOVZBL (R2)+,R1 ;GET LENGTH/ADDRESS OF STATE
02 58 01 E1 04CE 718 BBC #1,R8,10$ ;SKIP IF /NOBRIEF
79 51 D4 04D2 719 CLRL R1 ;PUSH NULL STRING
55 59 DO 04D4 720 10$: MOVQ R1,-(R9) ;SAVE STATE DESCRIPTOR
04D7 721 MOVL R9,R5 ;COPY SCRATCH STACK POINTER
04DA 722
04DA 723 :
04DA 724 : CREATE AND SAVE DESCRIPTOR OF ASCII FAO STRING. OUTPUT WILL LOOK LIKE:
04DA 725 :
04DA 726 : symbol = "value" (ECHO,TERMINATE,ERASE,LOCK,STATE=state)
04DA 727 :
52 FB48 CF 9E 04DA 728 MOVAB FULLFAO,R2 ;ASSUME FULL DISPLAY
05 58 01 E1 04DF 729 BBC #1,R8,20$ ;SKIP IF /NOBRIEF
52 FB31 CF 9E 04E3 730 MOVAB BRIEFFAO,R2 ;SET BRIEF DISPLAY
51 82 9A 04E8 731 20$: MOVZBL (R2)+,R1 ;MAKE INTO DESCRIPTOR
79 51 7D 04EB 732 MOVQ R1,-(R9) ;AND PUSH ONTO STACK
54 59 DO 04EE 733 MOVL R9,R4 ;COPY SCRATCH STACK POINTER
21 58 01 E0 04F1 734 BBS #1,R8,30$ ;SKIP IF /BRIEF

```

```

04F5 735
04F5 736
04F5 737 : CREATE FAO PARAMETER LIST. ASSUME NO ATTRIBUTES.
04F5 738 :
79 79 55 DO 04F5 739 : MOVL R5,-(R9) ;SET ADDR OF STATE DESCR
79 FB74 CF 9E 04F8 740 : MOVAB NULL,-(R9) ;ASSUME STATE FLAG NOT SET
79 FB6F CF 9E 04FD 741 : MOVAB NULL,-(R9) ;ASSUME STATE FLAG NOT SET
79 FB6A CF 9E 0502 742 : MOVAB NULL,-(R9) ;ASSUME LOCK FLAG SET
79 FB65 CF 9E 0507 743 : MOVAB NULL,-(R9) ;ASSUME ERASE FLAG SET
79 FB60 CF 9E 050C 744 : MOVAB NULL,-(R9) ;ASSUME TERMINATE FLAG SET
79 FB5B CF 9E 0511 745 : MOVAB NULL,-(R9) ;ASSUME ECHO FLAG SET
79 79 56 DO 0516 746 30$: MOVL R6,-(R9) ;SET ADDR OF VALUE DESCR
79 79 57 DO 0519 747 : MOVL R7,-(R9) ;SET ADDR OF NAME DESCR
57 59 DO 051C 748 : MOVL R9,R7 ;SAVE ADDRESS OF PARAMETER LIST
051F 749
051F 750
051F 751 : NOW RESET FAO ARGUMENTS FOR ANY ATTRIBUTES THAT WERE ABSENT.
051F 752 :
03 58 01 E1 051F 753 : BBC #1,R8,40$ ;SKIP IF /NOBRIEF
003D 31 0523 754 : BRW 90$ ;BRANCH IF /BRIEF
0526 755
06 0B 00 E0 0526 756 40$: BBS #SYM V ECHO,- ;IS ECHO SET?
08 A9 06 0B A3 0528 757 : SYM B FLAGS(R3),50$
FB37 CF 9E 052B 758 : MOVAB NO,8(R9)
0531 759
06 0B 01 E0 0531 760 50$: BBS #SYM V TERMINATE,- ;IS TERMINATE SET?
08 A9 06 0B A3 0533 761 : SYM B FLAGS(R3),60$
FB2C CF 9E 0536 762 : MOVAB NO,T2(R9)
053C 763
06 0B 04 E0 053C 764 60$: BBS #SYM V ERASE,- ;IS ERASE SET?
10 A9 06 0B A3 053E 765 : SYM B FLAGS(R3),70$
FB21 CF 9E 0541 766 : MOVAB NO,T6(R9)
0547 767
06 0B 03 E0 0547 768 70$: BBS #SYM V LOCK,- ;IS LOCK SET?
14 A9 06 0B A3 0549 769 : SYM B FLAGS(R3),80$
FB16 CF 9E 054C 770 : MOVAB NO,20(R9)
0552 771
06 0B 02 E1 0552 772 80$: BBC #SYM V STATE,- ;IS STATE SET?
18 A9 06 0B A3 0554 773 : SYM B FLAGS(R3),90$
1C A9 06 0B CF 9E 0557 774 : MOVAB COMMA,24(R9)
FB08 CF 9E 055D 775 : MOVAB STATE,28(R9)
0563 776
0563 777
0563 778 : FORMAT AND OUTPUT THE MESSAGE
0563 779
58 8ED0 0563 780 90$: POPL R8 ;RESTORE SCRATCH DESCRIPTOR
0566 781 : $FAOL_S (R4),(R8),(R8),(R7) ;FORMAT OUTPUT MESSAGE
51 68 7D 0575 782 : MOVQ (R8),R1 ;GET OUTPUT MESSAGE PARAMETERS
FAB5 30 0578 783 : BSBW DCL$MSGOUT ;OUTPUT THE MESSAGE
68 8ED0 057B 784 : POPL (R8) ;RESTORE SCRATCH DESCR LENGTH
02C0 8F BA 057E 785 : POPR #^M<R6,R7,R9> ;RESTORE REGISTERS
05 0582 786 : RSB ;RETURN

```

```

0583 788 :+
0583 789 : DISPHDR - DISPLAY A KEYPAD TABLE HEADER
0583 790 :
0583 791 : INPUTS:
0583 792 :
0583 793 : 4(SP) = FLAGS LONGWORD - BIT 2 IS CLEAR IF FIRST TABLE
0583 794 : R8 = ADDRESS OF SCRATCH BUFFER DESCRIPTOR.
0583 795 : R9 = ADDRESS OF SCRATCH STACK.
0583 796 : PRC_L_CURRKEY(R11) = ADDRESS OF ASCIC TABLE NAME
0583 797 :-
0583 798 DISPHDR:
05 04 AE 02 E3 0583 799 BBCS #2,4(SP),10$ :DISPLAY KEYPAD TABLE HEADER
51 51 7C 0588 800 CLRQ R1 :SKIP BLANK LINE IF FIRST HEADER
FA73' 30 058A 801 BSBW DCL$MSGOUT :SET NULL STRING
68 DD 058D 802 10$: PUSHL (R8) :OUTPUT THE BLANK LINE
52 FA6D CF 9E 058F 803 MOVAB SHOWHDR,R2 :SAVE BUFFER SIZE
51 51 82 9A 0594 804 MOVZBL (R2)+,R1 :GET ADDRESS OF ASCIC FAO STRING
7E 51 7D 0597 805 MCVQ R1,-(SP) :MAKE INTO DESCRIPTOR
50 5E DO 059A 806 MOVL SP,R0 :AND PUSH ONTO STACK
51 48 AB 9E 059D 807 OVAB PRC_L_CURRKEY(R11),R1 :SAVE ITS ADDRESS
05A1 808 -FAO_S (R0),R8),(R8),(R1) :GET ADDRESS OF ASCIC STATE
51 68 7D 05B0 809 MOVQ (R8),R1 :FORMAT OUTPUT MESSAGE
FA4A' 30 05B3 810 BSBW DCL$MSGOUT :GET OUTPUT MESSAGE PARAMETERS
5E 08 CO 05B6 811 ADDL #8,SP :OUTPUT THE MESSAGE
68 8E DO 05B9 812 MOVL (SP)+,(R8) :RESTORE THE STACK
05 05BC 813 RSB :RESTORE BUFFER SIZE
:RETURN

```

```

05BD 815 .SBTTL ALLOCATE AND INSERT ENTRY IN KEYPAD SYMBOL TABLE
05BD 816 :+
05BD 817 : DCL$ALLOCKEY - ALLOCATE AND INSERT ENTRY IN KEYPAD SYMBOL TABLE
05BD 818 :
05BD 819 : THIS ROUTINE IS CALLED TO ALLOCATE AND INSERT AN ENTRY IN THE KEYPAD
05BD 820 : SYMBOL TABLE.
05BD 821 :
05BD 822 : INPUTS:
05BD 823 :
05BD 824 : R6 = KEYPAD FLAGS
05BD 825 : R9 = ADDRESS OF BUFFER FORMATTED AS FOLLOWS
05BD 826 :
05BD 827 : (R9) = DESCRIPTOR OF SYMBOL VALUE
05BD 828 : 8(R9) = DESCRIPTOR OF SYMBOL NAME
05BD 829 : 16(R9) = DESCRIPTOR OF SET_STATE NAME
05BD 830 :
05BD 831 : R11 = ADDRESS OF PROCESS WORK AREA
05BD 832 : PRC_L_CURRKEY = STATE IN WHICH KEY IS TO BE ALLOCATED
05BD 833 :
05BD 834 : OUTPUTS:
05BD 835 :
05BD 836 : THE KEYPAD TABLE IS SEARCHED FOR THE SPECIFIED ENTRY, AND IF FOUND,
05BD 837 : THE OLD ENTRY IS DEALLOCATED. A SYMBOL TABLE ENTRY IS THEN ALLOCATED,
05BD 838 : FILLED WITH THE SYMBOL, VALUE, AND STATE INFORMATION, AND THEN
05BD 839 : INSERTED IN THE SYMBOL TABLE.
05BD 840 :
05BD 841 : R0 LOW BIT CLEAR INDICATES ALLOCATION FAILURE WITH CLIS_SYMOVF.
05BD 842 : R0 LOW BIT SET INDICATES SUCCESSFUL COMPLETION.
05BD 843 :
05BD 844 : R1,R2,R3,R4,R5 ARE DESTROYED.
05BD 845 :-
05BD 846
05BD 847 DCL$ALLOCKEY::
05BD 848 D:DISABLE ;DISABLE CTRL/Y'S
BE 7C 05C3 849 CLRQ (SP)+ ;REMOVE RETURN INFO FROM STACK
05C5 850
05C5 851 :
05C5 852 : SEARCH FOR PREVIOUS DEFINITION OF IDENTICAL SYMBOL. IF FOUND, THEN
05C5 853 : DEALLOCATE IT. FIND THE SPOT IN THE LINKED LIST TO INSERT THE NEW SYMBOL
05C5 854 : AT.
05C5 855 :
51 08 A9 7D 05C5 856 MOVQ 8(R9),R1 ;SET SYMBOL NAME DESCRIPTOR
0112 30 05C9 857 BSBW DCL$FIND_KEYPAD ;SEARCH FOR SYMBOL
0C 50 E9 05CC 858 BLBC R0,10$ ;IF LBC SEARCH FAILURE
7E 51 7D 05CF 859 MOVQ R1,-(SP) ;SAVE R1/R2
FA2B' 30 05D2 860 BSBW DCL$DEALLOCSYM ;DEALLOCATE KEYPAD ENTRY
51 8E 7D 05D5 861 MOVQ (SP)+,R1 ;RESTORE R1/R2
0103 30 05D8 862 BSBW DCL$FIND_KEYPAD ;SEARCH FOR SYMBOL
05DB 863
05DB 864 :
05DB 865 : CALCULATE SIZE OF NEW SYMBOL AND ALLOCATE IT.
05DB 866 :
51 48 AB D0 05DB 867 10$: MOVL PRC_L_CURRKEY(R11),R1 ;GET ADDR OF ASCII IF STATE
51 51 61 9A 05DF 868 MOVZBL (R1),R1 ;GET LENGTH OF IF STATE
51 10 A9 C0 05E2 869 ADDL 16(R9),R1 ;ADD IN SET STATE LENGTH
51 69 C0 05E6 870 ADDL (R9),R1 ;ADD IN VALUE LENGTH
51 04 C0 05E9 871 ADDL #4,R1 ;ADD IN SIZE OF LENGTH FIELDS

```

```

51 08 A9 DD 05EC 872      PUSHL R1          ;SAVE FOR FUTURE USE
      CO 05EE 873      ADDL 8(R9),R1     ;ADD IN META-KEY LENGTH
51 0F CO 05F2 874      ADDL #SYM_f_SYMBOL+3,R1 ;ADD IN FIXED OVERHEAD
      DD 05F5 875      PUSHL R3          ;SAVE SYMBOL TABLE PTR
      FA06' 30 05F7 876   BSBW DCL$ALLDYNMEM ;ALLOCATE DYNAMIC MEMORY
      53 8ED0 05FA 877   POPL R3         ;RESTORE SYMBOL TABLE PTR
      47 50 E9 05FD 878   BLBC R0,908    ;IF LBC ALLOCATION FAILURE
      0600 879
      0600 880
      0600 881 : INITIALIZE THE STATICALLY PLACED FIELDS AND INSERT IT IN THE LINKED LIST.
      0600 882 :
      08 A2 51 B0 0600 883   MOVW R1,SYM_W_SIZE(R2) ;SET SIZE OF ALLOCATED BLOCK
      08 A2 56 90 0604 884   MOVB R6,SYM_B_FLAGS(R2) ;SET KEYPAD FLAGS
      0A A2 04 90 0608 885   MOVB #SYM_K_KEYPAD,SYM_B_TYPE(R2) ;SET KEYPAD VALUE TYPE
      04 B3 62 0E 060C 886   INSQUE SYM_L_FL(R2),@SYM_L_BL(R3) ;INSERT ENTRY IN SYMBOL TABLE
      0610 887
      0610 888 : INITIALIZE THE DYNAMICALLY PLACED ASCII FIELDS.
      0610 889 :
      0610 890 :
      53 08 A9 7D 0610 891   MOVQ 8(R9),R3 ;GET SYMBOL NAME
      0C A2 53 90 0614 892   MOVB R3,SYM_T_SYMBOL(R2) ;INSERT LENGTH OF SYMBOL
      OD A2 64 53 28 0618 893   MOVC R3,(R4),SYM_T_SYMBOL+1(R2) ;INSERT SYMBOL NAME
      83 8E F7 061D 894   CVTLW (SP)+,(R3)+ ;INSERT LENGTH OF FOLLOWING
      52 48 AB D0 0620 895   ;
      51 82 9A 0620 896   ;
      51 82 9A 0620 897   MOVL PRC_L_CURRKEY(R11),R2 ;GET CURRENT STATE LENGTH/ADDRESS
      83 51 90 0624 898   MOVZBL (R2)+,R1 ;GET LENGTH OF STRING VALUE
      63 62 51 90 0627 899   MOVB R1,(R3)+ ;INSERT LENGTH OF STRING VALUE
      63 62 51 28 062A 900   MOVC R1,(R2),(R3) ;INSERT STRING VALUE
      51 69 7D 062E 901   ;
      83 51 B0 062E 902   MOVQ (R9),R1 ;GET SYMBOL VALUE
      63 62 51 28 0631 903   MOVW R1,(R3)+ ;INSERT LENGTH OF STRING VALUE
      63 62 51 28 0634 904   MOVC R1,(R2),(R3) ;INSERT STRING VALUE
      51 10 A9 7D 0638 905   ;
      83 51 90 0638 906   MOVQ 16(R9),R1 ;GET SET STATE VALUE
      63 62 51 28 063C 907   MOVB R1,(R3)+ ;INSERT LENGTH OF STRING VALUE
      63 62 51 28 063F 908   MOVC R1,(R2),(R3) ;INSERT STRING VALUE
      50 01 D0 0643 909   ;
      05 0643 910   MOVL #1,R0 ;SET SUCCESS INDICATOR
      0646 911   RSB ;
      0647 912   ;
      0647 913 : RETURN SYMBOL TABLE OVERFLOW STATUS.
      0647 914 :
      0647 915 :
      8E D5 0647 916 90$: TSTL (SP)+ ;RESTORE THE STACK
      0649 917   STATUS SYMOVF ;SET SYMBOL TABLE OVERFLOW STATUS
      05 0650 918   RSB ;

```



```

0651 920 .SBTTL CHECK FOR SYNONYM KEY NAMES
0651 921 :+
0651 922 : DCL$SYNONYM - CHECK FOR SYNONYM KEY NAMES
0651 923 :
0651 924 : THIS ROUTINE IS CALLED TO DETERMINE WHETHER OR NOT THE KEY NAME INPUT
0651 925 : HAS A SYNONYM NAME. IF SO, IT TRANSLATES THE KEY NAME TO A COMMON KEY NAME
0651 926 : FOR THAT PARTICULAR KEY, WHICH IS THEN USED IN CONSTRUCTING THE KEYPAD
0651 927 : SYMBOL TABLE. IF /LOG IS SPECIFIED IN THE COMMAND LINE, A CONVERSION MESSAGE
0651 928 : IS OUTPUT INDICATING WHAT THE SYNONYM KEY WAS CHANGED TO IN THE KEYPAD
0651 929 : SYMBOL TABLE.
0651 930 :
0651 931 :
0651 932 : INPUTS:
0651 933 :
0651 934 : R0 = /LOG FLAG (LBS = /LOG, LBC = /NOLOG)
0651 935 : R1 = LENGTH OF ENTERED KEY NAME
0651 936 : R2 = ADDRESS OF ENTERED KEY NAME
0651 937 :
0651 938 : OUTPUTS:
0651 939 :
0651 940 : IF SYNONYM FOUND:
0651 941 :
0651 942 : R1 = LENGTH OF TRANSLATED KEY NAME
0651 943 : R2 = ADDR. OF TRANSLATED KEY NAME
0651 944 :
0651 945 :
0651 946 : IF SYNONYM NOT FOUND:
0651 947 :
0651 948 : R1 UNCHANGED
0651 949 : R2 UNCHANGED
0651 950 :
0651 951 :-
0651 952 :
0651 953 DCL$SYNONYM:
0651 954 MOVQ R6,-(SP) ;SAVE WORK REGISTERS
0651 955 MOVL R0,-(SP) ;SAVE /LOG FLAG
56 FA18 CF 9E 0657 956 MOVAB SYNNAME_TAB,R6 ;GET ADDR OF SYNONYM TABLE
065C 957
57 66 9A 065C 958 10$: MOVZBL (R6),R7 ;GET LENGTH OF THIS ENTRY
7E 56 7D 0654 955 BEQL 100$ ;EXIT IF NO MATCHING ENTRY FOUND
7E 50 DO 0654 955 BEQL 100$ ;EXIT IF NO MATCHING ENTRY FOUND
57 51 B1 0661 960 CMPW R1,R7 ;DOES THE LENGTH MATCH THIS ENTRY?
OF 12 0664 961 BNEQ 40$ ;NO, SKIP TO NEXT ENTRY IN TABLE
7E 51 7D 0666 962 MOVQ R1,-(SP) ;SAVE POINTERS
01 A6 57 00 62 51 2D 0669 963 CMPCS R1,(R2),#0,R7,1(R6) ;IS THERE A MATCH ON THIS ENTRY?
OA 13 0670 964 BEQL 50$ ;YES, GET NEW KEY NAME FROM TRANSLATION TABL
51 8E 7D 0672 965 MOVQ (SP)+,R1 ;RESTORE POINTERS
56 03 A647 9E 0675 966 40$: MOVAB 3(R6)[R7],R6 ;MOVE TO NEXT ENTRY IN SYNONYM TABLE
E0 11 067A 968 BRB 10$
067C 969 :
067C 970 : HAVE FOUND A MATCH IN SYNONYM TABLE. GET ACTUAL KEY NAME FROM TRANSLATION TABLE.
067C 971 :
56 51 8E 7D 067C 972 50$: MOVQ (SP)+,R1 ;RESTORE POINTERS
01 A647 9E 067F 973 MOVAB 1(R6)[R7],R6 ;GET ADDR. OF OFFSET INTO TRANS. TABLE
56 56 66 3C 0684 974 MOVZWL (R6),R6 ;GET ACTUAL OFFSET
56 FA2B CF46 9E 0687 975 MOVAB SYND$F_TAB[R6],R6 ;GET ADDR. OF COMMON KEY NAME STRING
53 51 7D 068D 976 MOVQ R1,R3 ;SAVE ENTERED KEY NAME FOR CONV. MESSAGE.

```

51	86	9A	0690	977	MOVZBL	(R6)+,R1	:FORM DESCRIPTOR FOR TRANS. NAME	
52	66	9E	0693	978	MOVAB	(R6),R2	:	
			0696	979				
			0696	980			: OUTPUT CONVERSION MESSAGE IF /LOG SPECIFIED	
			0696	981			:	
	22	6E	E9	0696	982	BLBC	(SP),100\$:SKIP MESSAGE IF /NOLOG
	5E	10	C2	0699	983	SUBL	#16,SP	:MAKE A TEMPORARY SCRATCH BUFFER
	6E	51	7D	069C	984	MOVQ	R1,(SP)	:GET TRANSLATED KEY NAME
08	AE	53	7D	069F	985	MOVQ	R3,8(SP)	:GET ENTERED KEY NAME
		6E	9F	06A3	986	PUSHAB	(SP)	:SET ADDR. OF TRANS. KEY NAME
	0C	AE	9F	06A5	987	PUSHAB	12(SP)	:SET ADDR. OF ENTERED KEY NAME
	51	02	D0	06A8	988	MOVL	#2,R1	:SET ARGUMENT COUNTER
50	0003DE33	8F	D0	06AB	989	MOVL	#CLIS,KEYCNV,R0	:SET CONVERTED KEY STATUS
		F94B'	30	06B2	990	BSBW	DCL\$FORMMSG	:OUTPUT CONVERSION MESSAGE
	51	6E	7D	06B5	991	MOVQ	(SP),R1	:RESTORE TRANSLATED DESCRIPTOR
	5E	10	C0	06B8	992	ADDL	#16,SP	:REMOVE TEMPORARY SCRATCH BUFFER
				06BB	993			
		8E	D5	06BB	994	100\$: TSTL	(SP)+	:REMOVE /LOG FLAG
	56	8E	7D	06BD	995	MOVQ	(SP)+,R6	:RESTORE WORK REGISTERS
			05	06C0	996	RSB		:EXIT

```

06C1 998 .SBTTL SEARCH FOR SYMBOL ENTRY IN KEYPAD SYMBOL TABLE
06C1 999 :+
06C1 1000 : DCL$SEARCH_KEYPAD - SEARCH FOR SYMBOL ENTRY IN KEYPAD SYMBOL TABLE
06C1 1001 :
06C1 1002 : THIS ROUTINE IS CALLED TO SEARCH THE KEYPAD SYMBOL TABLE FOR AN ENTRY.
06C1 1003 :
06C1 1004 : INPUTS:
06C1 1005 :
06C1 1006 : R11 = ADDRESS OF PROCESS WORK AREA
06C1 1007 :
06C1 1008 : R1 = LENGTH OF SYMBOL.
06C1 1009 : R2 = ADDRESS OF SYMBOL.
06C1 1010 :
06C1 1011 : OUTPUTS:
06C1 1012 :
06C1 1013 : R0 = STATUS
06C1 1014 : R1/R2 = QUADWORD DESCRIBING SYMBOL VALUE:
06C1 1015 : IF R2 NONZERO, QUADWORD IS A STRING DESCRIPTOR
06C1 1016 : IF R2 ZERO, R1 IS A BINARY LONGWORD VALUE
06C1 1017 : R3 = ADDRESS OF SYMBOL ENTRY
06C1 1018 : R4 = KEYPAD FLAGS
06C1 1019 :
06C1 1020 :-
06C1 1021 :
06C1 1022 DCL$SEARCH_KEYPAD:: :SEARCH FOR SYMBOL ENTRY IN KEYPAD TABLE
1B 10 06C1 1023 BSBB DCL$FIND_KEYPAD :SEARCH KEYPAD SYMBOL TABLE FOR ENTRY
17 50 E9 06C3 1024 BLBC R0,10$ :IF LBC NO MATCH FOUND
06C6 1025
51 0C A3 9A 06C6 1026 MOVZBL SYM_T_SYMBOL(R3),R1 :GET LENGTH OF SYMBOL
52 OF A341 9E 06CA 1027 MOVAB SYM_T_SYMBOL+3(R3)[R1],R2 :GET ADDRESS OF IF STATE LENGTH
51 82 9A 06CF 1028 MOVZBL (R2)+,R1 :GET LENGTH OF IF STATE
52 6241 9E 06D2 1029 MOVAB (R2)[R1],R2 :GET ADDRESS OF VALUE LENGTH
51 82 3C 06D6 1030 MOVZWL (R2)+,R1 :GET LENGTH OF VALUE
54 OB A3 9A 06D9 1031 MOVZBL SYM_B_FLAGS(R3),R4 :GET KEYPAD FLAGS
06DD 1032
05 06DD 1033 10$: RSB ;

```

```

06DE 1035 .SBTTL SEARCH KEYPAD SYMBOL TABLE FOR ENTRY
06DE 1036 :+
06DE 1037 : DCL$FIND_KEYPAD - SEARCH KEYPAD SYMBOL TABLE FOR ENTRY
06DE 1038 :
06DE 1039 : THIS ROUTINE IS CALLED TO SEARCH THE KEYPAD SYMBOL TABLE FOR AN ENTRY.
06DE 1040 : ONLY DEFINITIONS FOR THE PRC_L_CURRKEY STATE ARE CHECKED.
06DE 1041 :
06DE 1042 : INPUTS:
06DE 1043 :
06DE 1044 : R1 = LENGTH OF SYMBOL NAME.
06DE 1045 : R2 = ADDRESS OF SYMBOL NAME.
06DE 1046 : R11 = ADDRESS OF PRC DATA STRUCTURE
06DE 1047 : PRC_L_CURRKEY = CURRENT KEY STATE
06DE 1048 :
06DE 1049 : OUTPUTS:
06DE 1050 :
06DE 1051 : R0 LOW BIT CLEAR INDICATES SEARCH FAILURE.
06DE 1052 :
06DE 1053 : R1 = LENGTH OF SYMBOL NAME.
06DE 1054 : R2 = ADDRESS OF SYMBOL NAME.
06DE 1055 : R3 = ADDRESS OF NEXT GREATEST SYMBOL ENTRY.
06DE 1056 : R4 ARE DESTROYED.
06DE 1057 :
06DE 1058 : R0 LOW BIT SET INDICATES SYMBOL FOUND WITH:
06DE 1059 :
06DE 1060 : R1 = LENGTH OF SYMBOL NAME.
06DE 1061 : R2 = ADDRESS OF SYMBOL NAME.
06DE 1062 : R3 = ADDRESS OF SYMBOL ENTRY.
06DE 1063 : R4 IS DESTROYED
06DE 1064 :-
06DE 1065 :
06DE 1066 DCL$FIND_KEYPAD:: ;SEARCH KEYPAD SYMBOL TABLE FOR ENTRY
06DE 1067 :
06DE 1068 :
06DE 1069 : SET ADDRESS OF SYMBOL TABLE.
06DE 1070 :
53 40 AB 9E 06DE 1071 MOVAB PRC_Q_KEYPAD(R11),R3 ;SET ADDRESS OF KEYPAD SYMBOL TABLE LISTHEAD
50 53 D0 06E2 1072 MOVL R3,R0 ;COPY ADDRESS OF SYMBOL TABLE LISTHEAD
06E5 1073 :
06E5 1074 : SEARCH FOR THE SPECIFIED SYMBOL.
06E5 1075 :
53 63 D0 06E5 1077 10$: MOVL SYM_L_FL(R3),R3 ;GET ADDRESS OF NEXT ENTRY
53 50 D1 06E8 1078 CMPL R0,R3 ;END OF TABLE?
38 13 06EB 1079 BEQL 90$ ;IF EQL YES
06ED 1080 :
06ED 1081 :
06ED 1082 : CHECK THAT THE SYMBOL STATE MATCHES.
06ED 1083 :
51 OF BB 06ED 1084 PUSHR #*M<R0,R1,R2,R3> ;SAVE SEARCH PARAMETERS
54 0C A3 9A 06EF 1085 MOVZBL SYM_T_SYMBOL(R3),R1 ;GET LENGTH OF SYMBOL
50 84 9A 06F3 1086 MOVAB SYM_T_SYMBOL+3(R3)[R1],R4 ;GET ADDRESS OF IF_STATE LENGTH
52 48 AB D0 06F8 1087 MOVZBL (R4)+,R0 ;GET IF STATE LENGTH
51 82 9A 06FB 1088 MOVL PRC_L_CURRKEY(R11),R2 ;GET CURRENT STATE LENGTH/ADDRESS
64 50 00 62 51 9A 06FF 1089 MOVZBL (R2)+,R1 ;
2D 0702 1090 CMPC5 R1,(R2),#0,R0,(R4) ;STATES MATCH?
OF BA 0708 1091 20$: POPR #*M<R0,R1,R2,R3> ;RESTORE SEARCH PARAMETERS

```

			D9	14	070A	1092		BGTR	10\$:IF NEQ NO
			17	19	070C	1093		BLSS	90\$:
					070E	1094					:
					070E	1095					:
					070E	1096					:
					070E	1097					:
					070E	1098					:
					0712	1099					:
					0714	1100					:
					0717	1101					:
					071D	1102					:
					071F	1103					:
					0721	1104					:
					0723	1105					:
					0723	1106					:
					0725	1107	90\$:				:
					0726	1108					:

64	50	00	50	62	54	0C	A3	9E	070E	1098		MOVAB	SYM T SYMBOL(R3),R4		:GET ADDRESS OF SYMBOL NAME
							0F	BB	0712	1099		PUSHR	#M<R0,R1,R2,R3>		:SAVE SEARCH PARAMETERS
							84	9A	0714	1100		MOVZBL	(R4)+,R0		:GET LENGTH OF SYMBOL NAME
							51	2D	0717	1101		CMPC5	R1,(R2),#0,R0,(R4)		:SYMBOLS MATCH?
							0F	BA	071D	1102		POPR	#M<R0,R1,R2,R3>		:RESTORE SEARCH PARAMETERS
							C4	14	071F	1103		BGTR	10\$:IF NEQ NO
							02	19	0721	1104		BLSS	90\$:
									0723	1105					:
							50	D6	0723	1106		INCL	R0		:SET SUCCESS INDICATOR
								05	0725	1107		RSB			:

```

0726 1110 .SBTTL SET KEYPAD STATE
0726 1111 :+
0726 1112 : DCL$SETKEY - SET KEYPAD STATE
0726 1113 :
0726 1114 : THIS ROUTINE IS CALLED AS AN INTERNAL COMMAND TO EXECUTE THE SET KEYPAD
0726 1115 : COMMAND.
0726 1116 :
0726 1117 : INPUTS:
0726 1118 :
0726 1119 : R8 = ADDRESS OF SCRATCH BUFFER DESCRIPTOR.
0726 1120 : R9 = ADDRESS OF SCRATCH STACK.
0726 1121 : R10 = BASE ADDRESS OF COMMAND WORK AREA.
0726 1122 : R11 = BASE ADDRESS OF PROCESS WORK AREA.
0726 1123 :
0726 1124 : OUTPUTS:
0726 1125 :
0726 1126 : THE SPECIFIED KEYPAD STATE BECOMES THE LOCKED CURRENT STATE.
0726 1127 :-
0726 1128 :
0726 1129 DCL$SETKEY:: :SET KEYPAD SYMBOL TABLE STATE
58 01 D0 0726 1130 MOVL #1,R8 :ASSUME /LOG
56 56 7C 0729 1131 CLRQ R6 :INIT STATE NAME DESCRIPTOR
072B 1132 :
072B 1133 :
072B 1134 : PROCESS THE TOKENS ON THE COMMAND LINE.
072B 1135 :
55 F8D2' 30 072B 1136 10$: BSBW DCL$GETDVAL :GET NEXT DESCRIPTOR VALUE
55 04 91 072E 1137 CMPB #PTR_K_ENDLINE,R5 :END OF LINE?
55 30 13 0731 1138 BEQL 50$ :BRANCH IF SO
55 03 91 0733 1139 CMPB #PTR_K_PARAMETR,R5 :PARAMETER?
F3 13 0736 1140 BEQL 10$ :IGNORE IF SO
00'8F F8C5' 30 0738 1141 BSBW DCL$GETNVAL :GET QUALIFIER NUMBER
51 91 073B 1142 CMPB R1,#CLISK_STKY_STAT :/STATE?
00'8F 08 13 073F 1143 BEQL 20$ :YES, PROCESS IT
51 91 0741 1144 CMPB R1,#CLISK_STKY_LOG :/LOG?
10 13 0745 1145 BEQL 30$ :YES, PROCESS IT
E2 11 0747 1146 BRB 10$ :NO, GET NEXT TOKEN
0749 1147 :
DC 53 56 7C 0749 1148 20$: CLRQ R6 :INIT STATE NAME DESCRIPTOR
00 E0 074B 1149 BBS #PTR_V_NEGATE-PTR_V_FLAGS,R3,10$ :IGNORE IF NOT /STATE
56 F8AE' 30 074F 1150 BSBW DCL$GETDVAL :GET NEXT DESCRIPTOR VALUE
51 7D 0752 1151 MOVQ R1,R6 :SAVE IT AWAY
D4 11 0755 1152 BRB 10$ :GET NEXT
0757 1153 :
CD 58 01 C8 0757 1154 30$: BISL #1,R8 :ASSUME /LOG
53 00 E1 075A 1155 BBC #PTR_V_NEGATE-PTR_V_FLAGS,R3,10$ :IGNORE IF NOT /NOLOG
58 01 CA 075E 1156 BICL #1,R8 :CLEAR FLAG
C8 11 0761 1157 BRB 10$ :GET NEXT
0763 1158 :
0763 1159 :
0763 1160 : SET THE SPECIFIED STATE.
0763 1161 :
51 56 7D 0763 1162 50$: MOVQ R6,R1 :GET STATE DESCRIPTOR
24 13 0766 1163 BEQL 90$ :EXIT IF NONE SPECIFIED
2A 10 0768 1164 BSBB DCL$ALLOC_STATE :SET NEW STATE
1F 50 E9 076A 1165 BLBC R0,90$ :EXIT IF ERROR
50 4C AB D0 076D 1166 MOVL PRG_L_LASTKEY(R11),R0 :CLEAR LAST STATE

```

	0056	30	0771	1167	BSBW	DCL\$DEALLOC STATE	:
	48 AB	DO	0774	1168	MOVL	PRC_L_CURRKEY(R11),-	: COPY KEY DEFINITION
	4C AB		0777	1169		PRC_L_LASTKEY(R11)	:
			0779	1170			:
			0779	1171			:
			0779	1172			: OUTPUT LOG MESSAGE IF REQUESTED.
			0779	1173			:
	10 58	E9	0779	1174	BLBC	R8,90\$: SKIP IF /NOLOG SPECIFIED
	48 AB	DD	077C	1175	PUSHL	PRC_L_CURRKEY(R11)	: SET ADDRESS OF ASCII STATE NAME
	51 01	DO	077F	1176	MOVL	#1,R1-	: SET ARGUMENT COUNT
50	0003DDD3 8F	DO	0782	1177	MOVL	#CLIS SETKEY,RO	: SET STATUS
	F874	30	0789	1178	BSBW	DCL\$FORMMSG	: OUTPUT THE LOG MESSAGE
			078C	1179			:
		05	078C	1180	90\$: STATUS	NORMAL	: SET NORMAL SUCCESS STATUS
			0793	1181	RSB		: RETURN
			0794	1182			:

```

0794 1184 .SBTTL ALLOCATE AND INIT A KEYPAD STATE SYMBOL
0794 1185 :+
0794 1186 : DCL$ALLOC_STATE - ALLOCATE AND INIT A KEYPAD STATE SYMBOL
0794 1187 :
0794 1188 : THIS ROUTINE IS CALLED TO ALLOCATE AND INIT A KEYPAD STATE SYMBOL.
0794 1189 :
0794 1190 : INPUTS:
0794 1191 :
0794 1192 : R1/R2 = DESCRIPTOR OF NEW KEYPAD STATE
0794 1193 : R11 = ADDRESS OF PROCESS WORK AREA
0794 1194 :
0794 1195 : OUTPUTS:
0794 1196 :
0794 1197 : PRC_L_CURRKEY = SET TO THE NEWLY ALLOCATED STATE SYMBOL
0794 1198 :
0794 1199 : RO LBC INDICATES SYMBOL TABLE OVERFLOW
0794 1200 :-
0794 1201
0794 1202 DCL$ALLOC STATE::
0794 1203 POSHR #^M<R1,R2,R3,R4,R5> ;ALLOCATE STATE SYMBOL
0796 1204 DISABLE ;SAVE R1-R5
079C 1205 MOVQ R1,R4 ;DISABLE CTRL/Y'S
079F 1206 INCL R1 ;SAVE STATE DESCRIPTOR
07A1 1207 BSBW DCL$ALLDYNMEM ;ADD ROOM FOR BYTE COUNT
07A4 1208 BLBC R0,90$ ;GET MEMORY TO SAVE STATE IN
07A7 1209 MOVL R2,PRC_L_CURRKEY(R11) ;BRANCH IF NO ROOM FOR SYMBOL
07AB 1210 MOVB R4,(R2)+ ;SET CURRENT KEY STATE
07AE 1211 MOVC3 R4,(R5),(R2) ;MOVE THE STRING LENGTH
07B2 1212 STATUS NORMAL ;MOVE THE STRING
07B9 1213 ENABLE ;SET NORMAL STATUS
07BB 1214 POPR #^M<R1,R2,R3,R4,R5> ;ENABLE CTRL/Y'S
07BD 1215 RSB ;RESTORE R1-R5
07BE 1216
07BE 1217 90$: ENABLE ;ENABLE CTRL/Y'S
07C0 1218 POPR #^M<R1,R2,R3,R4,R5> ;RESTORE R1-R5
07C2 1219 STATUS SYMOVF
07C9 1220 RSB
07CA 1221

```

```

3E BB
54 51 7D
51 D6
FB5C' 30
17 50 E9
48 AB 52 D0
82 54 90
62 65 54 28
3E BA
05 07BD 1215
07BE 1216
3E BA
05

```



```

07CA 1223      .SBTTL  DEALLOCATE A KEYPAD STATE SYMBOL
07CA 1224      :+
07CA 1225      : DCL$DEALLOC_STATE - DEALLOCATE A KEYPAD STATE SYMBOL
07CA 1226      :
07CA 1227      : THIS ROUTINE IS CALLED TO DEALLOCATE A KEYPAD STATE SYMBOL.
07CA 1228      :
07CA 1229      : INPUTS:
07CA 1230      :
07CA 1231      :         R0 = ADDRESS OF ASCII KEYPAD STATE
07CA 1232      :         R11 = ADDRESS OF PROCESS WORK AREA
07CA 1233      :
07CA 1234      : OUTPUTS:
07CA 1235      :
07CA 1236      :         NONE
07CA 1237      : -
07CA 1238      :
07CA 1239      : DCL$DEALLOC_STATE::
07CA 1240      :     DISABLE
07E  50  7D  07D0 1241      :     MOVQ   R0,-(SP)
07E  52  7D  07D3 1242      :     MOVQ   R2,-(SP)
51  60  9A  07D6 1243      :     MOVZBL (R0),R1
      51  D6  07D9 1244      :     INCL   R1
      F822' 30  07DB 1245      :     BSBW   DCL$DEADYNMEM
52  8E  7D  07DE 1246      :     MOVQ   (SP)+,R2
50  8E  7D  07E1 1247      :     MOVQ   (SP)+,R0
      07E4 1248      :     ENABLE
      05  07E6 1249      :     RSB
      07E7 1250      :
      07E7 1251      :     .END
                                :DEALLOCATE STATE SYMBOL
                                :DISABLE CTRL/Y'S
                                :SAVE R0-R3
                                :
                                :GET LENGTH OF TEMPORARY STATE
                                :INCR TO INCLUDE BYTE COUNT
                                :DEALLOCATE THE BLOCK
                                :RESTORE R0-R3
                                :
                                :ENABLE CTRL/Y'S
                                :

```

KEYPAD
Symbol table

\$ST2	= 00000004			NULL	00000070 R	02
BRIEFAO	00000018	R	02	PRC-B_CONTINUE	000000F3	
CLISK_DEFK_ECHO	*****	X	02	PRC-B_DEFRADIX	000000AE	
CLISK_DEFK_ERAS	*****	X	02	PRC-B_EXMDEPMOD	000000AD	
CLISK_DEFK_IF_S	*****	X	02	PRC-B_EXMDEPWID	000000AC	
CLISK_DEFK_LOCK	*****	X	02	PRC-B_EXONLYL	0000012D	
CLISK_DEFK_LOG	*****	X	02	PRC-B_FLAGS2	000000AF	
CLISK_DEFK_SET	*****	X	02	PRC-B_IMGFLAG	00000078	
CLISK_DEFK_TERM	*****	X	02	PRC-B_OUTFLAGS	0000012C	
CLISK_DELK_LOG	*****	X	02	PRC-B_PROMPTLEN	000000F0	
CLISK_DELK_STAT	*****	X	02	PRC-C_LENGTH	00000534	
CLISK_SHKY_BRIE	*****	X	02	PRC-G_COMMANDS	00000133	
CLISK_SHKY_DIRE	*****	X	02	PRC-G_PROMPT	000000F4	
CLISK_SHKY_FULL	*****	X	02	PRC-K_LENGTH	00000534	
CLISK_SHKY_LOG	*****	X	02	PRC-L_CURRKEY	00000048	
CLISK_SHKY_STAT	*****	X	02	PRC-L_EXMDEPADR	000000A8	
CLISK_STKY_LOG	*****	X	02	PRC-L_EXTARG	00000094	
CLISK_STKY_STAT	*****	X	02	PRC-L_EXTBLK	0000008C	
CLIS_DEFKY	= 0003DDC3			PRC-L_EXTCOD	0000009C	
CLIS_DELKEY	= 0003DDCB			PRC-L_EXTHND	00000090	
CLIS_IVKEYNAM	= 00038280			PRC-L_EXTPRM	00000098	
CLIS_KEYCNV	= 0003DE33			PRC-L_IDFLNK	000000BC	
CLIS_NORMAL	= 00030001			PRC-L_IMGACTSTS	00000080	
CLIS_SETKEY	= 0003DDD3			PRC-L_INDCLOCK	0000007C	
CLIS_SYMOVF	= 00038138			PRC-L_INDEPTH	0000005C	
CLIS_UNDKY	= 00038260			PRC-L_INDFAB	0000001C	
COMMA	00000071	R	02	PRC-L_INDINPRAB	00000014	
DCL\$ALLDYMEM	*****	X	02	PRC-L_INDOUSTRAB	00000018	
DCL\$ALLOCKEY	000005BD	RG	02	PRC-L_INPRAB	00000008	
DCL\$ALLOC_STATE	00000794	RG	02	PRC-L_LASTKEY	0000004C	
DCL\$DEADYMEM	*****	X	02	PRC-L_LSTSTATUS	000000B0	
DCL\$DEALLOCSYM	*****	X	02	PRC-L_ONCTLY	000000B8	
DCL\$DEALLOC_STATE	000007CA	RG	02	PRC-L_ONERROR	0000006C	
DCL\$DEFKEY	000000C9	RG	02	PRC-L_OUTOFBAND	000000B4	
DCL\$DELKEY	00000205	RG	02	PRC-L_OUTRAB	0000000C	
DCL\$DISABLE	*****	X	02	PRC-L_OUTRABCTX	00000118	
DCL\$FIND_KEYPAD	000006DE	RG	02	PRC-L_PPFLIST	00000070	
DCL\$FORMMSG	*****	X	02	PRC-L_RECALLPTR	0000012F	
DCL\$GETDVAL	*****	X	02	PRC-L_RESTART	00000058	
DCL\$GETNVAL	*****	X	02	PRC-L_SAVAP	00000000	
DCL\$LOCKED_STATE	*****	X	02	PRC-L_SAVFP	00000004	
DCL\$MSGOUT	*****	X	02	PRC-L_SEVERITY	00000050	
DCL\$SEARCH_KEYPAD	000006C1	RG	02	PRC-L_SPWN	000000C0	
DCL\$SETKEY	00000726	RG	02	PRC-L_STACKLM	000000A4	
DCL\$SHOWKEY	00000317	RG	02	PRC-L_STACKPT	000000A0	
DCL\$SYNONYM	00000651	RG	02	PRC-L_STATUS	00000054	
DELKEY	000002E2	R	02	PRC-L_STS	00000084	
DISPHDR	00000583	R	02	PRC-L_STV	00000088	
DISPSYMB	00000496	R	02	PRC-L_SYMBOL	00000060	
E1_ADR	000000B7	R	02	PRC-L_TMBX	00000074	
E2_ADR	000000BA	R	02	PRC-L_TRMLIST	00000010	
E3_ADR	000000BD	R	02	PRC-Q_ALLOCREG	00000020	
E4_ADR	000000C0	R	02	PRC-Q_COMMAND	000000E0	
E5_ADR	000000C3	R	02	PRC-Q_FLUSHTIME	000000D0	
E6_ADR	000000C6	R	02	PRC-Q_GLOBAL	00000028	
FULLFAO	00000026	R	02	PRC-Q_IMAGENAME	000000D8	
NO	00000066	R	02	PRC-Q_KEYPAD	00000040	

KEYPAD
Symbol table

PRC_Q_LABEL	00000030		WRK_B_MINPARM	FFFFFFFFD1
PRC_Q_LOCAL	00000038		WRK_B_PARMCNT	FFFFFFFFCE
PRC_Q_SAVEPRIV	000000E8		WRK_B_PARMSUM	FFFFFFFFCF
PRC_T_OUTDVI	0000011C		WRK_B_RECALLCNT	FFFFFFFFC5
PRC_W_ASTIOSB	000000C6		WRK_B_VALLEV	FFFFFFFFC4
PRC_W_ASTRETN	000000C8		WRK_B_VERBTYP	FFFFFFFFC2
PRC_W_ASTSTATUS	000000C4		WRK_C_INPBUSIZ	= 00000100
PRC_W_ATTMBX	0000007A		WRK_C_LENGTH	FFFFFF486
PRC_W_FLAGS	00000068		WRK_G_BUFFER	FFFFFF492
PRC_W_INPCHAN	00000064		WRK_G_INPBUF	FFFFFF896
PRC_W_ONLEVEL	0000006A		WRK_G_RESULT	FFFFFF986
PRC_W_OUTIFI	00000114		WRK_K_LENGTH	FFFFFF486
PRC_W_OUTISI	00000116		WRK_L_CHARPTR	FFFFFF48E
PRC_W_OUTMBXCHN	000000CA		WRK_L_DISALLOW	FFFFFFE6
PRC_W_OUTMBXREF	000000CE		WRK_L_ERRORRTN	FFFFFF9AE
PRC_W_OUTMBXSIZ	000000CC		WRK_L_EXPANDPTR	FFFFFF486
PRC_W_PMPTCTRL	000000F1		WRK_L_IMAGE	FFFFFFE2
PRC_W_WAITIOSB	00000066		WRK_L_MARKPTR	FFFFFF48A
PTR_B_LEVEL	00000004		WRK_L_PAROUT	FFFFFFD2
PTR_B_NUMBER	00000005		WRK_L_PMPTADDR	FFFFFF9A2
PTR_B_PARMCNT	00000006		WRK_L_PROMPTRTN	FFFFFF9A6
PTR_B_VALUE	00000000		WRK_L_PROPTR	FFFFFFC6
PTR_C_LENGTH	0000000C		WRK_L_QUABLK	FFFFFFCA
PTR_K_COMMA	= 00000005		WRK_L_READRTN	FFFFFF9AA
PTR_K_ENDLINE	= 00000004		WRK_L_RECALLPTR	FFFFFFEA
PTR_K_LENGTH	0000000C		WRK_L_RSLEND	FFFFFFB6
PTR_K_PARAMETR	= 00000003		WRK_L_RSLNXT	FFFFFFBA
PTR_L_DESCR	00000000		WRK_L_SAVAP	FFFFFFF8
PTR_L_ENTITY	00000008		WRK_L_SAVFP	FFFFFFFC
PTR_V_FLAGS	= 00000014		WRK_L_SAVSP	FFFFFFF4
PTR_V_KEYWORD	= 00000015		WRK_L_SIGNALRTN	FFFFFFD6
PTR_V_NEGATE	= 00000014		WRK_L_SPECTRN	FFFFFF9B2
SHOWHDR	00000000	R	WRK_L_TAB_VEC	FFFFFFDE
STATE	00000069	R	WRK_L_VERB	FFFFFFBE
STSSM_INHIB_MSG	= 10000000		WRK_W_FLAGS	FFFFFFF0
SYM_B_FLAGS	0000000B		WRK_W_FLAGS2	FFFFFFF2
SYM_B_NONUNIQUE	0000000B		WRK_W_IMGCHAN	FFFFFFFE
SYM_B_TYPE	0000000A		WRK_W_PMPTLEN	FFFFFF99E
SYM_K_KEYPAD	= 00000004		_SS_	= 000000EF
SYM_L_BL	00000004			
SYM_L_FL	00000000			
SYM_M_ECHO	= 00000001			
SYM_T_SYMBOL	0000000C			
SYM_V_ECHO	= 00000000			
SYM_V_ERASE	= 00000004			
SYM_V_LOCK	= 00000003			
SYM_V_STATE	= 00000002			
SYM_V_TERMINATE	= 00000001			
SYM_W_SIZE	00000008			
SYNDEF_TAB	000000B7	R		
SYNNAME_TAB	00000073	R		
SYSSFAO	*****	X		
SYSSFAOL	*****	GX		
UNDKEY	000002FE	R		
VALIDATE_KEY_NAME	*****	X		
WRK_B_CMDOPT	FFFFFFFFC3			
WRK_B_MAXPARM	FFFFFFD0			

+-----+
! Psect synopsis !
+-----+

PSECT name	Allocation	PSECT No.	Attributes
. ABS .	00000000 (0.)	00 (0.)	NOPIC USR CON ABS LCL NOSHR NOEXE NORD NOWRT NOVEC BYTE
\$ABSS	FFFFFFFFC (0.)	01 (1.)	NOPIC USR CON ABS LCL NOSHR EXE RD WRT NOVEC BYTE
DCL\$ZCODE	000007E7 (2023.)	02 (2.)	NOPIC USR CON REL LCL NOSHR EXE RD NOWRT NOVEC BYTE

+-----+
! Performance indicators !
+-----+

Phase	Page faults	CPU Time	Elapsed Time
Initialization	10	00:00:00.07	00:00:00.47
Command processing	87	00:00:00.72	00:00:03.56
Pass 1	257	00:00:09.83	00:00:28.30
Symbol table sort	0	00:00:00.87	00:00:02.66
Pass 2	216	00:00:03.21	00:00:11.48
Symbol table output	24	00:00:00.17	00:00:00.66
Psect synopsis output	2	00:00:00.02	00:00:00.02
Cross-reference output	0	00:00:00.00	00:00:00.00
Assembler run totals	596	00:00:14.91	00:00:47.17

The working set limit was 1350 pages.
52334 bytes (103 pages) of virtual memory were used to buffer the intermediate code.
There were 40 pages of symbol table space allocated to hold 538 non-local and 89 local symbols.
1251 source lines were read in Pass 1, producing 20 object records in Pass 2.
44 pages of virtual memory were used to define 28 macros.

+-----+
! Macro library statistics !
+-----+

Macro library name	Macros defined
_\$255\$DUA28:[SYSLIB]SYSBLDMLB.MLB;1	0
-\$255\$DUA28:[DCL.OBJ]DCL.MLB;1	11
-\$255\$DUA28:[SYS.OBJ]LIB.MLB;1	0
-\$255\$DUA28:[SYSLIB]STARLET.MLB;2	8
TOTALS (all libraries)	19

686 GETS were required to define 19 macros.

There were no errors, warnings or information messages.

MACRO/LIS=LIS\$:KEYPAD/OBJ=OBJ\$:KEYPAD MSRCS\$:KEYPAD/UPDATE=(ENHS\$:KEYPAD)+EXECMLS\$/LIB+LIBS\$:DCL/LIB+SYSS\$LIBRARY:SYSBLDMLB/LIB

INQUIRE
LIS

LEXICON
LIS

KEYPAD
LIS

LOGICAL
LIS