





```

1 0001 0 MODULE ACLSUBR (
2 0002 0     LANGUAGE (BLISS32),
3 0003 0     IDENT = 'V04-000',
4 0004 0     ADDRESSING_MODE (EXTERNAL = GENERAL)
5 0005 0 ) =
6 0006 1 BEGIN
7 0007 1
8 0008 1 *****
9 0009 1 *
10 0010 1 *  COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
11 0011 1 *  DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
12 0012 1 *  ALL RIGHTS RESERVED.
13 0013 1 *
14 0014 1 *  THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
15 0015 1 *  ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
16 0016 1 *  INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
17 0017 1 *  COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
18 0018 1 *  OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
19 0019 1 *  TRANSFERRED.
20 0020 1 *
21 0021 1 *  THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
22 0022 1 *  AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
23 0023 1 *  CORPORATION.
24 0024 1 *
25 0025 1 *  DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
26 0026 1 *  SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
27 0027 1 *
28 0028 1 *
29 0029 1 *****
30 0030 1
31 0031 1 ++
32 0032 1
33 0033 1 FACILITY:      File system subroutines
34 0034 1
35 0035 1 ABSTRACT:
36 0036 1
37 0037 1     This module contains the subroutines that manage in memory
38 0038 1     access control lists.
39 0039 1
40 0040 1 ENVIRONMENT:
41 0041 1
42 0042 1     Modular procedure. No own storage used.
43 0043 1
44 0044 1 --
45 0045 1
46 0046 1
47 0047 1 AUTHOR:      L. Mark Pilant      CREATION DATE: 30-Sep-1982 11:00
48 0048 1
49 0049 1 MODIFIED BY:
50 0050 1
51 0051 1     V03-006 LMP0290      L. Mark Pilant,      31-Jul-1984 10:40
52 0052 1     Make sure ACL_MODENTRY tracks the ACL_LOCATEACE interface
53 0053 1     change.
54 0054 1
55 0055 1     V03-005 LMP0284      L. Mark Pilant,      25-Jul-1984 15:06
56 0056 1     Add an ACL initialization routine, ACL_INIT_QUEUE.
57 0057 1

```

```

58 0058 1 : V03-004 LMP0273 L. Mark Pilant, 6-Jul-1984 13:56
59 0059 1 : Fix a bug that caused an ACE to be dropped when the user's
60 0060 1 : buffer filled up during an ACL read.
61 0061 1 :
62 0062 1 : V03-003 ACG0426 Andrew C. Goldstein, 4-May-1984 15:14
63 0063 1 : Fix clearing of input buffer in ACL_ERROR call in ACL_ADDENTRY
64 0064 1 :
65 0065 1 : V03-002 ACG0418 Andrew C. Goldstein, 19-Apr-1984 13:15
66 0066 1 : Fix returning of NOMOREACE in reading ACL's
67 0067 1 :
68 0068 1 : V03-001 ACG0415 Andrew C. Goldstein, 3-Apr-1984 14:33
69 0069 1 : Break out from SYSACLSRV.B32 to make common routines;
70 0070 1 : rework add algorithm to: support multiple ACEs in one
71 0071 1 : add, correctly protect positioning of alarm and audit
72 0072 1 : ACEs at the front of the ACL, fix the block split of
73 0073 1 : large ACLs; general code cleanup and minor bug fixes.
74 0074 1 :
75 0075 1 : **
76 0076 1 :
77 0077 1 LIBRARY 'SYSS$LIBRARY:LIB.L32';
78 0078 1 REQUIRE 'SRC$:FCPDEF';
79 1069 1 :
80 1070 1 :
81 1071 1 FORWARD ROUTINE
82 1072 1 ACL_INIT_QUEUE, : Initialize ACL queue
83 1073 1 ACL_ADDENTRY, : add an ACE to an ACL
84 1074 1 ACL_DELENTY, : remove an ACE from an ACL
85 1075 1 ACL_MODENTRY, : modify an existing ACE
86 1076 1 ACL_FINDENTRY, : locate a specific ACE
87 1077 1 ACL_FINDTYPE, : locate a specific type of ACE
88 1078 1 ACL_DELETEACL, : remove entire ACL from object
89 1079 1 ACL_READACL, : read one or more ACEs
90 1080 1 ACL_ACLLENGTH, : determine the size of the ACL
91 1081 1 ACL_READACE, : read a single ACE
92 1082 1 ACL_LOCATEACE, : locate ACE by context value
93 1083 1 :
94 1084 1 EXTERNAL ROUTINE
95 1085 1 ALLOC_PAGED, : Paged pool allocator
96 1086 1 DALLOC_PAGED, : Paged pool deallocator
97 1087 1 :
98 1088 1 MACRO
99 1089 1 ACL_ERROR (STATUS) =
100 1090 1 BEGIN
101 1091 1 CH$FILL (0, .COUNT, .ACE);
102 1092 1 ACE[ACES$W_FLAGS] = STATUS;
103 1093 1 RETURN STATUS;
104 1094 1 END
105 1095 1 %;
106 1096 1 :
107 1097 1 ! Fields used in the ACL context longword.
108 1098 1 :
109 1099 1 MACRO
110 1100 1 CONTEXT_INDEX = 0, 0, 24, 0 %; ! ACL entry index
111 1101 1 CONTEXT_TYPE = 0, 24, 8, 0 %; ! entry type in use

```

ACL\_INIT\_QUEUE - initialize ACL queue head

```

113 1102 1 %SBTTL 'ACL_INIT_QUEUE - initialize ACL queue head'
114 1103 1 GLOBAL ROUTINE ACC_INIT_QUEUE (ORB_ADDRESS) =
115 1104 1
116 1105 1  !++
117 1106 1
118 1107 1  FUNCTIONAL DESCRIPTION:
119 1108 1
120 1109 1      This routine is called to initialize an uninitialized ACL queue.
121 1110 1      If the queue has already been initialized, this routine is a no-op.
122 1111 1
123 1112 1  CALLING SEQUENCE:
124 1113 1      ACL_INIT_QUEUE (ARG1)
125 1114 1
126 1115 1  INPUT PARAMETERS:
127 1116 1      ARG1: address of the ORB
128 1117 1
129 1118 1  IMPLICIT INPUTS:
130 1119 1      none
131 1120 1
132 1121 1  OUTPUT PARAMETERS:
133 1122 1      none
134 1123 1
135 1124 1  IMPLICIT OUTPUTS:
136 1125 1      none
137 1126 1
138 1127 1  ROUTINE VALUE:
139 1128 1      1
140 1129 1
141 1130 1  SIDE EFFECTS:
142 1131 1      ACL queue head is initialized, and the ACL queue bit in the ORB
143 1132 1      is set.
144 1133 1
145 1134 1  --
146 1135 1
147 1136 2 BEGIN
148 1137 2
149 1138 2 MAP
150 1139 2     ORB_ADDRESS      : REF BBLOCK;           ! Address of the ORB
151 1140 2
152 1141 2 LOCAL
153 1142 2     ORB              : REF BBLOCK;           ! Address of the ORB for PRIMARY_FCB
154 1143 2
155 1144 2 EXTERNAL
156 1145 2     CTL$GL_PCB        : REF BBLOCK ADDRESSING_MODE (ABSOLUTE);
157 1146 2
158 1147 2 LINKAGE
159 1148 2     L_MUTEX           = JSB (REGISTER = 0, REGISTER = 4)
160 1149 2     : NOTUSED (5, 6, 7, 8, 9, 10, 11);
161 1150 2
162 1151 2 EXTERNAL ROUTINE
163 1152 2     SCH$LOCKW         : L_MUTEX ADDRESSING_MODE (ABSOLUTE),
164 1153 2     : Lock mutex for write
165 1154 2     SCH$UNLOCK        : L_MUTEX ADDRESSING_MODE (ABSOLUTE);
166 1155 2     : Unlock mutex
167 1156 2
168 1157 2 ! If the ACL queue head is uninitialized, do the initialization now.
169 1158 2

```



ACL\_ADDENTRY - add an ACE to an ACL

```

186 1174 1 %SBTTL 'ACL_ADDENTRY - add an ACE to an ACL'
187 1175 1 GLOBAL ROUTINE ACL_ADDENTRY (ACL_QUEUE_HEAD, ACL_CONTEXT, LENGTH, ACE_BUFFER) =
188 1176 1
189 1177 1 ++
190 1178 1
191 1179 1 FUNCTIONAL DESCRIPTION:
192 1180 1
193 1181 1 This routine is used to add an Access Control Entry to the file ACL.
194 1182 1 If the ACL context is zero, the ACE is added to the beginning of the
195 1183 1 ACL. Otherwise, it is inserted into the ACL at the selected place.
196 1184 1
197 1185 1 It should be noted that adding an ACE anywhere in the ACL other than
198 1186 1 the end could possibly result in corruption of the ACL if the system
199 1187 1 should crash while the new ACE is being inserted.
200 1188 1
201 1189 1 CALLING SEQUENCE:
202 1190 1 ACL_ADDENTRY (ACL_QUEUE_HEAD, ACL_CONTEXT, LENGTH, ACE_BUFFER)
203 1191 1
204 1192 1 INPUT PARAMETERS:
205 1193 1 ACL_QUEUE_HEAD: address of queue header for ACL
206 1194 1 ACL_CONTEXT: address of ACL context longword
207 1195 1 LENGTH: size of the user Access Control Entry
208 1196 1 ACE_BUFFER: address of the user Access Control Entry
209 1197 1
210 1198 1 IMPLICIT INPUTS:
211 1199 1 NONE
212 1200 1
213 1201 1 OUTPUT PARAMETERS:
214 1202 1 NONE
215 1203 1
216 1204 1 IMPLICIT OUTPUTS:
217 1205 1 NONE
218 1206 1
219 1207 1 ROUTINE VALUE:
220 1208 1 1
221 1209 1
222 1210 1 SIDE EFFECTS:
223 1211 1 Access Control Entry inserted in or appended to the file ACL. If
224 1212 1 it is an insertion, the ACL context is updated to point after the
225 1213 1 inserted ACE.
226 1214 1
227 1215 1 --
228 1216 1
229 1217 2 BEGIN
230 1218 2
231 1219 2 MAP
232 1220 2 ACL_QUEUE_HEAD : REF $BLOCK, ! Queue header for ACL
233 1221 2 ACL_CONTEXT : REF $BLOCK; ! Context longword
234 1222 2
235 1223 2 LABEL
236 1224 2 ADD_ENTRY; ! Add one ACE to the ACL
237 1225 2
238 1226 2 LOCAL
239 1227 2 COUNT, ! Length of remaining buffer
240 1228 2 ACE : REF $BLOCK, ! The address of the user ACE
241 1229 2 ACL_POINTER : REF $BLOCK, ! Pointer to current ACL segment
242 1230 2 ACL_SPLIT : REF $BLOCK, ! Offset to current ACE

```

: R

```

: 243 1231 2 ACE_POINTER : REF $BBLOCK, ! Pointer to current ACE
: 244 1232 2 ACE_NUMBER, ! Index of ACE in ACL
: 245 1233 2 ACL_LENGTH, ! Length of all ACE's in segment
: 246 1234 2 NEW_ACL : REF $BBLOCK, ! Address of the new ACL segment
: 247 1235 2 OLD_CONTEXT : $BBLOCK [4]; ! Index of existing ACL entry
: 248 1236 2
: 249 1237 2
: 250 1238 2 ! The ACE buffer may contain multiple ACEs. Loop over the ACEs in the buffer,
: 251 1239 2 ! adding them one at a time.
: 252 1240 2
: 253 1241 2 COUNT = .LENGTH;
: 254 1242 2 ACE = .ACE_BUFFER;
: 255 1243 2 UNTIL .COUNT LEQ 0
: 256 1244 2 DO
: 257 1245 3 BEGIN
: 258 1246 4 ADD_ENTRY: BEGIN
: 259 1247 4
: 260 1248 4 ! Sanity check the contents of the ACE - make sure the count field does
: 261 1249 4 ! not exceed the remaining buffer, and that the ACE is at least 4 bytes long.
: 262 1250 4
: 263 1251 4 IF .COUNT LSSU 4
: 264 1252 4 THEN RETURN SSS_BADPARAM;
: 265 1253 4
: 266 1254 4 IF .ACE[ACESB_SIZE] GTR .COUNT
: 267 1255 4 OR .ACE[ACESB_SIZE] EQL 0
: 268 1256 4 THEN ACL_ERROR (SSS_IVACL);
: 269 1257 4
: 270 1258 4 ! If the ACE being added is an AUDIT or ALARM ACE, force it to the beginning
: 271 1259 4 ! of the ACL.
: 272 1260 4
: 273 1261 4 ACE_NUMBER = .ACL_CONTEXT[CONTEXT_INDEX];
: 274 1262 4 IF .ACE[ACESB_TYPE] EQL ACESC_AUDIT
: 275 1263 4 OR .ACE[ACESB_TYPE] EQL ACESC_ALARM
: 276 1264 4 THEN ACE_NUMBER = 0;
: 277 1265 4
: 278 1266 4 ! Determine if the ACE exists already. If it does, the result depends on
: 279 1267 4 ! the relative position of the old and new ACEs. Effectively, we remove
: 280 1268 4 ! the one that is masked by the one preceding it in the ACL.
: 281 1269 4
: 282 1270 4 IF ACL_FINDENTRY (.ACL_QUEUE_HEAD, OLD_CONTEXT, .ACE[ACESB_SIZE], .ACE, 1)
: 283 1271 4 THEN
: 284 1272 5 BEGIN
: 285 1273 5 IF .OLD_CONTEXT[CONTEXT_INDEX] LSSU .ACE_NUMBER
: 286 1274 5 THEN LEAVE ADD_ENTRY;
: 287 1275 5 ACL_DELENTY (.ACL_QUEUE_HEAD, OLD_CONTEXT, 0, 0);
: 288 1276 4 END;
: 289 1277 4
: 290 1278 4 ! Now locate the appropriate ACL segment. If there is no ACL
: 291 1279 4 ! as yet, simply allocate a block of memory and build
: 292 1280 4 ! the new ACL.
: 293 1281 4
: 294 1282 4 IF .ACL_QUEUE_HEAD[ACL$SL_FLINK] EQLA ACL_QUEUE_HEAD[ACL$SL_FLINK]
: 295 1283 4 THEN
: 296 1284 5 BEGIN
: 297 1285 5 ACL_POINTER = ALLOC_PAGED (ACL$C_LENGTH + .ACE[ACESB_SIZE], ACL_TYPE);
: 298 1286 5 CHSMOVE (.ACE[ACESB_SIZE], .ACE, ACL_POINTER[ACL$SL_LIST]);
: 299 1287 5 ACL_POINTER[ACL$W_SIZE] = ACL$C_LENGTH + .ACE[ACESB_SIZE];

```



```

: 300 1288 5      INSQUE (.ACL_POINTER, .ACL_QUEUE_HEAD[ACL$FLINK]);
: 301 1289 5      ACE_NUMBER = 1;
: 302 1290 5      END
: 303 1291 5
: 304 1292 5 ! If there is an existing ACL, position to the location indicated by the
: 305 1293 5 ! context. Then advance over any existing audit or alarm ACEs to ensure
: 306 1294 5 ! that they stay at the front of the ACL. Finally, if we are positioned
: 307 1295 5 ! at the start of a segment, back up to the end of the previous. This prevents
: 308 1296 5 ! successive additions at the same point from fragmenting the ACL.
: 309 1297 5
: 310 1298 4      ELSE
: 311 1299 5      BEGIN
: 312 1300 5      ACE_NUMBER = ACL_LOCATEACE (.ACL_QUEUE_HEAD, .ACE_NUMBER, ACL_POINTER, ACL_SPLIT);
: 313 1301 5      ACE_POINTER = ACE_POINTER[ACL$LIST] + .ACL_SPLIT;
: 314 1302 5      UNTIL ACL_POINTER[ACL$FLINK] EQA ACL_QUEUE_HEAD[ACL$FLINK]
: 315 1303 6      OR (.ACE_POINTER[ACE$B_TYPE] NEQ ACE$C_AUDIT
: 316 1304 6      AND .ACE_POINTER[ACE$B_TYPE] NEQ ACE$C_ALARM)
: 317 1305 5      DO
: 318 1306 6      BEGIN
: 319 1307 6      ACE_POINTER = .ACE_POINTER + .ACE_POINTER[ACE$B_SIZE];
: 320 1308 6      ACE_NUMBER = .ACE_NUMBER + 1;
: 321 1309 6      IF .ACE_POINTER GEQA .ACL_POINTER + .ACL_POINTER[ACL$W_SIZE]
: 322 1310 6      THEN
: 323 1311 7      BEGIN
: 324 1312 7      ACE_POINTER = .ACL_POINTER[ACL$FLINK];
: 325 1313 7      ACE_POINTER = ACE_POINTER[ACL$LIST];
: 326 1314 6      END;
: 327 1315 5      END;
: 328 1316 5
: 329 1317 5      IF .ACE_POINTER EQA ACL_POINTER[ACL$LIST]
: 330 1318 5      AND .ACE_POINTER[ACL$BLINK] NEQA ACE_QUEUE_HEAD[ACL$FLINK]
: 331 1319 5      THEN
: 332 1320 6      BEGIN
: 333 1321 6      ACE_POINTER = .ACL_POINTER[ACL$BLINK];
: 334 1322 6      ACE_POINTER = .ACL_POINTER + .ACE_POINTER[ACL$W_SIZE];
: 335 1323 5      END;
: 336 1324 5
: 337 1325 5 ! Now check the size of the segment. If the new entry still fits within
: 338 1326 5 ! the maximum segment size, insert it by allocating a new segment and
: 339 1327 5 ! copying in the pieces.
: 340 1328 5
: 341 1329 5      ACE_SPLIT = .ACE_POINTER - ACE_POINTER[ACL$LIST];
: 342 1330 5      ACE_LENGTH = .ACE_POINTER[ACL$W_SIZE] - ACE_LENGTH;
: 343 1331 5      IF .ACE_LENGTH + .ACE[ACE$B_SIZE] LEQA MAX_ACE_SIZE
: 344 1332 5      THEN
: 345 1333 6      BEGIN
: 346 1334 6      NEW_ACL = ALLOC PAGED (ACE_LENGTH + .ACE_LENGTH + .ACE[ACE$B_SIZE], ACE_TYPE);
: 347 1335 6      NEW_ACL[ACL$W_SIZE] = ACE_LENGTH + .ACE_LENGTH + .ACE[ACE$B_SIZE];
: 348 1336 6      ACE_POINTER = CH$MOVE (.ACL_SPLIT, ACE_POINTER[ACL$LIST],
: 349 1337 6      NEW_ACL[ACL$LIST]);
: 350 1338 6      ACE_POINTER = CH$MOVE (.ACE[ACE$B_SIZE], .ACE, .ACE_POINTER);
: 351 1339 6      CH$MOVE (.ACE_LENGTH - .ACL_SPLIT,
: 352 1340 6      ACE_POINTER[ACL$LIST] + .ACL_SPLIT, .ACE_POINTER);
: 353 1341 6      INSQUE (.NEW_ACL, .ACL_POINTER[ACL$BLINK]);
: 354 1342 6      END
: 355 1343 6
: 356 1344 6 ! Otherwise we have to split the segment. We put the new ACE in whichever

```

ACL\_ADDENTRY - add an ACE to an ACL

```

357 1345 6 ! segment is smaller. Because the max size of an ACE is 256, and the
358 1346 6 ! max segment size is 512, we are guaranteed that the new ACE will fit
359 1347 6 ! in one or the other (i.e., a 3-way split is not necessary).
360 1348 6
361 1349 5     ELSE
362 1350 6     BEGIN
363 1351 6     IF .ACL_SPLIT LEQU .ACL_LENGTH - .ACL_SPLIT
364 1352 6     THEN
365 1353 7     BEGIN
366 1354 7     NEW_ACL = ALLOC PAGED (ACL$C_LENGTH + .ACL_LENGTH - .ACL_SPLIT, ACL_TYPE);
367 1355 7     NEW_ACL[ACL$W_SIZE] = ACL$C_LENGTH + .ACL_LENGTH - .ACL_SPLIT;
368 1356 7     CH$MOVE (.ACL_LENGTH - .ACL_SPLIT,
369 1357 7     ACL_POINTER[ACL$C_LIST] + .ACL_SPLIT, NEW_ACL[ACL$C_LIST]);
370 1358 7     INSQUE (.NEW_ACL, ACL_POINTER[ACL$C_FLINK]);
371 1359 7     NEW_ACL = ALLOC PAGED (ACL$C_LENGTH + .ACL_SPLIT + .ACE[ACESB_SIZE], ACL_TYPE);
372 1360 7     NEW_ACL[ACL$W_SIZE] = ACL$C_LENGTH + .ACL_SPLIT + .ACE[ACESB_SIZE];
373 1361 7     ACE_POINTER = CH$MOVE (.ACL_SPLIT, ACL_POINTER[ACL$C_LIST],
374 1362 7     NEW_ACL[ACL$C_LIST]);
375 1363 7     CH$MOVE (.ACE[ACESB_SIZE], .ACE, .ACE_POINTER);
376 1364 7     INSQUE (.NEW_ACL, ACL_POINTER[ACL$C_FLINK]);
377 1365 7     END
378 1366 6     ELSE
379 1367 7     BEGIN
380 1368 7     NEW_ACL = ALLOC PAGED (ACL$C_LENGTH + .ACL_LENGTH - .ACL_SPLIT + .ACE[ACESB_SIZE], ACL_TYPE);
381 1369 7     NEW_ACL[ACL$W_SIZE] = ACL$C_LENGTH + .ACL_LENGTH - .ACL_SPLIT + .ACE[ACESB_SIZE];
382 1370 7     ACE_POINTER = CH$MOVE (.ACE[ACESB_SIZE], .ACE, NEW_ACL[ACL$C_LIST]);
383 1371 7     CH$MOVE (.ACL_LENGTH - .ACL_SPLIT,
384 1372 7     ACL_POINTER[ACL$C_LIST] + .ACL_SPLIT, .ACE_POINTER);
385 1373 7     INSQUE (.NEW_ACL, ACL_POINTER[ACL$C_FLINK]);
386 1374 7     NEW_ACL = ALLOC PAGED (ACL$C_LENGTH + .ACL_SPLIT, ACL_TYPE);
387 1375 7     NEW_ACL[ACL$W_SIZE] = ACL$C_LENGTH + .ACL_SPLIT;
388 1376 7     CH$MOVE (.ACL_SPLIT, ACL_POINTER[ACL$C_LIST], NEW_ACL[ACL$C_LIST]);
389 1377 7     INSQUE (.NEW_ACL, ACL_POINTER[ACL$C_FLINK]);
390 1378 6     END;
391 1379 5     END;
392 1380 5     REMQUE (.ACL_POINTER, ACL_POINTER);
393 1381 5     DALLOC_PAGED (.ACL_POINTER, ACL_TYPE);
394 1382 4     END;
395 1383 4
396 1384 4 ! At this point the ACE has been added to the ACL. Finish up by setting the
397 1385 4 ! ACL context.
398 1386 4
399 1387 4     IF .ACE[ACESB_TYPE] EQL ACESC_AUDIT
400 1388 4     OR .ACE[ACESB_TYPE] EQL ACESC_ALARM
401 1389 4     THEN .ACL_CONTEXT = .ACL_CONTEXT + 1
402 1390 4     ELSE .ACL_CONTEXT = .ACE_NUMBER + 1;
403 1391 3     END;
404 1392 3     COUNT = .COUNT - .ACE[ACESB_SIZE];
405 1393 3     ACE = .ACE + .ACE[ACESB_SIZE];
406 1394 2     END;
407 1395 2
408 1396 2 RETURN 1;
409 1397 2
410 1398 1 END;

```

! end of block ADD\_ENTRY  
! end of ACE processing loop  
! End of routine ACL\_ADDENTRY

			OFFC	00000	.ENTRY	ACL_ADDENTRY, Save R2,R3,R4,R5,R6,R7,R8,R9,-;	
						R10,R11	1175
		5E	0C	C2 00002	SUBL2	#12, SP	
		5B	0C	AC D0 00005	MOVL	LENGTH, COUNT	1241
		5B	10	AC D0 00009	MOVL	ACE BUFFER, ACE	1242
				5B D5 0000D 1\$:	TSTL	COUNT	1243
				03 14 0000F	BGTR	2\$	
				02A2 31 00011	BRW	23\$	
		04		5B D1 00014 2\$:	CMPL	COUNT, #4	1251
				04 1E 00017	BGEQU	3\$	
		50		14 D0 00019	MOVL	#20, R0	1252
				04 0001C	RET		
5B	68	08		00 ED 0001D 3\$:	CMPZV	#0, #8, (ACE), COUNT	1254
				04 14 00022	BGTR	4\$	
				68 95 00024	TSTC	(ACE)	1255
				12 12 00026	Br.EQ	5\$	
5B	00	6E		00 2C 00028 4\$:	MOVC'	#0, (SP), #0, COUNT, (ACE)	1256
				68 0002D			
	02	A8	21E4	8F B0 0002E	MOVW	#8676, 2(ACE)	
		50	21E4	8F 3C 00034	MOVZWL	#8676, R0	
				04 00039	RET		
5A	08	BC		00 EF 0003A 5\$:	EXTZV	#0, #24, @ACL_CONTEXT, ACE_NUMBER	1261
		05	01	A8 91 00040	CMPB	1(ACE), #5	1262
				06 13 00044	BEQL	6\$	
		06	01	A8 91 00046	CMPB	1(ACE), #6	1263
				02 12 0004A	BNEQ	7\$	
				5A D4 0004C 6\$:	CLRL	ACE_NUMBER	1264
				01 DD 0004E 7\$:	PUSHL	#1	1270
				58 DD 00050	PUSHL	ACE	
		7E		68 9A 00052	MOVZBL	(ACE), -(SP)	
			0C	AE 9F 00055	PUSHAB	OLD_CONTEXT	
			04	AC DD 00058	PUSHL	ACL_QUEUE_HEAD	
		0000V		05 FB 0005B	CALLS	#5, -ACL_FINDENTRY	
		17		50 E9 00060	BLBC	R0, 9\$	
5A	6E	18		00 ED 00063	CMPZV	#0, #24, OLD_CONTEXT, ACE_NUMBER	1273
				03 1E 00068	BGEQU	8\$	
				023A 31 0006A	BRW	22\$	
				7E 7C 0006D 8\$:	CLRQ	-(SP)	1275
			08	AE 9F 0006F	PUSHAB	OLD_CONTEXT	
			04	AC DD 00072	PUSHL	ACL_QUEUE_HEAD	
		0000V		04 FB 00075	CALLS	#4, -ACL_DELENTY	
		04	04	BC D1 0007A 9\$:	CMPL	@ACL_QUEUE_HEAD, ACL_QUEUE_HEAD	1282
				3A 12 0007F	BNEQ	10\$	
				07 DD 00081	PUSHL	#7	1285
		7E		68 9A 00083	MOVZBL	(ACE), -(SP)	
		6E		0C C0 00086	ADDL2	#12, (SP)	
		00000000G		02 FB 00089	CALLS	#2, ALLOC PAGED	
		08		50 D0 00090	MOVL	R0, ACL_POINTER	
				68 9A 00094	MOVZBL	(ACE), R1	1286
		50	08	AE D0 00097	MOVL	ACL_POINTER, R0	
	0C	A0		51 28 0009B	MOVC3	R1, -(ACE), 12(R0)	
		50	08	AE D0 000A0	MOVL	ACL_POINTER, R0	1287
		08		68 9B 000A4	MOVZBW	(ACE), 8(R0)	
		08		0C A0 000A8	ADDW2	#12, 8(R0)	
		50	04	BC 9E 000AC	MOVAB	@ACL_QUEUE_HEAD, R0	1288

	00	B0	08	BE	0E	000B0	INSQUE	@ACL_POINTER, @0(R0)			
		5A		01	D0	000B5	MOVL	#1, ACE_NUMBER		1289	
				01D6	31	000B8	BRW	19\$		1282	
			04	AE	9F	000BB	10\$: PUSHAB	ACL_SPLIT		1300	
			0C	AE	9F	000BE	PUSHAB	ACL_POINTER			
				5A	DD	000C1	PUSHL	ACE_NUMBER			
			04	AC	DD	0C0C3	PUSHL	ACL_QUEUE_HEAD			
	0000V	CF		04	04	FB	000C6	CALLS	#4, ACL_LOCATEACE		
		5A			50	D0	000CB	MOVL	R0, ACE_NUMBER		
53		08	04	AE	C1	000CE	ADDL3	ACL_SPLIT, ACL_POINTER, R3		1301	
		59	0C	A3	9E	000D4	MOVAB	12(R3), ACE_POINTER			
		50	08	AE	D0	000D8	11\$: MOVL	ACL_POINTER, R0		1302	
		04		AC	50	D1	000DC	C MPL	R0, ACL_QUEUE_HEAD		
					2B	13	000E0	BEQL	13\$		
			05		01	A9	91	000E2	C MPB	1(ACE_POINTER), #5	1303
					06	13	000E6	BEQL	12\$		
			06		01	A9	91	000E8	C MPB	1(ACE_POINTER), #6	1304
					1F	12	000EC	BNEQ	13\$		
				51	69	9A	000EE	12\$: MOVZBL	(ACE_POINTER), R1	1307	
				59	51	C0	000F1	ADDL2	R1, ACE_POINTER		
					5A	D6	000F4	INCL	ACE_NUMBER	1308	
				51	08	A0	3C	000F6	MOVZWL	8(R0), R1	1309
				51	50	C0	000FA	ADDL2	R0, R1		
				51	59	D1	000FD	C MPL	ACE_POINTER, R1		
					D6	1F	00100	BLSSU	11\$		
		08		AE	60	D0	00102	MOVL	(R0), ACL_POINTER	1312	
59		08		AE	0C	C1	00106	ADDL3	#12, ACL_POINTER, ACE_POINTER	1313	
					CB	11	0010B	BRB	11\$	1302	
				50	08	AE	D0	0010D	13\$: MOVL	ACL_POINTER, R0	1317
				51	0C	A0	9E	00111	MOVAB	12(R0), R1	
				51	59	D1	00115	C MPL	ACE_POINTER, R1		
					17	12	00118	BNEQ	14\$		
		04		AC	04	A0	D1	0011A	C MPL	4(R0), ACL_QUEUE_HEAD	1318
					10	13	0011F	BEQL	14\$		
		08		AE	04	A0	D0	00121	MOVL	4(R0), ACL_POINTER	1321
		50	08	AE	D0	D0	00126	MOVL	ACL_POINTER, R0	1322	
		59	08	A0	3C	0012A	MOVZWL	8(R0), ACE_POINTER			
		59			50	C0	0012E	ADDL2	R0, ACE_POINTER		
		50	08	AE	D0	00131	14\$: MOVL	ACL_POINTER, R0		1329	
53		59			50	C3	00135	SUBL3	R0, ACE_POINTER, R3		
		04	F4	A3	9E	00139	MOVAB	-12(R3), ACL_SPLIT			
		56	08	A0	3C	0013E	MOVZWL	8(R0), ACL_LENGTH		1330	
		56			0B	C2	00142	SUBL2	#11, ACL_LENGTH		
		53			68	9A	00145	MOVZBL	(ACE), R3	1331	
		52			7643	9E	00148	MOVAB	-(ACL_LENGTH)[R3], R2		
	00000200	8F			52	D1	0014C	C MPL	R2, #512		
					4E	1A	00153	BGTRU	15\$		
					07	DD	00155	PUSHL	#7	1334	
			0C		A2	9F	00157	PUSHAB	12(R2)		
	00000000G	00			02	FB	0015A	CALLS	#2, ALLOC PAGED		
		57			50	D0	00161	MOVL	R0, NEW_ACL		
		50			68	9A	00164	MOVZBL	(ACE), R0	1335	
		51	0C	A046	9E	00167	MOVAB	12(R0)[ACL_LENGTH], R1			
		08		A7	51	B0	0016C	MOVW	R1, 8(NEW_ACL)		
		50	08	AE	D0	00170	MOVL	ACL_POINTER, R0		1336	
0C	A7	0C	04	AE	28	00174	MOV C3	ACL_SPLIT, 12(R0), 12(NEW_ACL)		1337	
				59	53	D0	0017B	MOVL	R3, ACE_POINTER		

: R

		50		68	9A 0017E	MOVZBL	(ACE), R0	1338
69		68		50	28 00181	MOVCL3	R0, (ACE), (ACE_POINTER)	
		59		53	D0 00185	MOVL	R3, ACE_POINTER	
52		56	04	AE	C3 00188	SUBL3	ACL_SPLIT, ACL_LENGTH, R2	1339
50	08	AE	04	AE	C1 0018D	ADDL3	ACL_SPLIT, ACL_POINTER, R0	1340
69	0C	A0		52	28 00193	MOVCL3	R2, -12(R0), (ACE_POINTER)	
		50	08	AE	D0 00198	MOVL	ACL_POINTER, R0	1341
	04	B0		67	0E 0019C	INSQUE	(NEW_ACL), @4(R0)	
				00DD	31 001A0	BRW	18\$	1331
52		56	04	AE	C3 001A3	SUBL3	ACL_SPLIT, ACL_LENGTH, R2	1354
		52		0C	C0 001A8	ADDL2	#12, R2	
50		56	04	AE	C3 001AB	SUBL3	ACL_SPLIT, ACL_LENGTH, R0	1351
		50	04	AE	D1 001B0	CMP	ACL_SPLIT, R0	
				66	1A 001B4	BGTRU	16\$	
				07	DD 001B6	PUSHL	#7	1354
				52	DD 001B8	PUSHL	R2	
	00000000G	00		02	FB 001BA	CALLS	#2, ALLOC_PAGED	
		57		50	D0 001C1	MOVL	R0, NEW_ACL	
08		56	04	AE	C3 001C4	SUBL3	ACL_SPLIT, ACL_LENGTH, R2	1355
		52		0C	A1 001C9	ADDW3	#12, R2, 8(NEW_ACL)	
		56	04	AE	C3 001CE	SUBL3	ACL_SPLIT, ACL_LENGTH, R2	1356
		50	04	AE	C1 001D3	ADDL3	ACL_SPLIT, ACL_POINTER, R0	1357
0C		A0		52	28 001D9	MOVCL3	R2, -12(R0), 12(NEW_ACL)	
	08	BE		67	0E 001DF	INSQUE	(NEW_ACL), @ACL_POINTER	1358
				07	DD 001E3	PUSHL	#7	1359
		50		68	9A 001E5	MOVZBL	(ACE), R0	
		50	08	AE	C0 001E8	ADDL2	ACL_SPLIT, R0	
			0C	A0	9F 001EC	PUSHAB	12(R0)	
	00000000G	00		02	FB 001E9	CALLS	#2, ALLOC_PAGED	
		57		50	D0 001F6	MOVL	R0, NEW_ACL	
		50		68	9A 001F9	MOVZBL	(ACE), R0	1360
08		50	04	AE	C0 001FC	ADDL2	ACL_SPLIT, R0	
		50		0C	A1 00200	ADDW3	#12, R0, 8(NEW_ACL)	
		50	08	AE	D0 00205	MOVL	ACL_POINTER, R0	1361
0C		A0	04	AE	28 00209	MOVCL3	ACL_SPLIT, 12(R0), 12(NEW_ACL)	1362
		59		53	D0 00210	MOVL	R3, ACE_POINTER	
		50		68	9A 00213	MOVZBL	(ACE), R0	1363
69		68		50	28 00216	MOVCL3	R0, (ACE), (ACE_POINTER)	
				60	11 0021A	BRB	17\$	1364
				07	DD 0021C	PUSHL	#7	1368
				6342	9F 0021E	PUSHAB	(R3)[R2]	
	00000000G	00		02	FB 00221	CALLS	#2, ALLOC_PAGED	
		57		50	D0 00228	MOVL	R0, NEW_ACL	
52		56	04	AE	C3 0022B	SUBL3	ACL_SPLIT, ACL_LENGTH, R2	1369
		50		68	9A 00230	MOVZBL	(ACE), R0	
		52		50	C0 00233	ADDL2	R0, R2	
08		52		0C	A1 00236	ADDW3	#12, R2, 8(NEW_ACL)	
		50		68	9A 0023B	MOVZBL	(ACE), R0	1370
0C		68		50	28 0023E	MOVCL3	R0, (ACE), 12(NEW_ACL)	
		59		53	D0 00243	MOVL	R3, ACE_POINTER	
52		56	04	AE	C3 00246	SUBL3	ACL_SPLIT, ACL_LENGTH, R2	1371
50	08	AE	04	AE	C1 0024B	ADDL3	ACL_SPLIT, ACL_POINTER, R0	1372
69	0C	A0		52	28 00251	MOVCL3	R2, -12(R0), (ACE_POINTER)	
	08	BE		67	0E 00256	INSQUE	(NEW_ACL), @ACL_POINTER	1373
				07	DD 0025A	PUSHL	#7	1374
7E	08	AE		0C	C1 0025C	ADDL3	#12, ACL_SPLIT, -(SP)	
	00000000G	00		02	FB 00261	CALLS	#2, ALLOC_PAGED	

ACL\_ADDENTRY - add an ACE to an ACL

B 14  
15-Sep-1984 23:51:08  
14-Sep-1984 12:30:07

VAX-11 Bliss-32 V4.0-742  
DISK\$VMSMASTER:[F11X.SRC]ACLSUBR.B32;1

08	A7	04	57	50	D0	00268	MOVL	R0, NEW_ACL	:			
			AE	0C	A1	0026B	ADDW3	#12, ACE_SPLIT, 8(NEW_ACL)	:	1375		
			50	08	AE	D0	00271	MOVL	ACL_POINTER, R0	:	1376	
0C	A7	0C	AU	04	AE	28	00275	MOVC3	ACL_SPLIT, 12(R0), 12(NEW_ACL)	:		
		08	BE	67	0E	0027C	17\$:	INSQUE	(NEW_ACL), @ACL_POINTER	:	1377	
		08	AE	08	BE	0F	00280	18\$:	REMQE	@ACL_POINTER, ACL_POINTER	:	1380
				07	DD	00285		PUSHL	#7	:	1381	
				CC	AE	DD	00287	PUSHL	ACL_POINTER	:		
	00000000G	00		02	FB	0028A		CALLS	#2, DALLOC_PAGED	:		
		05		01	A8	91	00291	19\$:	CMPB	1(ACE), #5	:	1387
				06	13	00295		BEQL	20\$	:		
		06		01	A8	91	00297		CMPB	1(ACE), #6	:	1388
				05	12	0029B		BNEQ	21\$	:		
				08	BC	D6	0029D	20\$:	INCL	@ACL_CONTEXT	:	1389
				05	11	002A0		BRB	22\$	:		
		08	BC	01	AA	9E	002A2	21\$:	MOVAB	1(R10), @ACL_CONTEXT	:	1390
			50	68	9A	002A7	22\$:	MOVZBL	(ACE), R0	:	1392	
			5B	50	C2	002AA		SUBL2	R0, COUNT	:		
			50	68	9A	002AD		MOVZBL	(ACE), R0	:	1393	
			58	50	C0	002B0		ADDL2	R0, ACE	:		
				FD57	31	002B3		BRW	1\$	:	1243	
			50	01	D0	002B6	23\$:	MOVL	#1, R0	:	1396	
				04	04	002B9		RET		:	1398	

; Routine Size: 698 bytes, Routine Base: \$CODE\$ + 0049

ACL\_DELENTY - remove an ACE from an ACL

```

412 1399 1 %SBTTL 'ACL DELENTY - remove an ACE from an ACL'
413 1400 1 GLOBAL ROUTINE ACL_DELENTY (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, ACE) =
414 1401 1
415 1402 1 !++
416 1403 1
417 1404 1 FUNCTIONAL DESCRIPTION:
418 1405 1
419 1406 1 This routine is used to delete an Access Control Entry from a file ACL.
420 1407 1 If the ACL context is valid, and no ACE is specified, then the ACE
421 1408 1 pointed to by the context is removed. If an ACE is specified,
422 1409 1 regardless of the ACL context, it is first located and then removed.
423 1410 1
424 1411 1 CALLING SEQUENCE:
425 1412 1 ACL_DELENTY (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, ACE)
426 1413 1
427 1414 1 INPUT PARAMETERS:
428 1415 1 ACL_QUEUE_HEAD: address of queue header for ACL
429 1416 1 ACL_CONTEXT: address of ACL context longword
430 1417 1 COUNT: size of the user Access Control Entry
431 1418 1 ACE: address of the user Access Control Entry
432 1419 1
433 1420 1 IMPLICIT INPUTS:
434 1421 1 NONE
435 1422 1
436 1423 1 OUTPUT PARAMETERS:
437 1424 1 NONE
438 1425 1
439 1426 1 IMPLICIT OUTPUTS:
440 1427 1 NONE
441 1428 1
442 1429 1 ROUTINE VALUE:
443 1430 1 1
444 1431 1
445 1432 1 SIDE EFFECTS:
446 1433 1 The Specified ACE is removed from the ACL. If the ACL segment is then
447 1434 1 empty, it is removed from the chain. The ACL context is updated to
448 1435 1 point to the next ACE in the ACL.
449 1436 1
450 1437 1 --
451 1438 1
452 1439 2 BEGIN
453 1440 2
454 1441 2 MAP
455 1442 2 ACL_QUEUE_HEAD : REF $BLOCK, ! Queue header for ACL
456 1443 2 ACL_CONTEXT : REF $BLOCK, ! Context longword
457 1444 2 ACE : REF $BLOCK; ! Address of the user ACE
458 1445 2
459 1446 2 LOCAL
460 1447 2 ACL_POINTER : REF $BLOCK, ! Pointer to current ACL segment
461 1448 2 ACL_SPLIT : REF $BLOCK, ! Offset to current ACE
462 1449 2 ACE_POINTER : REF $BLOCK, ! Pointer to current ACE
463 1450 2 ACE_NUMBER, ! Index of ACE in ACL
464 1451 2 ACL_LENGTH, ! Length of all ACE's in segment
465 1452 2 NEW_ACL : REF $BLOCK; ! Address of the new ACL segment
466 1453 2
467 1454 2
468 1455 2 ! Sanity check the length of the supplied ACE.

```

```

469 1456 2
470 1457 2 IF .COUNT LSSU 4
471 1458 2 AND .COUNT NEQ 0
472 1459 2 THEN RETURN SSS_BADPARAM;
473 1460 2
474 1461 2 ! Locate the ACE by content if the content is specified. Note that this
475 1462 2 ! will change the context.
476 1463 2
477 1464 2 IF .ACL_QUEUE_HEAD[ACL$FLINK] EQLA ACL_QUEUE_HEAD[ACL$FLINK]
478 1465 2 THEN ACC_ERROR (SS$ACLEMPY);
479 1466 2
480 1467 2 IF .COUNT NEQ 0
481 1468 2 THEN IF NOT ACL_FINDENTRY (.ACL_QUEUE_HEAD, .ACL_CONTEXT, .COUNT, .ACE, 1)
482 1469 2 THEN ACL_ERROR (SS$NOENTRY);
483 1470 2
484 1471 2 ACE_NUMBER = ACL_LOCATEACE (.ACL_QUEUE_HEAD, .ACL_CONTEXT[CONTEXT_INDEX], ACL_POINTER, ACL_SPLIT);
485 1472 2 ACE_POINTER = ACC_POINTER[ACL$LIST] + .ACL_SPLIT;
486 1473 2
487 1474 2 ! Having located the ACE, compute the length of the remaining segment.
488 1475 2 ! If it is non-null, allocate a new segment and copy in the remaining
489 1476 2 ! portions of the old one. Finally deallocate the old segment.
490 1477 2
491 1478 2 ACL_LENGTH = .ACL_POINTER[ACL$W_SIZE] - ACL$C_LENGTH - .ACE_POINTER[ACE$B_SIZE];
492 1479 2 IF .ACL_LENGTH NEQ 0
493 1480 2 THEN
494 1481 3 BEGIN
495 1482 3 NEW_ACL = ALLOC PAGED (ACL$C_LENGTH + .ACL_LENGTH, ACL_TYPE);
496 1483 3 NEW_ACL[ACL$W_SIZE] = ACL$C_LENGTH + .ACL_LENGTH;
497 1484 3 CH$MOVE (.ACL_SPLIT, ACL_POINTER[ACL$LIST], NEW_ACL[ACL$LIST]);
498 1485 3 CH$MOVE (.ACL_LENGTH - .ACL_SPLIT,
499 1486 3 ACL_POINTER[ACL$LIST] + .ACL_SPLIT + .ACE_POINTER[ACE$B_SIZE],
500 1487 3 NEW_ACL[ACL$LIST] + .ACL_SPLIT);
501 1488 3 INSQUE (.NEW_ACL, .ACL_POINTER[ACL$BLINK]);
502 1489 2 END;
503 1490 2
504 1491 2 REMQUE (.ACL_POINTER, ACL_POINTER);
505 1492 2 DALLOC_PAGED (.ACL_POINTER, ACL_TYPE);
506 1493 2
507 1494 2 RETURN 1;
508 1495 2
509 1496 1 END;

```

! End of routine ACL\_DELENTY

				01FC 0000	.ENTRY	ACL_DELENTY, Save R2,R3,R4,R5,R6,R7,R8	: 1400
	5E		08	C2 00002	SUBL2	#8, SP	
	04	0C	AC	D1 00005	CMP	COUNT, #4	: 1457
			09	1E 00009	BGEQU	1\$	
		0C	AC	D5 0000B	TSTL	COUNT	: 1458
			04	13 0000E	BEQL	1\$	
	50		14	D0 00010	MOVL	#20, R0	: 1459
				04 00013	RET		
	04	AC	04	BC D1 00014 1\$:	CMP	@ACL_QUEUE_HEAD, ACL_QUEUE_HEAD	: 1464
			18	12 00019	BNEQ	2\$	
0C	AC	00	6E	00 2C 0001B	MOVCS	#0, (SP), #0, COUNT, @ACE	: 1465





```

: 511 1497 1 %SBTTL 'ACL_MODENTRY - modify an existing ACE'
: 512 1498 1 GLOBAL ROUTINE ACL_MODENTRY (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, ACE) =
: 513 1499 1
: 514 1500 1 ++
: 515 1501 1
: 516 1502 1 FUNCTIONAL DESCRIPTION:
: 517 1503 1
: 518 1504 1 This routine is used to replace an Access Control Entry in a file ACL.
: 519 1505 1 The entry pointed to by the context is replaced with the ACE given.
: 520 1506 1
: 521 1507 1 CALLING SEQUENCE:
: 522 1508 1 ACL_MODENTRY (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, ACE)
: 523 1509 1
: 524 1510 1 INPUT PARAMETERS:
: 525 1511 1 ACL_QUEUE_HEAD: address of queue header for ACL
: 526 1512 1 ACL_CONTEXT: address of ACL context longword
: 527 1513 1 COUNT: size of the user Access Control Entry
: 528 1514 1 ACE: address of the user Access Control Entry
: 529 1515 1
: 530 1516 1 IMPLICIT INPUTS:
: 531 1517 1 NONE
: 532 1518 1
: 533 1519 1 OUTPUT PARAMETERS:
: 534 1520 1 NONE
: 535 1521 1
: 536 1522 1 IMPLICIT OUTPUTS:
: 537 1523 1 NONE
: 538 1524 1
: 539 1525 1 ROUTINE VALUE:
: 540 1526 1 1
: 541 1527 1
: 542 1528 1 SIDE EFFECTS:
: 543 1529 1 The ACE is replaced with the new one. This is done by deleting the
: 544 1530 1 ACE pointed to by the context and then inserting (adding) the
: 545 1531 1 changed ACE.
: 546 1532 1
: 547 1533 1 --
: 548 1534 1
: 549 1535 2 BEGIN
: 550 1536 2
: 551 1537 2 MAP
: 552 1538 2 ACL_QUEUE_HEAD : REF $BLOCK, ! Queue header for ACL
: 553 1539 2 ACL_CONTEXT : REF $BLOCK, ! Context longword
: 554 1540 2 ACE : REF $BLOCK; ! Address of user supplied ACE
: 555 1541 2
: 556 1542 2 LOCAL
: 557 1543 2 ACL_POINTER : REF $BLOCK, ! Pointer to current ACL segment
: 558 1544 2 ACL_SPLIT : REF $BLOCK, ! Offset to current ACE
: 559 1545 2 ACE_POINTER : REF $BLOCK, ! Pointer to current ACE
: 560 1546 2 ACE_NUMBER; ! Index of ACE in ACL
: 561 1547 2
: 562 1548 2
: 563 1549 2 ! Sanity check the length of the supplied ACE.
: 564 1550 2
: 565 1551 2 IF .COUNT LSSU 4
: 566 1552 2 THEN RETURN $$$_BADPARAM;
: 567 1553 2

```

```

: 568 1554 2 ! Check for something in the ACL.
: 569 1555 2
: 570 1556 2 IF .ACL_QUEUE_HEAD[ACL$FLINK] EQLA ACL_QUEUE_HEAD[ACL$FLINK]
: 571 1557 2 THEN ACC_ERROR (SS$ACEMPTY);
: 572 1558 2
: 573 1559 2 ! Now locate the ACE to be modified.
: 574 1560 2
: 575 1561 2 ACE_NUMBER = ACL_LOCATEACE (.ACL_QUEUE_HEAD, .ACL_CONTEXT[CONTEXT_INDEX], ACL_POINTER, ACL_SPLIT);
: 576 1562 2 IF .ACL_POINTER[ACL$FLINK] EQLA ACL_QUEUE_HEAD[ACL$FLINK]
: 577 1563 2 AND .ACC_SPLIT EQL .ACL_POINTER[ACL$W_SIZE] - ACL$C_LENGTH
: 578 1564 2 THEN ACL_ERROR (SS$NOENTRY);
: 579 1565 2
: 580 1566 2 ! Remove the old ACE by context.
: 581 1567 2
: 582 1568 2 ACL_DELENTY (.ACL_QUEUE_HEAD, .ACL_CONTEXT, 0, 0);
: 583 1569 2
: 584 1570 2 ! Insert the new ACE.
: 585 1571 2
: 586 1572 2 ACL_ADDENTRY (.ACL_QUEUE_HEAD, .ACL_CONTEXT, .COUNT, .ACE);
: 587 1573 2
: 588 1574 2 RETURN 1;
: 589 1575 2
: 590 1576 1 END;

```

! End of routine ACL\_MODENTRY

					003C 00000	.ENTRY	ACL_MODENTRY, Save R2,R3,R4,R5		1498
		5E		08	C2 00002	SUBL2	#8, SP		
		04	0C	AC	D1 00005	CMPL	COUNT, #4		1551
				04	1E 00009	BGEQU	1\$		
		50		14	D0 0000B	MOVL	#20, R0		1552
					04 0000E	RET			
		04	AC	04	BC D1 0000F	1\$:	CMPL @ACL_QUEUE_HEAD, ACL_QUEUE_HEAD		1556
					18 12 00014	BNEQ	2\$		
0C	AC		00	6E	00 2C 00016	MOVCS	#0, (SP), #0, COUNT, @ACE		1557
					10 BC 0001C				
		50		10	AC D0 0001E	MOVL	ACE, R0		
		02	A0	09D0	8F B0 00022	MOVW	#2512, 2(R0)		
			50	09D0	8F 3C 00028	MOVZWL	#2512, R0		
					04 0002D	RET			
					5E DD 0002E	2\$:	PUSHL SP		1561
				08	AE 9F 00030	PUSHAB	ACL_POINTER		
	7E		08	BC	00 EF 00033	EXTZV	#0, #24, @ACL_CONTEXT, -(SP)		
					04 AC DD 00039	PUSHL	ACL_QUEUE_HEAD		
		0000V	CF	04	04 FB 0003C	CALLS	#4, ACL_LOCATEACE		
			50	04	AE D0 00041	MOVL	ACL_POINTER, R0		1562
		04	AC	04	60 D1 00045	CMPL	(R0), ACL_QUEUE_HEAD		
					24 12 00049	BNEQ	3\$		
		50		08	A0 3C 0004B	MOVZWL	8(R0), R0		1563
		50			0C C2 0004F	SUBL2	#12, R0		
		50			6E D1 00052	CMPL	ACL_SPLIT, R0		
					18 12 00055	BNEQ	3\$		
0C	AC		00	6E	00 2C 00057	MOVCS	#0, (SP), #0, COUNT, @ACE		1564
					10 BC 0005D				
		50		10	AC D0 0005F	MOVL	ACE, R0		

ACL\_MODENTRY - modify an existing ACE

H 14  
15-Sep-1984 23:51:08  
14-Sep-1984 12:30:07

02	A0	09D8	8F	B0	00063	MOVW	#2520, 2(R0)	:	
	50	09D8	8F	3C	00069	MOVZWL	#2520, R0	:	
				04	0006E	RET		:	
			7E	7C	0006F	CLRQ	-(SP)	:	1568
FEA6	7E	04	AC	7D	00071	MOVQ	ACL_QUEUE HEAD, -(SP)	:	
	CF		04	FB	00075	CALLS	#4, -ACL_DELENTRY	:	
	7E	0C	AC	7D	0007A	MOVQ	COUNT, =(SP)	:	1572
	7E	04	AC	7D	0007E	MOVQ	ACL_QUEUE HEAD, -(SP)	:	
FBDF	CF		04	FB	00082	CALLS	#4, -ACL_ADDENTRY	:	
	50		01	D0	00087	MOVL	#1, R0	:	1574
			04	0008A	RET			:	1576

; Routine Size: 139 bytes, Routine Base: \$CODE\$ + 03E3

```

592 1577 1 %SBTTL 'ACL_FINDENTRY - locate a specific ACE'
593 1578 1 GLOBAL ROUTINE ACL_FINDENTRY (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, ACE, INTERNAL) =
594 1579 1
595 1580 1 !++
596 1581 1
597 1582 1 FUNCTIONAL DESCRIPTION:
598 1583 1
599 1584 1 This routine locates the specified Access Control Entry and sets the
600 1585 1 ACL context accordingly.
601 1586 1
602 1587 1 CALLING SEQUENCE:
603 1588 1 ACL_FINDENTRY (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, ACE, INTERNAL)
604 1589 1
605 1590 1 INPUT PARAMETERS:
606 1591 1 ACL_QUEUE_HEAD: address of queue header for ACL
607 1592 1 ACL_CONTEXT: address of ACL context longword
608 1593 1 COUNT: size of the user Access Control Entry
609 1594 1 ACE: address of the user Access Control Entry
610 1595 1 INTERNAL: 0 call generated by a user request
611 1596 1 1 call generated within the system
612 1597 1
613 1598 1 IMPLICIT INPUTS:
614 1599 1 NONE
615 1600 1
616 1601 1 OUTPUT PARAMETERS:
617 1602 1 NONE
618 1603 1
619 1604 1 IMPLICIT OUTPUTS:
620 1605 1 NONE
621 1606 1
622 1607 1 ROUTINE VALUE:
623 1608 1 1 if successful
624 1609 1 0 otherwise
625 1610 1
626 1611 1 SIDE EFFECTS:
627 1612 1 NONE
628 1613 1
629 1614 1 --
630 1615 1
631 1616 2 BEGIN
632 1617 2
633 1618 2 MAP
634 1619 2 ACL_QUEUE_HEAD : REF $BBLOCK, ! Queue header for ACL
635 1620 2 ACL_CONTEXT : REF $BBLOCK, ! Context longword
636 1621 2 ACE : REF $BBLOCK; ! Address of user ACE
637 1622 2
638 1623 2 LOCAL
639 1624 2 ACL_POINTER : REF $BBLOCK, ! Pointer to current ACL segment
640 1625 2 ACL_SPLIT : REF $BBLOCK, ! Offset to current ACE
641 1626 2 ACE_POINTER : REF $BBLOCK, ! Pointer to current ACE
642 1627 2 ACE_NUMBER; ! Index of ACE in ACL
643 1628 2
644 1629 2
645 1630 2 ! Sanity check the length of the supplied ACE.
646 1631 2
647 1632 2 IF .COUNT LSSU 4
648 1633 2 THEN RETURN $$_BADPARAM;

```



```

: 706      1691  5      AND CH$EQL (.ACE[ACESB_SIZE] - $BYTEOFFSET (ACESL_KEY)
: 707      1692  5      - .ACE[ACESV_RESERVED]*4,
: 708      1693  5      ACE[ACESL_KEY] + .ACE[ACESV_RESERVED]*4,
: 709      1694  5      .ACE_POINTER[ACESB_SIZE] - $BYTEOFFSET (ACESL_KEY)
: 710      1695  5      - .ACE_POINTER[ACESV_RESERVED]*4,
: 711      1696  5      ACE_POINTER[ACESL_KEY] + .ACE_POINTER[ACESV_RESERVED]*4);
: 712      1697  5
: 713      1698  5      [ACESC_AUDIT,
: 714      1699  5      ACESC_ALARM]:
: 715      1700  5      ..ACE EQL ..ACE_POINTER
: 716      1701  5      AND CH$EQL (.ACE[ACESB_SIZE] - $BYTEOFFSET (ACEST_AUDITNAME),
: 717      1702  5      ACE[ACEST_AUDITNAME],
: 718      1703  5      .ACE[ACESB_SIZE] - $BYTEOFFSET (ACEST_AUDITNAME),
: 719      1704  5      ACE_POINTER[ACEST_AUDITNAME]);
: 720      1705  5
: 721      1706  5      TES
: 722      1707  5      END
: 723      1708  4      THEN
: 724      1709  5      BEGIN
: 725      1710  5      .ACL_CONTEXT = .ACE_NUMBER;
: 726      1711  5      ACL_CONTEXT[CONTEXT_TYPE] = .ACE_POINTER[ACESB_TYPE];
: 727      1712  5      RETURN 1;
: 728      1713  4      END;
: 729      1714  4
: 730      1715  4      ACE_POINTER = .ACE_POINTER + .ACE_POINTER[ACESB_SIZE];
: 731      1716  3      END;
: 732      1717  3      END
: 733      1718  2      UNTIL .ACL_POINTER[ACLSL_FLINK] EQLA ACL_QUEUE_HEAD[ACLSL_FLINK];
: 734      1719  2      .ACL_CONTEXT = 0;
: 735      1720  2
: 736      1721  2      ! At this point the desired ACE has not been found. Return failure.
: 737      1722  2
: 738      1723  2      IF .INTERNAL THEN RETURN 0 ELSE ACL_ERROR (SS$_NOENTRY);
: 739      1724  2
: 740      1725  1      END;

```

! End of routine ACL\_FINDENTRY

				01FC 00000	.ENTRY	ACL_FINDENTRY, Save R2,R3,R4,R5,R6,R7,R8	: 1578
		04	0C	AC D1 00002	CMP	COUNT, #4	: 1632
		50		04 1E 00006	BGEQU	1\$	:
				14 D0 00008	MOVL	#20, R0	: 1633
				04 0000B	RET		:
0C	AC	10	BC	08 00 ED 0000C 1\$:	CMPZV	#0, #8, @ACE, COUNT	: 1638
				18 1B 00013	BLEQU	2\$	:
0C	AC		00	6E 00 2C 00015	MOVCS	#0, (SP), #0, COUNT, @ACE	: 1639
				10 BC 0001B			:
		50	10	AC D0 0001D	MOVL	ACE, R0	:
02	A0	21E4	8F	B0 00021	MOVW	#8676, 2(R0)	:
	50	21E4	8F	3C 00027	MOVZWL	#8676, R0	:
				04 0002C	RET		:
	04	AC	04	BC D1 0002D 2\$:	CMP	@ACL_QUEUE_HEAD, ACL_QUEUE_HEAD	: 1645
				22 12 00032	BNEQ	4\$	:
			08	BC D4 00034	CLRL	@ACL_CONTEXT	: 1646
	03		14	AC E9 00037	BLBC	INTERNAL, 3\$	: 1647





ACL\_FINDENTRY - locate a specific ACE

			50		08	C2	000F7		SUBL2	#8, R0		
	08	A4	08	A6		50	29	000FA	CMPC3	R0, 8(R6), 8(ACE_POINTER)	1704	
						0F	12	00100	BNEQ	14\$		
			08	BC		58	D0	00102	MOVL	ACE_NUMBER, @ALL_CONTEXT	1710	
08	BC			18	01	A4	F0	00106	INSV	1(ACE_POINTER), #24, #8, @ACL_CONTEXT	1711	
		08		50		01	D0	00100	MOVL	#1, R0	1712	
							04	00110	RET			
				50		64	9A	00111	MOVZBL	(ACE_POINTER), R0	1715	
				54		50	C0	00114	ADDL2	R0, ACE_POINTER		
						FF49	31	00117	BRW	6\$	1658	
		04	AC			65	D1	0011A	CMP	(ACL_POINTER), ACL_QUEUE_HEAD	1718	
						03	13	0011E	BEQL	16\$		
						FF39	31	00120	BRW	5\$		
					08	BC	D4	00123	CLRL	@ACL_CONTEXT	1719	
				03	14	AC	E9	00126	BLBC	INTERNAL, 18\$	1723	
						50	D4	0012A	CLRL	R0		
							04	0012C	RET			
0C	AC		00	6E		00	2C	0012D	MOVCS	#0, (SP), #0, COUNT, @ACE		
						10	BC	00133				
				50	10	AC	D0	00135	MOVL	ACE, R0		
		02		07	09D8	8F	B0	00139	MOVW	#2520, 2(R0)		
				50	09D8	8F	3C	0013F	MOVZWL	#2520, R0		
						04	00144		RET		1725	

; Routine Size: 325 bytes, Routine Base: \$CODE\$ + 046E

ACL\_FINDTYPE - locate a specific type of ACE

```

742 1726 1 %SBTTL 'ACL_FINDTYPE - locate a specific type of ACE'
743 1727 1 GLOBAL ROUTINE ACL_FINDTYPE (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, ACE, INTERNAL) =
744 1728 1
745 1729 1 :++
746 1730 1
747 1731 1 : FUNCTIONAL DESCRIPTION:
748 1732 1
749 1733 1 : This routine locates an Access Control Entry of a specific type.
750 1734 1 : The ACL context is set accordingly.
751 1735 1
752 1736 1 : CALLING SEQUENCE:
753 1737 1 : ACL_FINDTYPE (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, ACE, INTERNAL)
754 1738 1
755 1739 1 : INPUT PARAMETERS:
756 1740 1 : ACL_QUEUE_HEAD: address of queue header for ACL
757 1741 1 : ACL_CONTEXT: address of ACL context longword
758 1742 1 : COUNT: size of the user Access Control Entry
759 1743 1 : ACE: address of the user Access Control Entry
760 1744 1 : INTERNAL. 0 call generated by a user request
761 1745 1 : 1 call generated within the system
762 1746 1
763 1747 1 : IMPLICIT INPUTS:
764 1748 1 : NONE
765 1749 1
766 1750 1 : OUTPUT PARAMETERS:
767 1751 1 : NONE
768 1752 1
769 1753 1 : IMPLICIT OUTPUTS:
770 1754 1 : NONE
771 1755 1
772 1756 1 : ROUTINE VALUE:
773 1757 1 : 1 if successful
774 1758 1 : 0 otherwise
775 1759 1
776 1760 1 : SIDE EFFECTS:
777 1761 1 : NONE
778 1762 1
779 1763 1 :--
780 1764 1
781 1765 2 BEGIN
782 1766 2
783 1767 2 MAP
784 1768 2 : ACL_QUEUE_HEAD : REF $BLOCK, : Queue header for ACL
785 1769 2 : ACL_CONTEXT : REF $BLOCK, : Context longword
786 1770 2 : ACE : REF $BLOCK; : Address of the user ACE
787 1771 2
788 1772 2 LOCAL
789 1773 2 : ACL_POINTER : REF $BLOCK, : Pointer to current ACL segment
790 1774 2 : ACL_SPLIT : REF $BLOCK, : Offset to current ACE
791 1775 2 : ACE_POINTER : REF $BLOCK, : Pointer to current ACE
792 1776 2 : ACE_NUMBER; : Index of ACE in ACL
793 1777 2
794 1778 2
795 1779 2 : Sanity check the length of the supplied ACE.
796 1780 2
797 1781 2 IF .COUNT LSSU 4
798 1782 2 THEN RETURN $$$_BADPARAM;

```

```

799 1783 2
800 1784 2 ! Determine if the ACL is empty. If it is, set the context to zero, indicate
801 1785 2 ! a failure by clearing the returning ACE, and return success.
802 1786 2
803 1787 2 IF .ACL_QUEUE_HEAD[ACL$$_FLINK] EQLA ACL_QUEUE_HEAD[ACL$$_FLINK]
804 1788 2 THEN
805 1789 2 BEGIN
806 1790 2 .ACL_CONTEXT = 0;
807 1791 2 IF .INTERNAL THEN RETURN 0 ELSE ACL_ERROR (SS$_ACLEMPY);
808 1792 2 END;
809 1793 2
810 1794 2 ! If the search is for an ACE type different from the last ACE type found,
811 1795 2 ! start from the beginning of the ACL. Otherwise, continue the search from
812 1796 2 ! the ACE after the last one found. If the ACE type is found, save the
813 1797 2 ! current context and return the contents of the ACE. If the ACE type was
814 1798 2 ! not found, determine whether or not it is the first time through and set
815 1799 2 ! the appropriate error status.
816 1800 2
817 1801 2 IF .ACL_CONTEXT[CONTEXT_TYPE] EQL 0
818 1802 2 OR .ACL_CONTEXT[CONTEXT_TYPE] NEQ .ACE[ACESB_TYPE]
819 1803 2 THEN .ACL_CONTEXT = 0;
820 1804 2 ACE_NUMBER = ACL_LOCATEACE (.ACL_QUEUE_HEAD, .ACL_CONTEXT[CONTEXT_INDEX] + 1, ACL_POINTER, ACL_SPLIT);
821 1805 2 ACE_POINTER = ACE_POINTER[ACL$$_LIST] + .ACL_SPLIT;
822 1806 2
823 1807 2 WHILE 1
824 1808 2 DO
825 1809 2 BEGIN
826 1810 2 IF .ACE_POINTER GEQA .ACL_POINTER + .ACL_POINTER[ACL$$_SIZE]
827 1811 2 THEN
828 1812 2 BEGIN
829 1813 2 ACE_POINTER = .ACL_POINTER[ACL$$_FLINK];
830 1814 2 ACE_POINTER = ACE_POINTER[ACL$$_LIST];
831 1815 2 END;
832 1816 2 IF ACE_POINTER[ACL$$_FLINK] EQLA ACL_QUEUE_HEAD[ACL$$_FLINK]
833 1817 2 THEN EXITLOOP;
834 1818 2
835 1819 2 IF .ACE[ACESB_TYPE] EQL .ACE_POINTER[ACESB_TYPE]
836 1820 2 AND (IF .ACE[ACESB_TYPE] NEQ ACESC_INFO
837 1821 2 THEN 1
838 1822 2 ELSE .ACE[ACESV_INFO_TYPE] EQL .ACE_POINTER[ACESV_INFO_TYPE])
839 1823 2 THEN
840 1824 2 BEGIN
841 1825 2 .ACL_CONTEXT = .ACE_NUMBER;
842 1826 2 ACL_CONTEXT[CONTEXT_TYPE] = .ACE_POINTER[ACESB_TYPE];
843 1827 2 CH$COPY (.ACE_POINTER[ACESB_SIZE], .ACE_POINTER,
844 1828 2 0, .COUNT, .ACE);
845 1829 2 RETURN 1;
846 1830 2 END;
847 1831 2
848 1832 2 ACE_POINTER = .ACE_POINTER + .ACE_POINTER[ACESB_SIZE];
849 1833 2 ACE_NUMBER = .ACE_NUMBER + 1;
850 1834 2 END;
851 1835 2
852 1836 2 ! At this point the end of the ACL has been reached. Return failure.
853 1837 2
854 1838 2 .ACL_CONTEXT = 0;
855 1839 2 IF .INTERNAL THEN RETURN 0 ELSE ACL_ERROR (SS$_NOENTRY);

```



08	BC	08	08	BC	57	D0	000AF	8\$:	MOVL	ACE_NUMBER, @ACL_CONTEXT	:	1825
				18	01	A6	F0		INSV	1(ACE_POINTER), #24, #8, @ACL_CONTEXT	:	1826
				50		66	9A		MOVZBL	(ACE_POINTER), R0	:	1827
0C	AC	00		66		50	2C		MOVCS	R0, (ACE_POINTER), #0, COUNT, @ACE	:	1828
					10	BC					:	
						50	01		MOVL	#1, R0	:	1829
							04		RET		:	
						50	66		MOVZBL	(ACE_POINTER), R0	:	1832
						56	50		ADDL2	R0, ACE_POINTER	:	
							57		INCL	ACE_NUMBER	:	1833
							A0		BRB	6\$	:	1807
					08	BC	D4		CLRL	@ACL_CONTEXT	:	1838
					14	AC	E9		BLBC	INTERNAL, 12\$	:	1839
						50	D4		CLRL	R0	:	
							04		RET		:	
0C	AC	00		6E		00	2C		MOVCS	#0, (SP), #0, COUNT, @ACE	:	
					10	BC					:	
						50	10		MOVL	ACE, R0	:	
			02	A0	09D8	8F	B0		MOVW	#2520, 2(R0)	:	
				50	09D8	8F	3C		MOVZWL	#2520, R0	:	
							04		RET		:	1841

; Routine Size: 245 bytes, Routine Base: \$CODE\$ + 05B3



```

: 916 1899 2 ! Loop through removing each ACL segment and deallocate the memory. At this
: 917 1900 2 ! time, no check is made to see if any ACE within the ACL segment grants
: 918 1901 2 ! access to the file by the caller.
: 919 1902 2
: 920 1903 2 ACL_SEGMENT = .ACL_QUEUE_HEAD[ACL$$_FLINK];
: 921 1904 2 UNTIL .ACL_SEGMENT EQ LA ACL_QUEUE_HEAD[ACL$$_FLINK]
: 922 1905 2 DO
: 923 1906 2 BEGIN
: 924 1907 2 OLD_SEGMENT = .ACL_SEGMENT;
: 925 1908 2 ACL_SEGMENT = .ACL_SEGMENT[ACL$$_FLINK];
: 926 1909 2 REMOVE (.OLD_SEGMENT, DUMMY);
: 927 1910 2
: 928 1911 2 ! Preserve the protected ACEs if necessary.
: 929 1912 2
: 930 1913 2 IF .ACL_CONTEXT NEQ 0
: 931 1914 2 THEN
: 932 1915 2 BEGIN
: 933 1916 2 NEW_POINTER = OLD_POINTER = OLD_SEGMENT[ACL$$_LIST];
: 934 1917 2 NEW_LENGTH = 0;
: 935 1918 2 UNTIL .OLD_POINTER GEQA .OLD_SEGMENT + .OLD_SEGMENT[ACL$$_SIZE]
: 936 1919 2 DO
: 937 1920 2 BEGIN
: 938 1921 2 ACE_LENGTH = .OLD_POINTER[ACES$$_SIZE];
: 939 1922 2 IF .OLD_POINTER[ACES$$_PROTECTED]
: 940 1923 2 THEN
: 941 1924 2 BEGIN
: 942 1925 2 CH$MOVE (.ACE_LENGTH, .OLD_POINTER, .NEW_POINTER);
: 943 1926 2 NEW_LENGTH = .NEW_LENGTH + .ACE_LENGTH;
: 944 1927 2 NEW_POINTER = .NEW_POINTER + .ACE_LENGTH;
: 945 1928 2 END;
: 946 1929 2 OLD_POINTER = .OLD_POINTER + .ACE_LENGTH;
: 947 1930 2 END;
: 948 1931 2 IF .NEW_LENGTH NEQ 0
: 949 1932 2 THEN
: 950 1933 2 BEGIN
: 951 1934 2 NEW_SEGMENT = ALLOC PAGED (ACL$$_LENGTH + .NEW_LENGTH, ACL_TYPE);
: 952 1935 2 NEW_SEGMENT[ACL$$_SIZE] = ACL$$_LENGTH + .NEW_LENGTH;
: 953 1936 2 CH$MOVE (.NEW_LENGTH, OLD_SEGMENT[ACL$$_LIST], NEW_SEGMENT[ACL$$_LIST]);
: 954 1937 2 INSQUE (.NEW_SEGMENT, .ACL_SEGMENT[ACL$$_BLINK]);
: 955 1938 2 END;
: 956 1939 2 END;
: 957 1940 2
: 958 1941 2 DALLOC_PAGED (.OLD_SEGMENT, ACL_TYPE);
: 959 1942 2 END;
: 960 1943 2
: 961 1944 2 ! Set the context to zero, and return success.
: 962 1945 2
: 963 1946 2 IF .ACL_CONTEXT NEQ 0
: 964 1947 2 THEN .ACL_CONTEXT = 0;
: 965 1948 2
: 966 1949 2 RETURN 1;
: 967 1950 2
: 968 1951 1 END;

```

! End of routine ACL\_DELETEACL

				OFFC 00000	.ENTRY	ACL_DELETEACL, Save R2,R3,R4,R5,R6,R7,R8,- R9,R10,R11	
				08 C2 00002	SUBL2	#8, SP	1843
				04 04 BC D0 00005	MOVL	@ACL_QUEUE_HEAD, ACL_SEGMENT	1903
				5A D1 00009 1\$:	CMPL	ACL_SEGMENT, ACL_QUEUE_HEAD	1904
				6C 13 00000	BEQL	6\$	
				56 5A D0 0000F	MOVL	ACL_SEGMENT, OLD_SEGMENT	1907
				5A 6A D0 00012	MOVL	(ACL_SEGMENT), ACL_SEGMENT	1908
				6E 66 0F 00015	REMQUE	(OLD_SEGMENT), DUMMY	1909
				08 AC D5 00018	TSTL	ACL_CONTEXT	1913
				51 13 0001B	BEQL	5\$	
				04 04 57 0C A6 9E 0001D	MOVAB	12(R6), OLD_POINTER	1916
				57 D0 00021	MOVL	OLD_POINTER, NEW_POINTER	
				59 D4 00025	CLRL	NEW_LENGTH	1917
				50 08 A6 3C 00027 2\$:	MOVZWL	8(OLD_SEGMENT), R0	1918
				50 56 C0 0002B	ADDL2	OLD_SEGMENT, R0	
				50 57 D1 0002E	CMPL	OLD_POINTER, R0	
				19 1E 00031	BGEQU	4\$	
				5B 67 9A 00033	MOVZBL	(OLD_POINTER), ACE_LENGTH	1921
	0C	03		01 E1 00036	BBC	#1, 3(OLD_POINTER), 3\$	1922
04	BE			67 5B 28 0003B	MOVCL3	ACE_LENGTH, (OLD_POINTER), @NEW_POINTER	1925
				59 5B C0 00040	ADDL2	ACE_LENGTH, NEW_LENGTH	1926
		04		AE 5B C0 00043	ADDL2	ACE_LENGTH, NEW_POINTER	1927
				57 5B C0 00047 3\$:	ADDL2	ACE_LENGTH, OLD_POINTER	1929
				DB 11 0004A	BRB	2\$	1918
				59 D5 0004C 4\$:	TSTL	NEW_LENGTH	1931
				1E 13 0004E	BEQL	5\$	
				07 DD 00050	PUSHL	#7	1934
			0C	A9 9F 00052	PUSHAB	12(NEW_LENGTH)	
				02 FB 00055	CALLS	#2, ALLOC_PAGED	
				58 50 D0 0005C	MOVL	R0, NEW_SEGMENT	
08	A8			59 0C A1 0005F	ADDW3	#12, NEW_LENGTH, 8(NEW_SEGMENT)	1935
0C	A8	0C		A6 59 28 00064	MOVCL3	NEW_LENGTH, 12(OLD_SEGMENT), - 12(NEW_SEGMENT)	1936
				04 BA 68 0E 0006A	INSQUE	(NEW_SEGMENT), @4(ACL_SEGMENT)	1937
				07 DD 0006E 5\$:	PUSHL	#7	1941
				56 DD 00070	PUSHL	OLD_SEGMENT	
				02 FB 00072	CALLS	#2, DALLOC_PAGED	
				8E 11 00079	BRB	1\$	1904
			08	AC D5 0007B 6\$:	TSTL	ACL_CONTEXT	1946
				03 13 0007E	BEQL	7\$	
			08	BC D4 00080	CLRL	@ACL_CONTEXT	1947
				50 01 D0 00083 7\$:	MOVL	#1, R0	1949
				04 00086	RET		1951

; Routine Size: 135 bytes. Routine Base: \$CODE\$ + 06A8



```

970 1952 1 %SBTTL 'ACL_READACL - read one or more ACEs'
971 1953 1 GLOBAL ROUTINE ACL_READACL (ACL_QUEUE_HEAD, ACL_CONTEXT, LENGTH, ACE_BUFFER) =
972 1954 1
973 1955 1 ++
974 1956 1
975 1957 1 FUNCTIONAL DESCRIPTION:
976 1958 1
977 1959 1 This routine returns as much of the file ACL as will fit in the user's
978 1960 1 buffer. Successive calls will return the unread portions of the ACL
979 1961 1 until the entire ACL has been read. If an attempt is made to read
980 1962 1 beyond the end of the ACL, a error is returned to indicate that there
981 1963 1 is no more to be read.
982 1964 1
983 1965 1 CALLING SEQUENCE:
984 1966 1 ACL_READACL (ACL_QUEUE_HEAD, ACL_CONTEXT, LENGTH, ACE_BUFFER)
985 1967 1
986 1968 1 INPUT PARAMETERS:
987 1969 1 ACL_QUEUE_HEAD: address of queue header for ACL
988 1970 1 ACL_CONTEXT: address of ACL context longword
989 1971 1 LENGTH: size of the user buffer
990 1972 1 ACE_BUFFER: address of the user buffer
991 1973 1
992 1974 1 IMPLICIT INPUTS:
993 1975 1 NONE
994 1976 1
995 1977 1 OUTPUT PARAMETERS:
996 1978 1 NONE
997 1979 1
998 1980 1 IMPLICIT OUTPUTS:
999 1981 1 NONE
1000 1982 1
1001 1983 1 ROUTINE VALUE:
1002 1984 1 1 if successful
1003 1985 1 0 otherwise
1004 1986 1
1005 1987 1 SIDE EFFECTS:
1006 1988 1 The users's buffer is filled with as much of the ACL as will fit.
1007 1989 1 (Only entire ACE's are transferred.) The ACL context is then updated
1008 1990 1 to point to the next available ACE.
1009 1991 1
1010 1992 1 --
1011 1993 1
1012 1994 2 BEGIN
1013 1995 2
1014 1996 2 MAP
1015 1997 2 ACL_QUEUE_HEAD : REF $BLOCK, : Queue header for ACL
1016 1998 2 ACL_CONTEXT : REF $BLOCK; : Context longword
1017 1999 2
1018 2000 2 LOCAL
1019 2001 2 COUNT, : Remaining buffer size
1020 2002 2 ACE : REF $BLOCK, : Address of the user ACE buffer
1021 2003 2 ACL_POINTER : REF $BLOCK, : Pointer to current ACL segment
1022 2004 2 ACL_SPLIT : REF $BLOCK, : Offset to current ACE
1023 2005 2 ACE_POINTER : REF $BLOCK, : Pointer to current ACE
1024 2006 2 ACE_NUMBER; : Index of ACE in ACL
1025 2007 2
1026 2008 2

```

ACL\_READACL - read one or more ACEs

```

: 1027 2009 2 ! Initialize the buffer parameters.
: 1028 2010 2
: 1029 2011 2 COUNT = .LENGTH;
: 1030 2012 2 ACE = .ACE_BUFFER;
: 1031 2013 2
: 1032 2014 2 ! Sanity check the length of the supplied ACE.
: 1033 2015 2
: 1034 2016 2 IF .COUNT LSSU 4
: 1035 2017 2 THEN RETURN SSS_BADPARAM;
: 1036 2018 2
: 1037 2019 2 ! If the ACL is empty, return an error.
: 1038 2020 2
: 1039 2021 2 IF .ACL_QUEUE_HEAD[ACL$$_FLINK] EQLA ACL_QUEUE_HEAD[ACL$$_FLINK]
: 1040 2022 2 THEN
: 1041 2023 2 BEGIN
: 1042 2024 2 .ACL_CONTEXT = 0;
: 1043 2025 2 ACL_ERROR (SS$_ACLEMPY);
: 1044 2026 2 END;
: 1045 2027 2
: 1046 2028 2 ! Start reading ACE's from next available. If the ACL context is zero,
: 1047 2029 2 ! start reading ACE's from the beginning of the ACL. In either case only
: 1048 2030 2 ! fill the user's buffer with as many whole ACE's as will fit. Then save
: 1049 2031 2 ! the context for the next time through. An error is given when an attempt
: 1050 2032 2 ! is made to read beyond the end of the ACL.
: 1051 2033 2
: 1052 2034 2 ACE_NUMBER = ACL_LOCATEACE (.ACL_QUEUE_HEAD, .ACL_CONTEXT[CONTEXT_INDEX] + 1, ACL_POINTER, ACL_SPLIT);
: 1053 2035 2 ACE_POINTER = ACE_POINTER[ACL$$_LIST] + .ACL_SPLIT;
: 1054 2036 2
: 1055 2037 2 WHILE 1
: 1056 2038 2 DO
: 1057 2039 2 BEGIN
: 1058 2040 2 IF .ACE_POINTER GEQA .ACL_POINTER + .ACL_POINTER[ACL$$_SIZE]
: 1059 2041 2 THEN
: 1060 2042 2 BEGIN
: 1061 2043 2 ACL_POINTER = .ACL_POINTER[ACL$$_FLINK];
: 1062 2044 2 ACE_POINTER = ACE_POINTER[ACL$$_LIST];
: 1063 2045 2 END;
: 1064 2046 2 IF ACL_POINTER[ACL$$_FLINK] EQLA ACL_QUEUE_HEAD[ACL$$_FLINK]
: 1065 2047 2 THEN EXITLOOP;
: 1066 2048 2
: 1067 2049 2 IF .ACE_POINTER[ACESB_SIZE] GTRU .COUNT
: 1068 2050 2 THEN
: 1069 2051 2 BEGIN
: 1070 2052 2 .ACL_CONTEXT = .ACE_NUMBER - 1;
: 1071 2053 2 IF .ACE EQLA .ACE_BUFFER THEN ACL_ERROR (SS$_BUFFEROVF);
: 1072 2054 2 CH$FILL (0, .COUNT, .ACE);
: 1073 2055 2 RETURN 1;
: 1074 2056 2 END;
: 1075 2057 2 CH$MOVE (.ACE_POINTER[ACESB_SIZE], .ACE_POINTER, .ACE);
: 1076 2058 2 ACE = .ACE + .ACE_POINTER[ACESB_SIZE];
: 1077 2059 2 COUNT = .COUNT - .ACE_POINTER[ACESB_SIZE];
: 1078 2060 2
: 1079 2061 2 ACE_POINTER = .ACE_POINTER + .ACE_POINTER[ACESB_SIZE];
: 1080 2062 2 ACE_NUMBER = .ACE_NUMBER + 1;
: 1081 2063 2 END;
: 1082 2064 2
: 1083 2065 2 ! At this point the end of the ACL has been reached. Return the ACE's

```





ACL\_ACLLENGTH - determine the size of the ACL

```

1097 2078 1 %SBTTL 'ACL_ACLLENGTH - determine the size of the ACL'
1098 2079 1 GLOBAL ROUTINE ACL_ACLLENGTH (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, LENGTH) =
1099 2080 1
1100 2081 1 !++
1101 2082 1
1102 2083 1 FUNCTIONAL DESCRIPTION:
1103 2084 1
1104 2085 1     This routine returns the length of the Access Control List for the
1105 2086 1     specified file.
1106 2087 1
1107 2088 1 CALLING SEQUENCE:
1108 2089 1     ACL_ACLLENGTH (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, LENGTH)
1109 2090 1
1110 2091 1 INPUT PARAMETERS:
1111 2092 1     ACL_QUEUE_HEAD: address of queue header for ACL
1112 2093 1     ACL_CONTEXT: address of ACL context longword
1113 2094 1     COUNT: size of the user Access Control Entry
1114 2095 1     ACE: address of the user Access Control Entry
1115 2096 1
1116 2097 1 IMPLICIT INPUTS:
1117 2098 1     NONE
1118 2099 1
1119 2100 1 OUTPUT PARAMETERS:
1120 2101 1     NONE
1121 2102 1
1122 2103 1 IMPLICIT OUTPUTS:
1123 2104 1     NONE
1124 2105 1
1125 2106 1 ROUTINE VALUE:
1126 2107 1     1
1127 2108 1
1128 2109 1 SIDE EFFECTS:
1129 2110 1     The length of the ACL is returned. In addition, the ACL context
1130 2111 1     is cleared.
1131 2112 1
1132 2113 1 --
1133 2114 1
1134 2115 2 BEGIN
1135 2116 2
1136 2117 2 MAP
1137 2118 2     ACL_QUEUE_HEAD : REF $BLOCK,      ! Queue header for ACL
1138 2119 2     ACL_CONTEXT    : REF $BLOCK;      ! Context longword
1139 2120 2
1140 2121 2 LOCAL
1141 2122 2     ACL_POINTER    : REF $BLOCK,      ! Pointer to the current segment
1142 2123 2     ACL_LENGTH;    ! Length of the ACL
1143 2124 2
1144 2125 2 ! Calculate the length of the ACL.
1145 2126 2
1146 2127 2 ACL_LENGTH = 0;
1147 2128 2
1148 2129 2 ACL_POINTER = .ACL_QUEUE_HEAD[ACL$FLINK];
1149 2130 2 UNTIL .ACL_POINTER=EQLA ACL_QUEUE_HEAD[ACL$FLINK]
1150 2131 2 DO
1151 2132 2     BEGIN
1152 2133 2     ACL_LENGTH = .ACL_LENGTH + .ACL_POINTER[ACL$W_SIZE] - ACL$C_LENGTH;
1153 2134 2     ACL_POINTER = .ACL_POINTER[ACL$FLINK];

```

```

: 1154      2135 2      END;
: 1155      2136 2
: 1156      2137 2      ! Return the length of the ACL.
: 1157      2138 2
: 1158      2139 2      CH$COPY (4, ACL_LENGTH, 0, .COUNT, .LENGTH ,
: 1159      2140 2      RETURN 1;
: 1160      2141 2
: 1161      2142 1      END;

```

. End of routine ACL\_ACLLENGTH

				003C 00000	.ENTRY	ACL_ACLLENGTH, Save R2,R3,R4,R5	:	2079
				7E D4 00002	CLRL	ACL_LENGTH	:	2127
	04	51	04	BC D0 00004	MOVL	@ACL_QUEUE_HEAD, ACL_POINTER	:	2129
		AC		51 D1 00008 1\$:	CPL	ACL_POINTER, ACL_QUEUE_HEAD	:	2130
				10 13 0000C	BEQL	2\$	:	
		50	08	A1 3C 0000E	MOVZWL	8(ACL_POINTER), R0	:	2133
		50		6E C0 00012	ADDL2	ACL_LENGTH, R0	:	
		6E	F4	A0 9E 00015	MOVAB	-12(R0), ACL_LENGTH	:	
		51		61 D0 00019	MOVL	(ACL_POINTER), ACL_POINTER	:	2134
				EA 11 0001C	BRB	1\$	:	2130
OC	AC		00	04 2C 0001E 2\$:	MOVCS	#4, ACL_LENGTH, #0, COUNT, @LENGTH	:	2139
		6E	10	BC 00024			:	
		50		01 D0 00026	MOVL	#1, R0	:	2140
				04 00029	RET		:	2142

; Routine Size: 42 bytes, Routine Base: \$CODE\$ + 0808

```

: 1163 2143 1 XSBTTL 'ACL READACE - read a single ACE'
: 1164 2144 1 GLOBAL ROUTINE ACL_READACE (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, ACE) =
: 1165 2145 1
: 1166 2146 1 !++
: 1167 2147 1
: 1168 2148 1 FUNCTIONAL DESCRIPTION:
: 1169 2149 1
: 1170 2150 1     This routine reads a single ACE at a time from the ACL.  If the
: 1171 2151 1     ACE will not fit, the error code SSS_BUFFEROVF is returned as an
: 1172 2152 1     ACE error.
: 1173 2153 1
: 1174 2154 1 CALLING SEQUENCE:
: 1175 2155 1     ACL_READACE (ACL_QUEUE_HEAD, ACL_CONTEXT, COUNT, ACE)
: 1176 2156 1
: 1177 2157 1 INPUT PARAMETERS:
: 1178 2158 1     ACL_QUEUE_HEAD: address of queue header for ACL
: 1179 2159 1     ACL_CONTEXT: address of ACL context longword
: 1180 2160 1     COUNT: size of the user Access Control Entry
: 1181 2161 1     ACE: address of the user Access Control Entry
: 1182 2162 1
: 1183 2163 1 IMPLICIT INPUTS:
: 1184 2164 1     NONE
: 1185 2165 1
: 1186 2166 1 OUTPUT PARAMETERS:
: 1187 2167 1     NONE
: 1188 2168 1
: 1189 2169 1 IMPLICIT OUTPUTS:
: 1190 2170 1     NONE
: 1191 2171 1
: 1192 2172 1 ROUTINE VALUE:
: 1193 2173 1     1 if successful
: 1194 2174 1     error code otherwise
: 1195 2175 1
: 1196 2176 1 SIDE EFFECTS:
: 1197 2177 1     The user's buffer is filled with the next ACE if it will fit.
: 1198 2178 1     Otherwise an error is indicated.
: 1199 2179 1
: 1200 2180 1 --
: 1201 2181 1
: 1202 2182 2 BEGIN
: 1203 2183 2
: 1204 2184 2 MAP
: 1205 2185 2     ACL_QUEUE_HEAD : REF $BLOCK,      ! Queue header for ACL
: 1206 2186 2     ACL_CONTEXT   : REF $BLOCK,      ! Context longword
: 1207 2187 2     ACE           : REF $BLOCK;      ! Address of user ACE buffer
: 1208 2188 2
: 1209 2189 2 LOCAL
: 1210 2190 2     ACL_POINTER   : REF $BLOCK,      ! Pointer to current ACL segment
: 1211 2191 2     ACL_SPLIT     : REF $BLOCK,      ! Offset to current ACE
: 1212 2192 2     ACE_POINTER   : REF $BLOCK,      ! Pointer to current ACE
: 1213 2193 2     ACE_NUMBER;   ! Index of ACE in ACL
: 1214 2194 2
: 1215 2195 2
: 1216 2196 2 ! Sanity check the length of the supplied ACE.
: 1217 2197 2
: 1218 2198 2 IF .COUNT LSSU 4
: 1219 2199 2 THEN RETURN SSS_BADPAHAM;

```

B  
C  
D  
E  
F  
G  
H  
I  
J  
K  
L  
M  
N  
O  
P  
Q  
R  
S  
T  
U  
V  
W  
X  
Y  
Z

ACL\_READACE - read a single ACE

```

: 1220 2200 2
: 1221 2201 2 ! Determine if the ACL is empty. If it is, set the context to zero, and
: 1222 2202 2 ! indicate a failure by clearing the returning ACE, and return success.
: 1223 2203 2
: 1224 2204 2 IF .ACL_QUEUE_HEAD[ACL$$_FLINK] EQLA ACL_QUEUE_HEAD[ACL$$_FLINK]
: 1225 2205 2 THEN
: 1226 2206 2 BEGIN
: 1227 2207 2 .ACL_CONTEXT = 0;
: 1228 2208 2 ACL_ERROR (SS$_ACLEEMPTY);
: 1229 2209 2 END;
: 1230 2210 2
: 1231 2211 2 ! Transfer the next available ACE to the user's buffer. If the user's
: 1232 2212 2 ! buffer is not large enough to contain the ACE, the context is unchanged,
: 1233 2213 2 ! and an error is indicated.
: 1234 2214 2
: 1235 2215 2 ACE_NUMBFR = ACL_LOCATEACE (.ACL_QUEUE_HEAD, .ACL_CONTEXT[CONTEXT_INDEX] + 1, ACL_POINTER, ACL_SPLIT);
: 1236 2216 2 IF .ACL_POINTER[ACL$$_FLINK] EQLA ACL_QUEUE_HEAD[ACL$$_FLINK]
: 1237 2217 2 AND .ACL_SPLIT EQL .ACL_POINTER[ACL$$_SIZE] - ACL$$_LENGTH
: 1238 2218 2 THEN ACL_ERROR (SS$_NOMOREACE);
: 1239 2219 2 ACE_POINTER = ACL_POINTER[ACL$$_LIST] + .ACL_SPLIT;
: 1240 2220 2
: 1241 2221 2 ! The next available ACE has been located. Make sure there is room for it.
: 1242 2222 2
: 1243 2223 2 IF .ACE_POINTER[ACE$$_SIZE] GTR .COUNT THEN ACL_ERROR (SS$_BUFFEROVF);
: 1244 2224 2
: 1245 2225 2 ! There is room. Move it to the user's buffer.
: 1246 2226 2
: 1247 2227 2 CH$COPY (.ACE_POINTER[ACE$$_SIZE], .ACE_POINTER, 0, .COUNT, .ACE);
: 1248 2228 2 .ACL_CONTEXT = .ACE_NUMBER;
: 1249 2229 2
: 1250 2230 2 RETURN 1;
: 1251 2231 2
: 1252 2232 1 END;

```

! End of routine ACL\_READACE

				00FC 0000	.ENTRY	ACL_READACE, Save R2,R3,R4,R5,R6,R7	: 2144
		5E	08	C2 00002	SUBL2	#8, SP	:
		04	0C	AC D1 00005	CMPL	COUNT, #4	: 2198
				04 1E 00009	BGEQU	1\$	:
		50		14 D0 0000B	MOVL	#20, R0	: 2199
				04 0000E	RET		:
		04	AC	04 BC D1 0000F 1\$:	CMPL	@ACL_QUEUE_HEAD, ACL_QUEUE_HEAD	: 2204
				1B 12 00014	BNEQ	2\$	:
				08 BC D4 00016	CLRL	@ACL_CONTEXT	: 2207
0C	AC	00		00 2C 00019	MOVCS	#0, (SP), #0, COUNT, @A =	: 2208
				10 BC 0001F			:
		50		10 AC D0 00021	MOVL	ACE, R0	:
		02	A0	09D0 8F B0 00025	MOVW	#2512, 2(R0)	:
				50 09D0 8F 3C 0002B	MOVZWL	#2512, R0	:
				04 00030	RET		:
				5E DD 00031 2\$:	PUSHL	SP	: 2215
				08 AE 9F 00033	PUSHAB	ACL_POINTER	:
7E	08	BC		00 EF 00036	EXTZV	#0, #24, @ACL_CONTEXT, -(SP)	:
				6E D6 0003C	INCL	(SP)	:



			04	AC	DD	0003E		PUSHL	ACL_QUEUE HEAD	:	
	0000V	CF		04	FB	00041		CALLS	#4, ACL_LOCATEACE	:	
		57		50	D0	00046		MOVL	RO, ACE_NUMBER	:	
		50	04	AE	D0	00049		MOVL	ACL_POINTER, RO	2216	
	04	AC		60	D1	0004D		CMPL	(RO), ACL_QUEUE_HEAD	:	
				24	12	00051		BNEQ	3\$	:	
		50	08	A0	3C	00053		MOVZWL	8(RO), RO	2217	
		50		0C	C2	00057		SUBL2	#12, RO	:	
		50		6E	D1	0005A		CMPL	ACL_SPLIT, RO	:	
				18	12	0005D		BNEQ	3\$	:	
OC	AC		00	6E	00	2C	0005F	MOVCS	#0, (SP), #0, COUNT, @ACE	2218	
					10	BC	00065			:	
		50	10	AC	D0	00067		MOVL	ACE, RO	:	
	02	A0	09E0	8F	B0	0006B		MOVW	#2528, 2(RO)	:	
		50	09E0	8F	3C	00071		MOVZWL	#2528, RO	:	
					04	00076		RET		:	
		56	04	AE	6E	C1	00077	3\$:	ADDL3	ACL_SPLIT, ACL_POINTER, R6	2219
				56	0C	C0	0007C		ADDL2	#12, ACE_POINTER	:
OC	AC		66	08	00	ED	0007F		CMPZV	#0, #8, (ACE_POINTER), COUNT	2223
					18	15	00085		BLEQ	4\$	:
OC	AC		00	6E	00	2C	00087		MOVCS	#0, (SP), #0, COUNT, @ACE	:
					10	BC	0008D			:	
		50	10	AC	D0	0008F		MOVL	ACE, RO	:	
	02	A0	0601	8F	B0	00093		MOVW	#1537, 2(RO)	:	
		50	0601	8F	3C	00099		MOVZWL	#1537, RO	:	
					04	0009E		RET		:	
		50		66	9A	0009F	4\$:	MOVZBL	(ACE_POINTER), RO	2227	
OC	AC		00	66	50	2C	000A2		MOVCS	RO, (ACE_POINTER), #0, COUNT, @ACE	:
					10	BC	000A8			:	
	08	BC		57	D0	000AA		MOVL	ACE_NUMBER, @ACL_CONTEXT	2228	
		50		01	D0	000AE		MOVL	#1, RO	2230	
					04	000B1		RET		2232	

; Routine Size: 178 bytes, Routine Base: \$CODE\$ + 0832

```

: 1254 2233 1 %SBTT_ 'ACL_LOCATEACE - locate ACE by context value'
: 1255 2234 1 GLOBAL ROUTINE ACL_LOCATEACE (ACL_QUEUE_HEAD, ACE_INDEX, ACL_POINTER, ACL_SPLIT) =
: 1256 2235 1
: 1257 2236 1 !++
: 1258 2237 1
: 1259 2238 1 FUNCTIONAL DESCRIPTION:
: 1260 2239 1
: 1261 2240 1     This routine is used to position to a particular Access Control Entry.
: 1262 2241 1     This is done by the context specified. A context of zero results in
: 1263 2242 1     positioning to the start of the ACL; a number larger than the ACL
: 1264 2243 1     size results in positioning to the end.
: 1265 2244 1
: 1266 2245 1 CALLING SEQUENCE:
: 1267 2246 1     ACL_LOCATEACE (ACL_QUEUE_HEAD, ACE_INDEX, ACL_POINTER, ACL_SPLIT)
: 1268 2247 1
: 1269 2248 1 INPUT PARAMETERS:
: 1270 2249 1     ACL_QUEUE_HEAD: address of queue header for ACL
: 1271 2250 1     ACE_INDEX: index number of ACE to locate
: 1272 2251 1
: 1273 2252 1 IMPLICIT INPUTS:
: 1274 2253 1     NONE
: 1275 2254 1
: 1276 2255 1 OUTPUT PARAMETERS:
: 1277 2256 1     ACL_POINTER: address to store pointer to the selected ACL segment
: 1278 2257 1     ACL_SPLIT: address to store the offset to the selected ACE
: 1279 2258 1
: 1280 2259 1 IMPLICIT OUTPUTS:
: 1281 2260 1     NONE
: 1282 2261 1
: 1283 2262 1 ROUTINE VALUE:
: 1284 2263 1     0 if the context is invalid (points off the end of the ACL)
: 1285 2264 1     the numeric position of the ACE
: 1286 2265 1
: 1287 2266 1 SIDE EFFECTS:
: 1288 2267 1     NONE
: 1289 2268 1
: 1290 2269 1 --
: 1291 2270 1
: 1292 2271 2 BEGIN
: 1293 2272 2
: 1294 2273 2 MAP
: 1295 2274 2     ACL_QUEUE_HEAD : REF $BBLOCK,           ! Queue header for ACL
: 1296 2275 2     ACL_POINTER   : REF $BBLOCK;           ! Address of the current segment
: 1297 2276 2
: 1298 2277 2 LOCAL
: 1299 2278 2     ACL_SEGMENT   : REF $BBLOCK,           ! Address of the current segment
: 1300 2279 2     ACE_POINTER   : REF $BBLOCK,           ! Pointer to ACE within segment
: 1301 2280 2     ACE_NUMBER;   ! Position of ACE
: 1302 2281 2
: 1303 2282 2 ! Locate the ACE by context.  If an append is being done, locate to the
: 1304 2283 2 ! end of the ACL chain.
: 1305 2284 2
: 1306 2285 2 ACE_NUMBER = 0;
: 1307 2286 2 ACL_SEGMENT = ACL_QUEUE_HEAD[ACL$FLINK];
: 1308 2287 2 UNTIL .ACL_SEGMENT[ACL$FLINK] EQA ACL_QUEUE_HEAD[ACL$FLINK]
: 1309 2288 2 DO
: 1310 2289 2 BEGIN

```

```

: 1311      2290      3      ACL_SEGMENT = .ACL_SEGMENT[ACL$L_FLINK];
: 1312      2291      3      ACE_POINTER = ACL_SEGMENT[ACL$L_LIST];
: 1313      2292      3      UNTIL .ACE_POINTER GEQA .ACL_SEGMENT + .ACL_SEGMENT[ACL$W_SIZE]
: 1314      2293      3      DO
: 1315      2294      4          BEGIN
: 1316      2295      4              ACE_NUMBER = .ACE_NUMBER + 1;
: 1317      2296      4              IF .ACE_INDEX LEQO .ACE_NUMBER
: 1318      2297      4                  THEN
: 1319      2298      5                      BEGIN
: 1320      2299      5                          .ACL_SPLIT = .ACE_POINTER - ACL_SEGMENT[ACL$L_LIST];
: 1321      2300      5                          .ACL_POINTER = .ACL_SEGMENT;
: 1322      2301      5                          RETURN .ACE_NUMBER;
: 1323      2302      5                      END;
: 1324      2303      4              ACE_POINTER = .ACE_POINTER + .ACE_POINTER[ACE$B_SIZE];
: 1325      2304      3          END;
: 1326      2305      2      END;
: 1327      2306      2
: 1328      2307      2      ! The ACE pointed to by the ACL context field does not exist. Set up to
: 1329      2308      2      ! append the ACE to the end of the ACL.
: 1330      2309      2
: 1331      2310      2      .ACL_SPLIT = .ACL_SEGMENT[ACL$W_SIZE] - ACL$C_LENGTH;
: 1332      2311      2      .ACL_POINTER = .ACL_SEGMENT;
: 1333      2312      2      RETURN .ACE_NUMBER + 1;
: 1334      2313      2
: 1335      2314      1      END;

```

! End of routine ACL\_LOCATEACE

				000C 0000	.ENTRY	ACL_LOCATEACE, Save R2,R3	:	2234	
			51	D4 00002	CLRL	ACE_NUMBER	:	2285	
	04	50	04	AC D0 00004	MOVL	ACL_QUEUE_HEAD, ACL_SEGMENT	:	2286	
				60 D1 00008	1\$:	CML	(ACL_SEGMENT), ACL_QUEUE_HEAD	:	2287
				32 13 0000C	BEQL	4\$	:		
		50		60 D0 0000E	MOVL	(ACL_SEGMENT), ACL_SEGMENT	:	2290	
		52	0C	A0 9E 00011	MOVAB	12(R0), ACE_POINTER	:	2291	
		53	08	A0 3C 00015	2\$:	MOVZWL	8(ACL_SEGMENT), R3	:	2292
		53		50 C0 00019	ADDL2	ACL_SEGMENT, R3	:		
		53		52 D1 0001C	CML	ACE_POINTER, R3	:		
				E7 1E 0001F	BGEQU	1\$	:		
		51	08	51 D6 00021	INCL	ACE_NUMBER	:	2295	
		51		AC D1 00023	CML	ACE_INDEX, ACE_NUMBER	:	2296	
				0F 1A 00027	BGTRU	3\$	:		
	53	52		50 C3 00029	SUBL3	ACL_SEGMENT, ACE_POINTER, R3	:	2299	
		10	F4	A3 9E 0002D	MOVAB	-12(R3), @ACL_SPLIT	:		
		0C		50 D0 00032	MOVL	ACL_SEGMENT, @ACL_POINTER	:	2300	
				17 11 00036	BRB	5\$	:	2301	
		53		62 9A 00038	3\$:	MOVZBL	(ACE_POINTER), R3	:	2303
		52		53 C0 0003B	ADDL2	R3, ACE_POINTER	:		
				D5 11 0003E	BRB	2\$	:	2292	
	10	BC	08	A0 3C 00040	4\$:	MOVZWL	8(ACL_SEGMENT), @ACL_SPLIT	:	2310
	10	BC		0C C2 00045	SUBL2	#12, @ACL_SPLIT	:		
	0C	BC		50 D0 00049	MOVL	ACL_SEGMENT, @ACL_POINTER	:	2311	
				51 D6 0004D	INCL	R1	:	2312	
		50		51 D0 0004F	5\$:	MOVL	R1, R0	:	
				04 00052	RET		:	2314	

ACLSUBR  
V04-000

ACL\_LOCATEACE - locate ACE by context value

F 16  
15-Sep-1984 23:51:08  
14-Sep-1984 12:30:07

VAX-11 Bliss-32 V4.0-742  
DISK\$VM\$MASTER:[F11X.SRC]ACLSUBR.B32;1 (12) Page 42

: Routine Size: 83 bytes, Routine Base: \$CODE\$ + 0BE4

: 1336 2315 1  
: 1337 2316 1 END  
: 1338 2317 0 ELUDOM

PSECT SUMMARY

Name	Bytes	Attributes
\$CODE\$	2359	NOVEC, NOWRT, RD, EXE, NOSHR, LCL, REL, CON, NOPIC, ALIGN(2)

Library Statistics

File	Total	Symbols Loaded	Percent	Pages Mapped	Processing Time
_\$255\$DUA28:[SYSLIB]LIB.L32;1	18619	52	0	1000	00:01.8

COMMAND QUALIFIERS

: BLISS/CHECK=(FIELD, INITIAL, OPTIMIZE)/LIS=LIS\$:ACLSUBR/OBJ=OBJ\$:ACLSUBR MSRC\$:ACLSUBR/UPDATE=(ENH\$:ACLSUBR)

: Size: 2359 code + 0 data bytes  
: Run Time: 00:43.6  
: Elapsed Time: 01:36.9  
: Lines/CPU Min: 3192  
: Lexemes/CPU-Min: 19767  
: Memory Used: 278 pages  
: Compilation Complete



