

Systems Reference Library

IBM System/360 Operating System Assembler [F] Programmer's Guide

Program Number 360S-AS-037

This publication complements the IBM System/360 Operating System Assembler Language publications. It provides a guide to program assembling, linkage editing, executing, interpreting listings, assembler programming considerations, diagnostic messages, and object output cards.

Information in this manual on IBM System/360 Model 195 should be used for planning purposes only.



PREFACE

This publication is oriented to the F level assembler program (the assembler) functioning in the IBM System/360 Operating System (Primary Control Program, MFT, and MVT).

This publication is divided into an introduction and four sections which describe the following:

1. Assembler options and data set requirements.
2. Use of IBM-provided cataloged procedures for assembling; assembling and linkage editing; assembling, linkage editing, and executing assembler language source programs.
3. Use and interpretation of the assembler listing.
4. Programming considerations.

In addition, the appendixes provide a procedure for dynamic invocation of the assembly, a list and explanation of object output cards, and a sample program listing.

Other System Reference Library publications in the IBM System/360 Operating System series provide fuller, more detailed discussions of the topics introduced in this publication: a careful reading of the publication IBM System/360 Operating System: Concepts and Facilities, Order No. GC28-6535, is recommended. Knowledge of the assembler language is assumed. Where appropriate, the reader is directed to the following publications:

IBM System/360 Operating System: Job Control Language Reference, Order No. GC28-6704

IBM System/360 Operating System: Storage Estimates, Order No. GC28-6551

IBM System/360 Operating System: Job Control Language User's Guide, Order No. GC28-6703

IBM System/360 Operating System: Linkage Editor and Loader, Order No. GC28-6538

IBM System/360 Operating System: Supervisor and Data Management Services, Order No. GC28-6646

IBM System/360 Operating System: Supervisor and Data Management Macro Instructions, Order No. GC28-6647

IBM System/360 Operating System: TESTRAN, Order No. GC28-6648

IBM System/360 Operating System: Messages and Codes, Order No. GC28-6631

IBM System/360 Operating System: Assembler Language, Order No. GC28-6514

IBM System/360 Operating System: Utilities, Order No. GC28-6586

IBM System/360 Operating System: FORTRAN IV (E), Library Subprograms, Order No. GC28-6596

IBM System/360 Operating System: System Programmer's Guide, Order No. GC28-6550

IBM System/360 Operating System: FORTRAN IV (E) Programmer's Guide, Order No. GC28-6603

IBM System/360 Operating System: COBOL (E) Programmer's Guide, Order No. GC24-5029

References to these publications are usually by a short title, e.g., Linkage Editor or Data Management Services.

Fifth Edition (July, 1969)

This edition corresponds to Release 18 of the IBM System/360 Operating System. It is a major revision of, and obsoletes, GC26-3756-3. The major changes are addition of System/360 Model 85 programming information and a cataloged procedure for the Loader. Other changes are a new PARM field option (OS/DOS), increase in maximum Set symbol dimension, cataloged procedure support for dedicated work files, and new assembler statistics. Also, there are several editorial changes. An extensively modified page is denoted by the symbol ● next to the page number.

Specifications contained herein are subject to change from time to time. Any such changes will be reported in subsequent revisions or Technical Newsletters.

Requests for copies of IBM publications should be made to your IBM representative or to the IBM Branch Office serving your locality.

A form is provided at the back of this publication for reader's comments. If the form has been removed, address comments to IBM Nordic Laboratory, Technical Communications, Box 962, S-181 09 Lidings 9, Sweden.

IBM Technical Newsletter

File Number S360-21

Re: Order No. GC26-3756-4

This Newsletter No. GN33-8075

Date June 1, 1970

Previous Newsletter Nos. None

IBM SYSTEM/360 OPERATING SYSTEM
ASSEMBLER (F) PROGRAMMER'S GUIDE

This Technical Newsletter, a part of release 19 of IBM System/360 Operating System, provides replacement pages for IBM System/360 Operating System Assembler (F) Programmer's Guide (Order No. GC26-3756-4). These replacement pages remain in effect for subsequent releases unless specifically altered. Pages to be inserted and/or removed are listed below.

Front Cover,ii
1-10
15,16
21-28
35,36
49,50

A change to the text or a small change to an illustration is indicated by a vertical line to the left of the change; a changed or added illustration is denoted by the symbol ● to the left of the caption.

Summary of Amendments

- Inclusion of information on Model 195 support.
- Data type designation for the L-type data constant in the TESTRAN card.
- Minor technical corrections and editorial changes.

File this cover letter at the back of the manual to provide a record of changes.

IBM Nordic Laboratory, Technical Communications, Box 962, Lidingsö 9, Sweden

CONTENTS

INTRODUCTION	1	Macro Definition Library Additions	16
ASSEMBLER OPTIONS AND DATA SET REQUIREMENTS	2	Load Module Modification - Entry Point Restatement	17
Assembler Options	2	Object Module Linkage	17
Default Entry	2	Dictionary Size and Source Statement Complexity	17
Assembler Data Set Requirements	2	Dictionaries Used in Conditional Assembly and Macro Instruction Expansion	18
Ddname SYSUT1, SYSUT2, SYSUT3	3	Global Dictionary at Collection Time	19
Ddname SYSIN	3	Local Dictionaries at Collection Time	19
Ddname SYSLIB	3	Global Dictionary at Generation Time	19
Ddname SYSPRINT	3	Local Dictionaries at Generation Time	20
Ddname SYSPUNCH	3	Additional Dictionary Requirements	20
Ddname SYSGO	3	Correction of Dictionary Overflow	20
Defining Data Set Characteristics	3	Symbol Table Overflow	21
Return Codes	5	Source Statement Complexity	21
CATALOGED PROCEDURES	6	Macro Generation and Conditional Assembly Limitation	21
Cataloged Procedure for Assembly (ASMFC)	6	Assembler Portion Limitations	21
Cataloged Procedure for Assembly and Linkage Editing (ASMFCLE)	7	Model 91 Programming Considerations	21
Cataloged Procedure for Assembly, Linkage-Editing, and Execution (ASMFCLEG)	8	Controlling Instruction Execution Sequence	22
Cataloged Procedure for Assembly and Loader Execution (ASMFCG)	9	Model 85 Programming Considerations	22
Overriding Statements in Cataloged Procedures	9	Extended-Precision Machine Instructions	22
EXEC Statements	9	OPSYN--Operation Code Equate Instruction	22
DD Statements	9	Support of Unaligned Data	23
Examples	9	Type L Data Constant	23
ASSEMBLER LISTING	11	APPENDIX A. DIAGNOSTIC MESSAGES	25
External Symbol Dictionary (ESD)	11	APPENDIX B. OBJECT DECK OUTPUT	35
Source and Object Program	13	APPENDIX C. ASSEMBLER F PROGRAM LISTING	38
Relocation Dictionary	14	APPENDIX D. DYNAMIC INVOCATION OF THE ASSEMBLER	47
Cross Reference	14	INDEX	49
Diagnostics	15		
PROGRAMMING CONSIDERATIONS	16		
Saving and Restoring General Register Contents	16		
Program Termination	16		
PARM Field Access	16		

ILLUSTRATIONS

Figures

1. Cataloged Procedures for Assembly (ASMFC)	6	4. Cataloged Procedure for Assembly and Loader Execution (ASMFCG)	10
2. Cataloged Procedure for Assembling and Linkage Editing (ASMFCLE)	7	5. Assembler Listing	12
3. Cataloged Procedure for Assembly, Linkage Editing, and Execution (ASMFCLEG)	8	6. Linkage Statements	18
		7. Extended-Precision Floating Point Format	23
		8. TESTRAN SYM Card Format	37

Tables

1. Data Set Characteristics	4	7. Global Dictionary Entries at Generation Time	20
2. Return Codes	5	8. Local Dictionary Entries at Generation Time	20
3. Device Naming Conventions	6	9. Macro Definition Local Dictionary Parameter Table	20
4. Types of ESD Entries	11	10. Extended-Precision and Rounding Instructions	22
5. Global Dictionary Entries at Collection Time	19		
6. Local Dictionary Entries at Collection Time	19		

INTRODUCTION

Through the medium of job control statements, the programmer specifies job requirements directly to the operating system, thus eliminating many of the functions previously performed by the operating personnel. The job consists of one or more job steps. For example, the job of assembling, linkage-editing, and executing a source program involves three job steps:

1. Translating the source program, i.e., executing the assembler component of the operating system to produce an object module.
2. Processing the output of the assembler, i.e., executing the linkage-editor component of the operating system to produce a load module.
3. Executing the assembled and linkage-edited program, i.e., executing the load module.

A procedure is a sequence of job control language statements specifying a job. Procedures may enter the system via the input stream or from a library of procedures,

which are previously defined and contained in a procedure library. The input stream is the flow of job control statements and, optionally, input data entering the system from one input device. At the sequential scheduling system level of the operating system, only one input stream may exist at a time. (For a description of the operating system environment see IBM System/360 Operating System: Concepts and Facilities.)

The job definition (JOB), execute (EXEC), data definition (DD), and delimiter (/*) job control statements are shown in this publication as they are used to specify assembler processing. Detailed explanations of these statements are given in IBM System/360 Operating System: Job Control Language Reference.

Operating system factors influencing program preparation, such as terminating the program, saving and restoring general registers, and linking of independently produced object modules, are discussed in Programming Considerations, as are guides to determine whether assembler dictionary sizes and complexity limitations of source statements will be exceeded.

ASSEMBLER OPTIONS AND DATA SET REQUIREMENTS

ASSEMBLER OPTIONS

The programmer may specify the following assembler options in the PARM= field of the EXEC statement. They must appear between two apostrophes, separated by commas with no imbedded blanks. They can appear in any order and, if an entry is omitted, a standard setting will be assumed as shown below under "Default Entry."

```

    DECK  LOAD, LIST  TEST,  XREF,           ALGN OS  RENT'
    PARM= or  or  or  or  or  or  LINECNT=nn, or  or  or
    'NODECK,NOLOAD,NOLIST,NOTEST,NOXREF,    NOALGN,DOS,NORENT'
    
```

These options are defined as follows:

DECK -- The object module is placed on the device specified in the SYSPUNCH DD statement.

LOAD -- The object module is placed on the device specified in the SYSGO DD statement.

NOTE: Specification of the parameter **LOAD** causes object output to be written on a data set with ddname SYSGO. This action occurs independently of the output on SYSPUNCH caused by the parameter **DECK**. The output on SYSGO and SYSPUNCH is identical except that SYSPUNCH is closed with a disposition of **LEAVE**, and SYSGO is closed with a disposition of **REREAD**.

LIST -- An assembler listing is produced.

TEST -- The object module contains the special source symbol table required by the test translator (**TESTTRAN**) routine.

XREF -- The assembler produces a cross-reference table of symbols as part of the listing.

RENT -- The assembler checks for a possible coding violation of program re-entrability.

The prefix **NO** is used with the above options to indicate which options are not wanted.

LINECNT=nn This parameter specifies the number of lines to be printed between headings in the listing. The permissible range is 01 to 99 lines.

NOALGN -- The assembler suppresses the diagnostic message **IEU033 ALIGNMENT ERROR** if fixed point, floating point, or logical data referenced by an instruction operand is not aligned on the proper boundary. The message will be produced, however, for references to instructions (e.g., by a branch) which are not aligned on the proper (halfword) boundary. See the "Model 85 Programming

Considerations" section for information on alignment requirements.

ALGN -- The assembler does not suppress the alignment error diagnostic message.

OS -- The assembler will have complete Operating System Assembler F capability.

DOS -- The assembler will behave like Disk Operating System (DOS) Assembler F. **CXD**, **DXD**, and **OPSYN** assembler operations and Extended Precision (Model 85 and 195 only) machine operations will be treated as undefined. L-type and Q-type DC and DS statements will be treated as unknown types and RLDs will appear in the Relocation Dictionary in order of their occurrence (unsorted). The **DOS** option is incompatible with the **LOAD**, **TEST**, **RENT**, or **NOALGN** options. If any of these options are specified along with **DOS**, the assembler generates a diagnostic message (**IEU078**) and uses the default options **NOLOAD**, **NOTEST**, **NORENT**, or **ALGN**.

If contradictory options are entered, e.g., **LIST**, **NOLIST**, the rightmost option, **NOLIST**, is used.

The following is an example of specifying assembler options:

```
EXEC PGM=IEUASM,PARM='LOAD,NODECK,TEST'
```

DEFAULT ENTRY

If no options are specified, the assembler assumes the following default entry.

```
PARM='NOLOAD,DECK,LIST,NOTEST,XREF,LINECNT=55,ALGN,OS,NORENT'
```

The cataloged procedures discussed in this guide assume the default entry. However, the programmer may override any or all of the default options (see "Overriding Statements in Cataloged Procedures").

ASSEMBLER DATA SET REQUIREMENTS

The assembler requires the following four data sets:

- **SYSUT1**, **SYSUT2**, **SYSUT3** -- utility data sets used as intermediate external storage.
- **SYSIN** -- an input data set containing the source statements to be processed.

In addition to the above, four additional data sets may be required:

- SYSLIB -- a data set containing macro definitions (for macro definitions not defined in the source program) and/or source coding to be called for through COPY assembler instructions.
- SYSPRINT -- a data set containing output text for printing (unless NOLIST option is specified).
- SYSPUNCH -- a data set containing object module output usually for punching (unless NODECK option is specified).
- SYSGO -- a data set containing object module output usually for the linkage editor (only if LOAD option is specified).

The above data sets are described in the following text. The ddname that must be used in the DD statement describing the data set appears as the heading for each description.

Ddnames SYSUT1, SYSUT2, SYSUT3

These utility data sets are used by the assembler as intermediate external storage devices when processing the source program. The input/output device(s) assigned to these data sets must be capable of sequential access to records. The assembler does not support multi-volume utility data sets. Refer to the Storage Estimate manual for the space required.

Ddname SYSIN

This data set contains the input to the assembler -- the source statements to be processed. The input/output device assigned to this data set may be either the device transmitting the input stream, or another sequential input device designated by the programmer. The DD statement describing this data set appears in the input stream. The IBM-supplied procedures do not contain this statement.

Ddname SYSLIB

From this data set, the assembler obtains macro definitions and assembler language statements to be called by the COPY assembler instruction. It is a partitioned data set and each macro definition or sequence of assembler statements is a separate member, with the member name being the macro instruction mnemonic or COPY code name. The data set may be defined as SYS1.MACLIB or a user's private macro definition or COPY library. SYS1.MACLIB contains macro definitions for the system macro instructions provided by IBM. A user's private library may be concatenated with SYS1.MACLIB. The two libraries must

have the same attributes, i.e., the same blocking factors, block sizes, and record formats. The Job Control Language publication explains the concatenation of data sets.

Ddname SYSPRINT

This data set is used by the assembler to produce a listing. Output may be directed to a printer, magnetic tape, or DASD. The assembler uses the machine code carriage-control characters for this data set.

Ddname SYSPUNCH

The assembler uses this data set to produce the object module. The input/output unit assigned to this data set may be either a card punch or an intermediate storage device (capable of sequential access).

Ddname SYSGO

This is a DASD, magnetic tape, or card punch data set used by the assembler. It contains the same output text as SYSPUNCH. It is used as input for the linkage editor and may also be used as a punch device (see NOTE under "Assembler Options").

DEFINING DATA SET CHARACTERISTICS

Before a data set can be made available to a problem program, descriptive information defining the data set must be placed into a data control block for the access routines. Sources of information for the data control block are keyword operands in the DCB macro instruction or, in some cases, the DD statement, data set label, or user's problem program. General information concerning data set definition is contained in the Data Management Services manual (see Preface). Characteristics of data sets supplied by the DCB macro instruction are described in the Data Management Macro Instructions manual (see Preface).

The specific information that must be supplied depends upon the data set organization and access method. The following access methods are used to process the assembler data sets:

<u>Access Method</u>	<u>Data Sets</u>
QSAM (Queued Sequential)	SYSPRINT, SYSPUNCH, SYSGO, SYSIN
BSAM (Basic Sequential)	SYSUT1, SYSUT2, SYSUT3
BPAM (Basic Partitioned)	SYSLIB

Table 1 summarizes the assembler capabilities and restrictions on record length

• Table 1. Data Set Characteristics

	SYSIN	SYSLIB	SYSPRINT	SYSPUNCH	SYSGO	SYSUT1 SYSUT2 SYSUT3
LRECL	Fixed at 80	Fixed at 80	Fixed at 121	Fixed at 80	Fixed at 80	N/A
RECFM ①	User must specify in LABEL or DD card F, FS, FBS, FB, FBST, FBT, FT, FST	User must specify in LABEL or DD card F, FB, FBT, FT	F and M set by assembler, user may specify B and/or T in label or DD card FM, FMB, FMT, FMBT	F set by assembler, user may specify B and/or T in label or DD card F, FB, FT, FBT	F set by assembler, user may specify B and/or T in label or DD card F, FB, FT, FBT	Fixed for U
BLKSIZE ②	User must specify in LABEL or DD card, must be a multiple of LRECL	User must specify in LABEL or DD card, must be a multiple of LRECL	Optional, but must be a multiple of LRECL; If omitted BLKSIZE=LRECL	Optional, but must be a multiple of LRECL; if omitted BLKSIZE=LRECL	Optional, but must be a multiple of LRECL; if omitted BLKSIZE=LRECL	User can not specify; maximum of 3624 minimum of 1739
BUFNO	Optional; if omitted 2 is used	Set by assembler to 1	Optional; if omitted 2 is used	Optional; if omitted 3 is used for unit record and 1 for other devices	Optional; if omitted 3 is used for unit record and 1 for other devices	User can not specify; either 1 or 2
For 44K availability	BLKSIZE times BUFNO can not be greater than 3600	BLKSIZE can not be greater than 3600 ④	BLKSIZE times BUFNO can not be greater than 1210	BLKSIZE times BUFNO can not be greater than 400	BLKSIZE times BUFNO can not be greater than 400	
For calculating core requirements	L1 = BLKSIZE times BUFNO	L2 = BLKSIZE	L3 = BLKSIZE times BUFNO	L4 = BLKSIZE times BUFNO	L5 = BLKSIZE times BUFNO	
③ Minimum core required for the assembler is the largest of the following: (1) 45056 (2) $L_1 + L_2 + 41000$ (3) $L_3 + L_4 + L_5 + 41000$						
③ Maximum core that the assembler can effectively use = $L_4 + L_5 + 535,000$						

① U = undefined, F = fixed length records, B = blocked records, S = standard blocks, T = track overflow, M = machine code carriage control

② Blocking is not allowed on unit record devices. Blocking on other direct access can not be greater than the track size unless T is specified on RECFM

③ For MVT environment add 5,000 for core required

④ A smaller blocksize may have to be specified for SYSLIB if global or local dictionaries overflow. See item 4 under "Correction of Dictionary Overflow."

and format, as well as the blocksize buffering facilities available to the user. The values shown in Table 1 are based upon the minimum core requirements of Assembler F (44K), which will allow a symbol table length of approximately 7000 bytes. If more than 44K is available, the block sizes and buffer numbers can be increased. However, if the user specifies a combination of blocking and buffering which does not leave room for the symbol table, abnormal termination of the task may occur (ABEND 804) when the assembler attempts to issue a GETMAIN macro instruction.

In addition to the data set characteristics shown in Table 1, the following options are available to the user (refer to the Supervisor and Data Management Macro Instructions publication). Options not shown below are fixed by the assembler and cannot be specified.

<u>Data Sets</u>	<u>Options</u>
SYSIN, SYSPUNCH, SYSPRINT, SYSGO	{ DEVD (device type) BFALN (buffer boundary alignment) BUFL (buffer length) EROPT (error option)
SYSUT1, 2, 3	{ DEVD (device type) OPTCD (optional service for validity checking and chained scheduling)

RETURN CODES

Table 2 shows the return codes issued by the assembler for use with the COND=parameter of JOB or EXEC statements. The COND= parameter is explained in IBM System/360 Operating System Job Control Language Reference (GC28-6704).

The return code issued by the assembler is the highest severity code that is:

1. Associated with any error detected by the assembler (see Appendix A for diagnostic messages and severity codes).
2. Associated with MNOTE messages produced by macro instructions.
3. Associated with an unrecoverable I/O error occurring during the assembly.

If a permanent I/O error occurs on any of the assembler files or a DD card for a required data set is missing, a message is printed on SYSPRINT (or on the operator's console if the SYSPRINT DD card is missing or if the I/O error is on SYSPRINT) and a return with a user return code of 20 is given by the assembler. This terminates the assembly.

Table 2. Return Codes

Return Code	Explanation
0	No errors detected
4	Minor errors detected; successful program execution is probable
8	Errors detected; unsuccessful program execution is possible
12	Serious errors detected; unsuccessful program execution is probable
16	Critical errors detected; normal execution is impossible
20	Unrecoverable I/O error occurred during assembly or missing data sets; assembly terminated

CATALOGED PROCEDURES

This section describes four IBM-provided cataloged procedures: a procedure for assembling (ASMFC), a procedure for assembling and linkage editing (ASMFCL), and a procedure for assembling, linkage editing, and executing (ASMFCLG), and a procedure for assembling and loader-executing (ASMFCG). The procedures rely on conventions regarding the naming of device classes. These conventions, shown in Table 3, must be incorporated into the system at system generation time.

Table 3. Device Naming Conventions

Device Classname	Devices Assigned
SYSSQ	Any devices allowing sequential access to records for reading and writing
SYSDA	Direct-access devices
SYSCP	Card punches

To use cataloged procedures, EXEC statements naming the desired procedures are placed in the input stream following the JOB statement. Subsequently, the specified cataloged procedure is brought from a procedure library and merged into the input stream.

The System Programmer's Guide discusses the placing of procedures in the procedure library.

CATALOGED PROCEDURE FOR ASSEMBLY (ASMFC)

This procedure requests the operating system to load and execute the assembler. The name ASMFC must be used to call this procedure. The result of execution is an object module, in punched card form, and an assembler listing.

In the following example, input enters via the input stream. The statements entered in the input stream to use this procedure are:

```

//jobname      JOB
//stepname     EXEC PROC= ASMFC
//ASM.SYSIN   DD  *
              |
              | source program statements
              |
/* (delimiter statement)
    
```

The statements of the ASMFC procedure are brought from the procedure library and merged into the input stream.

Figure 1 shows the statements that make up the ASMFC procedure.

```

1 //ASM      EXEC  PGM=IEUASM,REGION=50K
2 //SYSLIB   DD    DSN=SYS1.MACLIB,DISP=SHR
3 //SYSUT1   DD    DSN=&SYSUT1,UNIT=SYSSQ,SPACE=(1700,(400,50)),      X
//          //    SEP=(SYSLIB)
4 //SYSUT2   DD    DSN=&SYSUT2,UNIT=SYSSQ,SPACE=(1700,(400,50))
5 //SYSUT3   DD    DSN=SYSUT3,SPACE=(1700,(400,50)),                X
//          //    UNIT=(SYSSQ,SEP=(SYSUT2,SYSUT1,SYSLIB))
6 //SYSPRINT DD    SYSOUT=A
7 //SYSPUNCH DD    SYSOUT=B
-----
-----
1 PARM= or COND=parameters may be added to this statement by the EXEC statement that calls the procedure (see Overriding Statements in Cataloged Procedures). The system name IEUASM identifies Assembler F.
2 This statement identifies the macro library data set. The data set name SYS1.MACLIB is an IBM designation.
3 4 5 These statements specify the assembler utility data sets. The device classname used here, SYSSQ, may represent a collection of tape drives, or direct-access units, or both. The I/O units assigned to this name are specified by the installation when the system is generated. A unit name, e.g., 2311 may be substituted for SYSSQ. The DSN= parameters guarantee use of Dedicated Workfiles if this feature is part of the Scheduler.
The SEP=subparameter in statement 5 and the SPACE=parameter in statements 3, 4, and 5 are effective only if the device assigned is a direct-access device; otherwise they are ignored. The space required is dependent on the make-up of the source program. The Job Control Language publication explains space allocation.
6 This statement defines the standard system output class, SYSOUT=A, as the destination for the assembler listing.
7 This statement describes the data set that will contain the object module produced by the assembler.
    
```

Figure 1. Cataloged Procedure for Assembly (ASMFC)


CATALOGED PROCEDURE FOR ASSEMBLY,
 LINKAGE EDITING, AND EXECUTION
 (ASMFCLG)

This procedure consists of three job steps: assembling, linkage editing, and executing.

Figure 3 shows the statements that make up the ASMFCLG procedure. Only those statements not previously discussed are explained in the figure.

The name ASMFCLG must be used to call this procedure. Assembler and linkage editor listings are produced.

The statements entered in the input stream to use this procedure are:



	//ASM	EXEC	PGM=IEUASM,PARM=LOAD,REGION=50K	
	//SYSLIB	DD	DSNAME=SYS1.MACLIB,DISP=SHR	
	//SYSUT1	DD	DSNAME=&SYSUT1,UNIT=SYSSQ,SPACE=(1700,(400,50)),	X
	//		SEP=(SYSLIB)	
	//SYSUT2	DD	DSNAME=&SYSUT2,UNIT=SYSSQ,SPACE=(1700,(400,50))	
	//SYSUT3	DD	DSNAME=&SYSUT3,SPACE=(1700,(400,50)),	X
	//		UNIT=(SYSSQ,SEP=(SYSUT2,SYSUT1,SYSLIB))	
	//SYSPRINT	DD	SYSOUT=A	
	//SYSPUNCH	DD	SYSOUT=B	
	//SYSGO	DD	DSNAME=&LOADSET,UNIT=SYSSQ,SPACE=(80,(200,50)),	X
	//		DISP=(MOD,PASS)	
1	//LKED	EXEC	PGM=IEWL,PARM=(XREF,LET,LIST,NCAL),REGION=96K,	X
	//		COND=(8,LT,ASM)	
	//SYSLIN	DD	DSNAME=&LOADSET,DISP=(OLD,DELETE)	
	//	DD	DDNAME=SYSIN	
2	//SYSLMOD	DD	DSNAME=&GOSET(GO),UNIT=SYSDA,SPACE=(1024,(50,20,1)),	X
	//		DISP=(MOD,PASS)	
	//SYSUT1	DD	DSNAME=&SYSUT1,UNIT=(SYSDA,SEP=(SYSLIN,SYSLMOD)),	x
	//		SPACE=(1024,(50,20))	
	//SYSPRINT	DD	SYSOUT=A	
3	//GO	EXEC	PGM=*.LKED.SYSLMOD,COND=((8,LT,ASM),(4,LT,LKED))	

1	The LET linkage-editor option specified in this statement causes the linkage editor to mark the load module as executable even though errors were encountered during processing.			
2	The output of the linkage editor is specified as a member of a temporary data set, residing on a direct-access device, and is to be passed to a succeeding job step.			
3	This statement initiates execution of the assembled and linkage edited program. The notation *.LKED.SYSLMOD identifies the program to be executed as being in the data set described in job step LKED by the DD statement named SYSLMOD. When running with MVT (Option 4) the REGION parameter can be calculated with the help of the Storage Estimates publication (see preface).			

Figure 3. Cataloged Procedure for Assembly, Linkage Editing and Execution (ASMFCLG)

CATALOGED PROCEDURE FOR ASSEMBLY AND
LOADER-EXECUTION (ASMFCG)

This procedure consists of two job steps assembling and loader-executing. The result of loader-execution is a combination of link-editing and loading the program for execution. Load modules for program libraries are not produced.

Figure 4 shows the statements that make up the ASMFCG procedure. Only those statements not previously discussed are explained in the figure.

The name ASMFCG must be used to call this procedure. Assembler and loader listings are produced.

The statements entered in the input stream to use this procedure are:

```
//jobname      JOB
//stepname     EXEC      PROC=ASMFCG
//ASM.SYSIN    DD        *
```

source program

```
/*
//GO.ddname    DD        (parameters)
//GO.ddname    DD        (parameters)
//GO.ddname    DD        *
} only
} if
} necessary
```

problem program input

```
/*
```

OVERRIDING STATEMENTS IN CATALOGED
PROCEDURES

Any parameter in a cataloged procedure can be overridden except the PGM= parameter in the EXEC statement. Such overriding of statements or fields is effective only for the duration of the job step in which the statements appear. The statements, as stored in the procedure library of the system, remain unchanged.

Overriding for the purposes of re-specification, addition, or nullification is accomplished by including in the input stream statements containing the desired changes and identifying the statements to be overridden.

EXEC Statements

The PARM= and COND= parameters can be added or, if present, re-specified by including in the EXEC statement calling the procedure the notation PARM.stepname=, or COND.stepname=, followed by the desired parameters. "Stepname" identifies the EXEC statement within the procedure to which the modification applies. Overriding the PGM= parameter is not possible.

If the procedure consists of more than one job step, a PARM.stepname= or COND.stepname= parameter may be entered for each step. The entries must be in order, i.e., PARM.step1=, PARM.step2=, etc.

DD Statements

All parameters in the operand field of DD statements may be overridden by including in the input stream (following the EXEC card calling the procedure) a DD statement with the notation //stepname.ddname in the name field. "Stepname" refers to the job step in which the statement identified by "ddname" appears.

Examples

In the assembly procedure ASMFC (Figure 1), the production of a punched object deck could be suppressed and the UNIT= and SPACE= parameters of data set SYSUT1 re-specified, by including the following statements in the input stream:

```
//stepname     EXEC      PROC=ASMFC,          X
//              PARM.ASM=NODECK
//ASM.SYSUT1    DD        UNIT=2311,          X
//              SPACE=(200,(300,40))
//ASM.SYSIN     DD        *
```

In procedure ASMFCLG (Figure 3), suppressing production of an assembler listing and adding the COND= parameter to the EXEC statement, which specifies execution of the linkage editor, may be desired. In this case, the EXEC statement in the input stream would appear as follows:

```
//stepname     EXEC      PROC=ASMFCLG,          X
//              PARM.ASM=(NOLIST,LOAD),       X
//              COND.LKED=(8 LT,stepname.ASM)
```

NOTE: Overriding the LIST parameter effectively deletes the PARM=LOAD so this must be repeated in the override statement.

For current execution of procedure ASMFCLG, no assembler listing would be produced, and execution of the linkage editor job step //LKED would be suppressed if the return code issued by the assembler (step ASM) was greater than 8. Using the procedure ASMFCL (Figure 2) to:

1. Read input from a non-labeled 9-track tape on unit 282 that has a standard blocking factor of 10.
2. Put the output listing on a labeled tape VOLID=TAPE10, with a data set name of PROG1 and a blocking factor of 5.
3. Block the SYSGO output of the assembler and use it as input to the linkage editor with a blocking factor of 5.

The assembler listing (Figure 5) consists of five sections, ordered as follows: external symbol dictionary items, the source and object program statements, relocation dictionary items, symbol cross reference table, and diagnostic messages. In addition, three statistical messages may appear in the listing:

1. After the diagnostics, a statements-flagged message indicates the total number of statements in error. It appears as follows: nnn STATEMENTS FLAGGED IN THIS ASSEMBLY.
2. After the statements-flagged message, the assembler prints the highest severity code encountered (if non-zero). This is equal to the assembler return code. The message appears as follows: nn WAS HIGHEST SEVERITY CODE.
3. After the severity code, the assembler prints a count of the number of records read from SYSIN and from SYSLIB. It also prints the options for the assembly. (See the section "Assembler Options"). These messages appear as follows:

```
*STATISTICS* SOURCE RECORDS (SYSIN) =
nnnnn SOURCE RECORDS (SYSLIB)= nnnnn
*OPTIONS IN EFFECT* xxxx,xxxxxx, etc.
```

4. After the options in effect, the assembler prints a count of lines printed, which appears as follows: nnn PRINTED LINES. This is a count of the actual number of 121-byte records generated by the assembler; it may be less than the total number of printed and blank lines appearing on the listing if the SPACE n assembler instruction is used. For a SPACE n that does not cause an eject, the assembler inserts n blank lines in the listing by generating n/3 blank 121-byte records -- rounded to the next lower integer if a fraction results; e.g., for a SPACE 2, no blank records are generated. The assembler does not generate a blank record to force a page eject.

In addition to the above items, the assembler prints the deck identification and current date on every page of the listing. If the timer is available, the assembler prints the time of day to the left of the date on page 1 of the ESD listing. This is the time when printing starts, rather than the start of the assembly, and is intended only to provide unique identification for assemblies made on the same day. The time is printed as hh.mm,

where hh is the hour of the day (midnight beginning at 00), and mm is the number of minutes past the hour.

EXTERNAL SYMBOL DICTIONARY (ESD)

This section of the listing contains the external symbol dictionary information passed to the linkage-editor or loader in the object module. The entries describe the control sections, external references, and entry points in the assembled program. There are six types of entries, shown in Table 4, along with their associated fields. The circled numbers refer to the corresponding heading in the sample listing (Figure 5). The X's indicate entries accompanying each type designation.

Table 4. Types of ESD Entries

① SYMBOL	② TYPE	③ ID	④ ADDR	⑤ LENGTH	⑥ LD ID
X	SD	X	X	X	-
X	LD	-	X	-	X
X	ER	X	-	-	-
-	PC	X	X	X	-
-	CM	X	X	X	-
X	XD	X	X	X	-

1. This column contains the name of every external dummy section, control section, entry point, and external symbol.
2. This column contains the type designator for the entry, as shown in the table. The type designators are defined as:
 - SD--Names section definition. The symbol appeared in the name field of a CSECT or START statement.
 - LD--The symbol appeared as the operand of the ENTRY statement.
 - ER--External reference. The symbol appeared as the operand of an EXTRN statement, or was defined as a V-type address constant.
 - PC--Unnamed control section definition.
 - CM--Common control section definition.
 - XD--External dummy section (same as PR, Pseudo Register in the Linkage Editor manual).
3. This column contains the external symbol dictionary identification number (ESDID). The number is a unique two-digit hexadecimal number identifying

EXTERNAL SYMBOL DICTIONARY

EXAM SYMBOL	TYPE	ID	ADDR	LENGTH	LD	ID
① SAMPLR	SD	01	000000	000388		

Page 1
00.16 4/11/66

SAMPLE PROGRAM

LOC	OBJECT CODE	ADDR1	ADDR2	STMT	SOURCE STATEMENT
000000	47F0 F00A		0000A	59+BEGIN B	10(0,15) BRANCH AROUND ID
000004	05			60+	DC AL1(5)
000005	C2C5C7C9D5			61+	DC CL5'BEGIN' IDENTIFIER
00000A	90EC D00C	0000C		62+	STM 14,12,12(13) SAVE REGISTERS
00000E	05C0			63	BALR R12,0 ESTABLISH ADDRESSABILITY OF PROGRAM
000010				64	USING *,R12 AND TELL THE ASSEMBLER WHAT BASE TO USE

Page 3
F 14FEB66 4/11/66

RELOCATION DICTIONARY

POS.ID	REL.ID	FLAGS	ADDRESS
01	01	0C	0001FC
01	01	0C	00020C
01	01	0C	00021C
01	01	0C	0002D4
01	01	0C	000334

Page 1
4/11/66

CROSS-REFERENCE

SYMBOL	LEN	VALUE	DEFN	REFERENCES
BEGIN	00004	000000	00059	0156 0158 0174 0184 0186 0220
EXIT	00004	00007E	00096	0111
HIGHER	00002	0000F4	00130	0125
IHB0005	00001	00007B	00093	0090
IHB0005A	00002	00007C	00094	0089

Page 1
4/11/66

DIAGNOSTICS

STMT	ERROR CODE	MESSAGE
19	IEU025	NEAR OPERAND COLUMN 7--RELOCATABILITY ERROR
21	IEU035	NEAR OPERAND COLUMN 9--ADDRESSABILITY ERROR

2 STATEMENTS FLAGGED IN THIS ASSEMBLY
8 WAS HIGHEST SEVERITY CODE
STATISTICS SOURCE RECORDS (SYSIN) = 225 SOURCE RECORDS (SYSLIB) = 5
OPTIONS IN EFFECT LIST, NODECK, NOLOAD, NORENT, XREF, NOTEST, ALGN, OS, LINE CNT = 58
261 PRINTED LINES

Page 1
4/11/66

● Figure 5. Assembler Listing

- the entry. It is used by the LD entry of the ESD and by the relocation dictionary for cross-referencing the ESD.
- This column contains the address of the symbol (hexadecimal notation) for SD- and LD-type entries, and zeros for ER-type entries. For PC- and CM-type entries, it indicates the beginning address of the control section. For XD-type entries, it indicates the alignment by printing a number one less than the number of bytes in the unit of alignment, e.g., 7 indicates double word alignment.
 - This column contains the assembled length, in bytes, of the control section (hexadecimal notation).
 - This column contains, for LD-type entries, the identification (ID) number assigned to the ESD entry that identifies the control section in which the symbol was defined.

SOURCE AND OBJECT PROGRAM

This section of the listing documents the source statements and the resulting object program.

7. This is the four-character deck identification. It is the symbol that appears in the name field of the first TITLE statement. The assembler prints the deck identification and date (item 16) on every page of the listing.
8. This is the information taken from the operand field of a TITLE statement.
NOTE: TITLE, SPACE and EJECT statements will not appear in the source listing unless the statement is continued onto another card. Then the first card of the statement is printed. However, any of these three types of statements, if generated as macro instruction expansion, will never be listed regardless of continuation.
9. Listing page number. Each section of the listing starts with page 1.
10. This column contains the assembled address (hexadecimal notation) of the object code.
11. This column contains the object code produced by the source statement. The entries are always left-justified. The notation is hexadecimal. Entries are machine instructions or assembled constants. Machine instructions are printed in full with a blank inserted after every four digits (two bytes). Constants may be only partially printed (see the PRINT assembler instruction in the Assembler Language publication).
12. These two columns contain effective addresses (the result of adding together a base register value and displacement value):
 - a. The column headed ADDR1 contains the effective address for the first operand of an SS instruction.
 - b. The column headed ADDR2 contains the effective address of the second operand of any instruction referencing storage.

Both address fields contain six digits; however, if the high-order digit is a zero, it is not printed.
13. This column contains the statement number. A plus sign (+) to the right of the number indicates that the statement was generated as the result of macro instruction processing.

14. This column contains the source program statement. The following items apply to this section of the listing:
 - a. Source statements are listed, including those brought into the program by the COPY assembler instruction, and including macro definitions submitted with the main program for assembly. Listing control instructions are not printed, except for the following case: PRINT is listed when PRINT ON is in effect and a PRINT statement is encountered.
 - b. Macro definitions obtained from SYSLIB are not listed.
 - c. The statements generated as the result of a macro instruction follow the macro instruction in the listing.
 - d. Assembler or machine instructions in the source program that contain variable symbols are listed twice: as they appear in the source input, and with values substituted for the variable symbols.
 - e. Diagnostic messages are not listed inline in the source and object program section. An error indicator, *****ERROR*****, follows the statement in error. The message appears in the diagnostic section of the listing.
 - f. MNOTE messages are listed inline in the source and object program section. An MNOTE indicator appears in the diagnostic section of the listing for MNOTE statements other than MNOTE *. The MNOTE message format is severity code, message text. The MNOTE * form of the MNOTE statements results in an inline message only. An MNOTE indicator does not appear in the diagnostic section of the listing.
 - g. When an error is found in a programmer macro definition, it is treated the same as any other assembly error: the error indication appears after the statement in error, and a diagnostic is placed in the list of diagnostics. However, when an error is encountered during the expansion of a macro instruction (system- or programmer-defined), the error indication appears in place of the erroneous statement, which is not listed. The error indication follows the last statement listed before the
 - h.

erroneous statement was encountered, and the associated diagnostic message is placed in the list of diagnostics.

- i. Literals that have not been assigned locations by an LTORG statement appear in the listing following the END statement. Literals are identified by the equal (=) sign preceding them.
 - j. If the END statement contains an operand, the transfer address appears in the location column (LOC).
 - k. In the case of COM, CSECT, and DSECT statements, the location field contains the beginning address of these control sections, i.e., the first occurrence.
 - l. In the case of EXTRN, ENTRY, and DXD instructions, the location field and object code field are blank.
 - m. For a USING statement, the location field contains the value of the first operand.
 - n. For LTORG and ORG statements, the location field contains the location assigned to the literal pool or the value of the ORG operand.
 - o. For an EQU statement, the location field contains the value assigned.
 - p. Generated statements always print in normal statement format. Because of this, it is possible for a generated statement to occupy three or more continuation lines on the listing. This is unlike source statements, which are restricted to two continuation lines.
15. This column contains the identifier of the assembler (F) and the date when this version was released by Systems Development Division to DPD Program Information Department.
 16. Current date (date run is made).
 17. Identification-sequence field from the source statement.

RELOCATION DICTIONARY

This section of the listing contains the relocation dictionary information passed to the linkage editor in the object module. The entries describe the address constants in the assembled program that are affected by relocation.

18. This column contains the external symbol dictionary ID number assigned to the ESD entry that describes the control section in which the address constant is used as an operand.

19. This column contains the external symbol dictionary ID number assigned to the ESD entry that describes the control section in which the referenced symbol is defined.
20. The two-digit hexadecimal number in this column is interpreted as follows:

First Digit. A zero indicates that the entry describes an A-type or Y-type address constant. A one indicates that the entry describes a V-type address constant. A two indicates that the entry describes a Q-type address constant. A three describes a CXD entry.

Second Digit. The first three bits of this digit indicate the length of the constant and whether the base should be added or subtracted:

<u>Bits 0 and 1</u>	<u>Bit 2</u>
00 = 1 byte	0 = +
01 = 2 bytes	1 = -
10 = 3 bytes	
11 = 4 bytes	

21. This column contains the assembled address of the field where the address constant is stored.

CROSS REFERENCE

This section of the listing information concerns symbols which are defined and used in the program.

22. This column contains the symbols.
23. This column states the length (decimal notation), in bytes, of the field occupied by the symbol value.
24. This column contains either the address the symbol represents, or a value to which the symbol is equated.
25. This column contains the statement number of the statement in which the symbol was defined.
26. This column contains the statement numbers of statements in which the symbol appears as an operand. In the case of a duplicate symbol, the assembler fills this column with the message:

****DUPLICATE****

The following notes apply to the cross-reference section:

- Symbols appearing in V-type address constants do not appear in the cross-reference listing.
- A PRINT OFF listing control instruction does not affect the production of the cross-reference section of the listing.

- In the case of an undefined symbol, the assembler fills columns 23, 24, and 25 with the message:

UNDEFINED.

DIAGNOSTICS

This section contains the diagnostic messages issued as a result of error conditions encountered in the program. The text, severity code, and explanatory notes for each message are contained in "Appendix A".

27. This column contains the number of the statement in error.
28. This column contains the message identifier.
29. This column contains the message, and, in most cases, an operand column pointer that indicates the vicinity of the error. In the following example, the approximate location of the addressability error occurred in the 9th column of the operand field:

Example:

STMT	ERROR CODE	MESSAGE
21	IEU035	NEAR OPERAND COLUMN 9 -- ADDRESSABILITY ERROR

The following notes apply to the diagnostic section:

- An MNOTE indicator of the form MNOTE STATEMENT appears in the diagnostic section if an MNOTE statement other than MNOTE* is issued by a macro instruction. The MNOTE statement itself is inline in the source and object program section of the listing. The operand field of an MNOTE* is printed as a comment, but does not appear in the diagnostic section.
- A message identifier consists of six characters and is of the form: IEUxxx
IEU identifies the issuing agent as Assembler F, and xxx is a unique number assigned to the message.

NOTE: Editing errors in system macro definitions (macro definitions included in a macro library) are discovered when the macro definitions are read from the macro library. This occurs after the END statement has been read. They will therefore be flagged after the END statement. If the programmer does not know which of his system macros caused an error it is necessary to punch all system macro definitions used in the program, including inner macro definitions, and insert them in the program as programmer macro definitions, since the programmer macro definitions are flagged in-line. To aid in debugging it is advisable to test all macro definitions as programmer macro definitions before incorporating them in a library as system macro definitions.

PROGRAMMING CONSIDERATIONS

This section consists of a number of discrete subjects about assembler language programming.

SAVING AND RESTORING GENERAL REGISTER CONTENTS

A problem program should save the values contained in the general registers upon commencing execution and, upon completion, restore to the general registers these same values. Thus, as control is passed from the operating system to a problem program and, in turn, to a subprogram, the status of the registers used by each program is preserved. This is done through use of the SAVE and RETURN system macro instructions.

The SAVE macro instruction should be the first statement in the program. It stores the contents of registers 14, 15, and 0 through 12 in an area provided by the program that passes control. When a problem program is given control, register 13 points to an area in which the general register contents should be saved.

If the program calls any subprograms, or uses any operating system services other than GETMAIN, FREEMAIN, ATTACH, and XCTL, it must first save the contents of register 13 and then load the address of an 18 full-word save area into register 13. This save area is in the problem program and is used by any subprograms or operating system services called by the problem program.

At completion, the problem program restores the contents of general registers 14, 15 and 0-12 by use of the RETURN system macro instruction (which also indicates program completion). The contents of register 13 must be restored before execution of the RETURN macro instruction.

The coding sequence that follows illustrates the basic process of saving and restoring the registers. A complete discussion of the SAVE and RETURN macro instructions and the saving and restoring of registers is contained in the Data Management Services and Data Management Macro-Instructions publications (see Preface).

Name	Operation	Operand
BEGIN	SAVE	(14, 12)
	.	set up base register
	ST	13,SAVEBLK+4
	LA	13,SAVEBLK
	.	
	L	13,SAVEBLK+4
SAVEBLK	RETURN	(14, 12)
	DC	18F'0'

PROGRAM TERMINATION

Completion of an assembler source program is indicated by using the RETURN system macro instruction to pass control from the terminating program to the program that initiated it. The initiating program may be the operating system or, if a subprogram issued the RETURN, the program that called it.


In addition to indicating program completion and restoring registers, the RETURN macro instruction may also pass a return code -- a condition indicator that may be used by the program receiving control. If the return is to the operating system, the return code is compared against the condition stated in the COND= parameter of the JOB or EXEC statements. If return is to another problem program, the return code is available in general register 15, and may be used as desired. Register 13 should be restored before issuing the RETURN macro instruction.

The RETURN system macro instruction is discussed in detail in the Supervisor and Data Management Macro Instructions publication.

PARAM FIELD ACCESS

Access to information in the PARM field of an EXEC statement is gained through general register 1. When control is given to the problem program, general register 1 contains the address of a full word which, in turn, contains the address of the data area containing the information.

The data area consists of a halfword containing the count (in binary) of the number of information characters, followed by the information field. The information field is aligned to a full-word boundary. The following diagram illustrates this process.



MACRO DEFINITION LIBRARY ADDITIONS

Source statement coding, to be retrieved by the COPY assembler instruction, and

macro definitions may be added to the macro library. The IEBUPDTE utility program is used for this purpose. Details of this program and its control statements are contained in the Utilities publication. The following sequence of job control statements can be used to call the utility program and identify the needed data sets. It is assumed that the job control statements, IEBUPDTE program control statements, and data are to enter the system via the input stream.

```
//jobname      JOB
//stepname     EXEC  PGM=IEBUPDTE,PARM=MOD
//SYSUT1      DD   DSNNAME=SYS1.MACLIB,DISP=OLD
//SYSUT2      DD   DSNNAME=SYS1.MACLIB,DISP=OLD
//SYSPRINT    DD   SYSOUT=A
//SYSIN       DD   *
```

IEBUPDTE control statements and source statements or macro-definitions to be added to the macro-library (SYS1.MACLIB)

/* (delimiter statement)

LOAD MODULE MODIFICATION - ENTRY POINT RESTATEMENT

If the editing functions of the linkage editor are to be used to modify a load module, the entry point to the load module must be restated when the load module is reprocessed by the linkage editor. Otherwise, the first byte of the first control section processed by the linkage editor will become the entry point. To enable restatement of the original entry point, or designation of a new entry point, the entry point must have been identified originally as an external symbol, i.e., appeared as an entry in the external symbol dictionary. External symbol identification is done automatically by the assembler if the entry point is the name of a control section or START statement; otherwise, an assembler ENTRY statement must be used to identify the entry point name as an external symbol.

When a new object module is added to or replaces part of the load module, the entry point is restated in one of three ways:

- By placing the entry point symbol in the operand field of an EXTRN statement and an END statement in the new object module.

- By using an END statement in the new object module to designate a new entry point in the new object module.
- By using a linkage editor ENTRY statement to designate either the original entry point or a new entry point for the load module.

Further discussion of load module entry points is contained in the Linkage Editor publication.

OBJECT MODULE LINKAGE

Object modules, whether Assembler-, FORTRAN-, or COBOL-generated, may be combined by the linkage editor to produce a composite load module, provided each object module conforms to the data formats and linkage conventions required. This topic discusses the use of the CALL system macro instruction to link an assembler language "main" program to subprograms produced by FORTRAN and COBOL. The Supervisor and Data Management Macro Instructions publication contains additional details concerning linkage conventions and the CALL system macro instruction.

Figure 6 shows the statements used to establish the assembler program linkage to the called subprograms.

If any input/output operations are performed by called subprograms, appropriate DD statements for the data sets used by the subprograms must be supplied. See the FORTRAN IV (E) Programmer's Guide publication for explanation of the DD statements used to describe data sets for FORTRAN programs and a description of the special FORTRAN data set record formats. The COBOL (E) Programmer's Guide publication provides DD statement information for COBOL programs.

DICTIONARY SIZE AND SOURCE STATEMENT COMPLEXITY

This section describes the composition of the assembler dictionaries and their entry sizes, and describes methods for determining if the limits on source statement complexity will be exceeded.

Dictionary entries, e.g., sequence symbol names, prototype symbolic parameters, vary in length. Therefore, the number of entries a dictionary can hold is determined by the types of entries.

Source statement complexity -- the number of symbols, characters, operators, delimiters, references to length attributes, self-defining terms, literals, and expressions appearing in a source statement -- determines whether or not the source statement can be successfully processed.

```

        SAVE    (14,12)
        .
        .      set up base register
        .
1      ST      13,SVAREA+4
        LA      15,SVAREA
        ST      15,8(13)
        LR      13,15
        .
        .
2      CALL    name,(V1,V2,V3),VL
        .
        .
        L      13,SVAREA+4
3      RETURN  (14,12)
4  SVAREA    DC    18F'0'
5  V1        DC    (data)
6  V2        DC    (data)
        V3    DC    (data)
        END

```

¹ This is an example of OS linkage convention. See the publication Supervisor and Data Management Services for details.

² The symbol used for "name" in this statement is:

- a. The name of a subroutine or function, when the linkage is to a FORTRAN-written subprogram.
- b. The name defined by the following COBOL statements in the procedure division:

```
ENTER LINKAGE. ENTRY' name'.
```

- c. The name of a CSECT or START statement, or a name used in the operand field of an ENTRY statement in an assembler subprogram.

The order in which the parameter list is written must reflect the order in which the called subprogram expects the argument. If the called routine is a FORTRAN-written function, the returned argument is not in the parameter list: a real or double precision function returns the value in floating point register zero; an integer function returns the value in general purpose register zero.

CAUTION: When linking to FORTRAN-written subprograms, consideration must be given to the storage requirements of IBCOM (FORTRAN execution-time I/O and interrupt handling routines) which accompanies the compiled FORTRAN subprogram. In some instances the call for IBCOM is not automatically generated during the FORTRAN compilation. The FORTRAN IV Library publication provides information about IBCOM requirements and assembler statements used to call IBCOM.

FORTRAN-written subprograms and FORTRAN library subprograms allow variable-length parameter lists in linkages which call them; therefore all linkages to FORTRAN subprograms are required to have the high-order bit in the last parameter in the linkage set to 1. COBOL-written subprograms have fixed-length calling linkages; therefore, for COBOL the high-order bit in the last parameter need not be set to 1.

³ This statement reserves the save area needed by the called subprogram. When control is passed to the subprogram, register 13 contains the address of this area.

^{4 5 6} When linking to a FORTRAN or COBOL subprogram, the data formats declared in these statements are determined by the data formats required by the FORTRAN or COBOL subprograms.

Figure 6. Linkage Statements

DICTIONARIES USED IN CONDITIONAL ASSEMBLY AND MACRO INSTRUCTION EXPANSION

To accomplish macro instruction expansion and conditional assembly, the assembler constructs a general dictionary consisting of two parts: one global dictionary for the entire program, and an area for all of the local dictionaries.

The global dictionary contains one entry for each machine operation code, extended mnemonic operation code, assembler operation code, macro instruction, and global SET variable symbol.

The local dictionary area consists of one local dictionary for each different

macro definition in the program, and one local dictionary for the main portion of the program (those statements not within a macro definition, also called "open code."). The contents of the local dictionaries are described in subsequent paragraphs.

The capacity of the general dictionary (global dictionary and all local dictionaries) is up to 64 blocks of 1024 bytes each. The division of the dictionary into global and local sections is done dynamically: as the global dictionary becomes larger, it occupies blocks taken from the local dictionary area. Thus, the global dictionary is always core resident. As it

expands into the local dictionary area, the local dictionaries may overflow onto a utility file. The size of the dictionaries in core depends upon core availability. The minimum core allocation is three blocks for the global dictionary and two blocks for each local dictionary.

Each block in the global and local dictionaries contains complete entries. Any entry not fitting into a block is placed in the next block; the remaining bytes in the current block are not used.

The global and local dictionaries take two forms: one when the dictionary entries are collected, i.e., picked up during the initial scan of the source program, and one during the actual conditional assembly and macro generation, i.e., generation time. The following text describes the global and local dictionaries at both collection time and generation time.

Global Dictionary at Collection Time

One global dictionary is built for the entire program. It contains machine operation codes, extended mnemonic operation codes, assembler operation codes, OPSYN defined operation codes, macro instruction mnemonics, and global SET variable symbols. One entry is made is shown in Table 5.

●Table 5. Global Dictionary Entries at Collection Time

Entry	Size
Each machine operation code **	5 bytes plus mnemonic*
Each extended mnemonic operation code or assembler operation **	6 bytes plus mnemonic*
Each macro mnemonic operation code	10 bytes plus mnemonic*
Each global SET variable symbol	7 bytes plus name*

*One byte is used for each character in the name or mnemonic.

**For the first two types of entries, a total of $06FE_{16}$ (1790₁₀) bytes of core is required.

Fixed overhead for this dictionary is:

- 8 bytes for the first block
- 4 bytes for each succeeding block
- 5 bytes for the last block

Local Dictionaries at Collection Time

For the main portion of the program (those statements not within a macro definition), one local dictionary is constructed in which ordinary symbols, sequence symbols, and local SET variable symbols are entered. In addition, one local dictionary is constructed for each different macro definition in the program. These local dictionaries contain one entry for each local SET variable symbol, sequence symbol, and prototype symbolic parameter declared within the macro definition. If a sequence symbol is defined before it is referenced, an extra entry for the symbol is made. Table 6 shows the size of each type of entry.

●Table 6. Local Dictionary Entries at Collection Time

Entry	Size
Each sequence symbol	10 bytes plus name*
Each local SET variable symbol	7 bytes plus name*
Each prototype symbolic parameter	5 bytes plus name*
Each ordinary symbol appearing in the main portion of the program.	10 bytes plus name*

*One byte is used for each character in the name or mnemonic.

Fixed overhead for this dictionary is:

- 8 bytes for the first block (if in the main program)
- 32 bytes for the first block (if in a macro definition)
- 4 bytes for each succeeding block
- 5 bytes for the last block

Global Dictionary at Generation Time

The sizes of the global dictionary entries at generation time are shown in Table 7.

● Table 7. Global Dictionary Entries at Generation Time

Entry	Size
Each macro mnemonic operation code	3 bytes
Each global SETA symbol (dimensioned)	2 byte plus 4N*
Each global SETA symbol (undimensioned)	4 bytes
Each global SETB symbol (dimensioned)	2 byte plus (N/8)* (N/8 is rounded to the next highest integer)
Each global SETB symbol (undimensioned)	1 bit
Each global SETC symbol (dimensioned)	2 byte plus 9N*
Each global SETC symbol (undimensioned)	9 bytes

*N = dimension

Fixed overhead for this dictionary is 4 bytes plus word alignment.

Local Dictionaries at Generation Time

Table 8 shows the sizes of the various entries appearing in the local dictionaries at generation time.

● Table 8. Local Dictionary Entries at Generation Time

Entry	Size
Each sequence symbol	5 bytes
Each local SETA symbol (dimensioned)	2 byte plus 4N*
Each local SETA symbol (undimensioned)	4 bytes
Each local SETB symbol (dimensioned)	2 byte plus (N/8)* (N/8 is rounded to the next highest integer)
Each local SETB symbol (undimensioned)	1 bit
Each local SETC symbol (dimensioned)	2 byte plus 9N*
Each local SETC symbol (undimensioned)	9 bytes
Each ordinary symbol appearing in the main portion of the program.**	5 bytes

*N=dimension

**These entries appear only in the main program local dictionary.

Fixed overhead for this dictionary is 20 bytes plus word alignment.

Additional Dictionary Requirements

The generation time global dictionary and the generation time local dictionary for the main portion of the program must be resident in main storage.

In addition, if the program contains any macro instructions, main storage is required for the largest local dictionary of the macro definitions being processed. Furthermore, during processing of macro definitions containing inner macro instructions, main storage is required for the generation time local dictionaries for the inner macro instructions contained within the macro definition.

In addition to those requirements specified for the local dictionary of the main portion of the program, each macro definition local dictionary requires space for entries shown in Table 9.

Table 9. Macro Definition Local Dictionary Parameter Table

Entry	Size
Each character string (1)	3 bytes plus L
Each hexadecimal, binary, decimal, and character self-defining term (2)	7 bytes plus L
Each symbol (3)	9 bytes plus L
Each sublist	9 bytes plus 3N bytes plus Y

L = Length of BCD entry in bytes

N = Number of entries in sublist

Y = $E_1 + E_2 + E_3 + \dots + E_n$
where E = size of an entry (formats 1, 2, and 3 above)

Fixed overhead for the macro definition local dictionary parameter table is 22 bytes. Each nested macro instruction also requires space in its local dictionary for the following:

Parameter pointer list 8 bytes plus 2N
(N = the number of operands)

Pointers to parameter pointer list and parameter table 8 bytes plus word alignment

Correction of Dictionary Overflow

If an assembly is terminated at collection time with either a GLOBAL DICTIONARY FULL message (IEU053) or a LOCAL DICTIONARY FULL

message (IEU054), the programmer can take one or more of the following steps:

1. Split the assembly into two or more parts and assemble each separately.
2. Allocate more core for the assembler (the global and local dictionaries together can occupy up to 64K).
3. Run the assembly under Assembler E, unless it includes features not allowed by Assembler E. (Due to its dictionary building algorithm, Assembler E can handle more symbols with a given size dictionary than can Assembler F.)
4. Specify a smaller SYSLIB blocksize. Thus, if BLKSIZE=3600, try BLKSIZE=1800 or BLKSIZE=1200, reblock the library to the size chosen, and try the assembly again.

If the assembly is terminated at generation time with a GENERATION TIME DICTIONARY AREA OVERFLOWED message (IEU068), the programmer should allocate more core to the assembler and re-assemble his program. If he cannot allocate more core to the assembler, the programmer should split the assembly into two or more parts and assemble each separately.

SYMBOL TABLE OVERFLOW

Assembler performance can degrade when the source text plus macro-generated statements contains many ordinary symbols. If these are more ordinary symbols than will fit in the symbol table, the assembler will make one or more additional passes over the text. No symbols will be lost, but assembly time will increase.

In general, the assembler can handle 400 ordinary symbols without overflow in its minimum core (See Table 1). Because of input and/or output blocking differences, minimum core varies. It is approximately 45,000 bytes for PCP, 49,000 bytes for MFT, and 51,000 bytes for MVT. The assembler can process one additional symbol for each 18 bytes above minimum core.

SOURCE STATEMENT COMPLEXITY

The complexity of a source statement is limited both by the macro generator and the assembler portions of the assembler. The following topics provide the information necessary to determine if statement-complexity limitations for either portion of the assembler are being exceeded.

Macro Generation and Conditional Assembly Limitation

For any statement which

1. Is a conditional assembly statement,
2. Is a DC or DS statement,
3. Is an EXTRN statement,
4. Contains a sequence symbol or a variable symbol,
5. Is not a macro instruction or prototype statement,

the total number of explicit occurrences of

1. Ordinary symbols (includes machine mnemonics, assembler mnemonics, conditional assembly mnemonics, and macro instruction mnemonics),
2. Variable symbols,
3. Sequence symbols,

must not exceed 50 for the entire statement.

For macro instructions and prototype statements the number of occurrences of ordinary symbols, variable symbols, and sequence symbols must not exceed 50 in the name and operation fields combined; or in each operand unless the operand is a sublist, in which case the limit is applied to each sublist operand. In any operand if a character string has the same form as a symbol, it is counted as a symbol.

Examples of Counts:

```
&B2 SETB (T'NAME EQ 'W') count=3 (&B2,SETB,NAME)
EXTRN A,B,C,&C          count=5 (EXTRN,A,B,C,&C)
```

Assembler Portion Limitations

1. Generated statements may not exceed 236 characters. Statement length includes name, operation, operand, and comments. If a comments field exists, the blank separating the operand and comments field is included in the statement length. The statement is truncated if it exceeds 236 characters.
2. DC, DS, DXD, and literal DCs cannot contain more than 32 operands per statement.

SYSTEM/360 MODEL 91 PROGRAMMING CONSIDERATIONS

The assembly language programmer should be aware of the operational differences between the Model 91 and other System/360 models. The Model 91 requires a simulation

routine to execute most decimal instructions and it yields different floating-point instructions execution results. The Model 91 also decodes and executes instructions concurrently.

These and other coding and timing considerations are discussed in detail in IBM System/360 Model 91 Functional Characteristics, Form A22-6907. Additional information on how to control sequential and non-sequential instruction execution is given below.

Controlling Instruction Execution Sequence

The CPU maintains a logical consistency with respect to its own operations, including the beginning and ending of I/O operations, but it does not assume responsibility for such consistency in the operations performed by asynchronous units. Consequently, for any asynchronous unit that depends upon a strict adherence to sequential (or serial) execution, a problem program must set up its own procedures to ensure the proper instruction sequence.

For a program section that requires the serial or sequential execution of instructions, the following 'no-operation' instruction:

BCR M,0 where $M \neq 0$

causes the instruction decoder to halt, and the instructions that have already been decoded to be executed. (This action is called a pipe-line drain.) On the Model 91, this instruction ensures that all the instructions preceding it are executed before the instruction succeeding it is decoded. Use of this instruction should be minimized since it may affect the performance of the Model 91.

Isolating an instruction by preceding it and succeeding it with a BCR instruction eliminates multiple imprecise interruptions from more than one instruction by virtue of the pipe-line drain effect. However, since multiple exceptions may occur in one instruction, this technique does not eliminate a multiple imprecise interruption nor does it change an imprecise interruption into a precise interruption. The use of the BCR instruction does not assure a programmer that he can fix up an error situation. In general, the only information available will be the address of the BCR instruction. The length of the instruction preceding the BCR instruction is not recorded, and generally there is no way to determine what that instruction is.

SYSTEM/360 MODEL 85 PROGRAMMING CONSIDERATIONS

The Model 85 has two special features available to the assembler language programmer.

They are extended-precision (two doubleword) floating point instructions and byte-oriented (unaligned) operands. Detailed information on these features is in the IBM System/360 Principles of Operation manual (GA22-6821).

Assembler F supports these features with mnemonic operation codes for the extended-precision instructions, a two doubleword data constant (DC), an option for suppressing the alignment error message, and an assembler instruction for equating one operation code to another. These assembler features are explained in the following paragraphs.

Extended-Precision Machine Instructions

The extended-precision arithmetic instructions and the rounding instructions of the Model 85 are shown in Table 10. The data format for extended operands of the AXR, SXR, MXR, and LRDR instructions and for extended results of the AXR, SXR, MXR, MXDR, and MXD instructions is shown in Figure 7. A complete description of these instructions is in the Principles of Operation manual.

OPSYN--Operation Code Equate Instruction

A program containing the extended precision instructions cannot be executed successfully on another System/360 model unless those instructions are converted into others that can be executed by the non-Model 85 machine. The OPSYN assembler instruction helps provide a facility for doing this.

The format of the OPSYN statement is:

A OPSYN B

where A is the name field of the statement and is a source code mnemonic; and B is an existing machine instruction mnemonic, an

Table 10. Extended-Precision and Rounding Instructions

Name	Mnemonic	Type	Op Code
ADD NORMALIZED (extended operands, extended result)	AXR	RR	36
SUBTRACT NORMALIZED (extended operands, extended result)	SXR	RR	37
MULTIPLY (extended operands, extended result)	MXR	RR	26
MULTIPLY (long operands, extended result)	MXDR	RR	27
MULTIPLY (long operands, extended result)	MXD	RX	67
LOAD ROUNDED (extended to long)	LRDR	RR	25
LOAD ROUNDED (long to short)	LRER	RR	35




Figure 7. Extended-Precision Floating Point Format

extended mnemonic code, an operation code defined by a previous OPSYN statement, or blank. The OPSYN statement assigns to A all of the properties of B or, if B is blank, removes A from the Assembler F Opcode Table.

If a programmer wishes to use, for example, MXR (extended multiply) on a non-Model 85, he has at least two ways to do so:

1. The programmer can remove MXR from the Assembler F Opcode Table and add a macro instruction named MXR as a user macro, in this manner:

```

MXR OPSYN
MACRO
MXR      &R1,&R2
.
.
MEND
    
```

The first statement removes MXR as a machine instruction and allows the programmer to define MXR as a macro instruction; without the OPSYN statement, Assembler F would continue to assemble MXR as a machine instruction.

2. The programmer may approximate MXR by "equating" it to MDR (multiply long):

```

MXR OPSYN MDR
    
```

The MDR instruction is then assembled for each occurrence of MXR in the source program. This allows him to debug his routine on a non-Model 85 System/360 computer. Later, he can remove the OPSYN statement, reassemble the program, and run it on a Model 85.

Support of Unaligned Data

The Model 85 will execute unprivileged RX- and RS- format instructions with fixed-point, floating-point, or logical operands that are not on integral boundaries. Assembly of such instructions normally produces the diagnostic message "IEU033 Alignment Error". A new PARM option in the EXEC statement for the Assembler F, ALGN or

NOALGN, makes it possible to suppress the message and thereby obtain a "clean" assembly listing. The object code is not affected.

Note that an assembled program that requires use of the byte-oriented operand feature must be run on a Model 85 or 195 machine. Further, it cannot run successfully under the Operating System if it violates any alignment restrictions imposed by OS.

Type L Data Constant

A Define Constant operand type, L, has been added to provide extended-precision floating-point constants for the programmer. It can be used as a Define Storage operand or in a literal. Unless changed by a length modifier, the Type L constant is 16 bytes long and is aligned on a double word boundary. Its format is that of two contiguous Type D constants, as shown in Figure 7, except that it is assembled with the sign of the second double word equal to that of the first, and the characteristic of the second equal to that of the first minus 14, modulo 128.

SYSTEM/360 MODEL 195 PROGRAMMING CONSIDERATIONS

The Model 195 has the following special features: concurrent instruction execution, extended-precision (two doubleword) floating-point instructions, and byte-oriented (unaligned) operands. The previous descriptions of these features under "System/360 Model 91 Programming Considerations" and "System/360 Model 85 Programming Considerations" also apply to the Model 195.

Detailed information on the Model 195 can be found in IBM System/360 Model 195 Functional Characteristics, Order No. GA22-6943.

NOTE: The Model 195 does not need the decimal simulator routine used by the Model 91.

APPENDIX A. DIAGNOSTIC MESSAGES

This appendix explains the messages issued by the assembler. A more detailed description, including information on how the programmer can respond to a message, is included in IBM System/360 Operating System Messages and Codes (GC28-6631). Refer to this publication before responding to any message or calling IBM.

<u>Code</u>	<u>Message</u>	<u>Explanation</u>	<u>Severity Code</u>
IEU001	DUPLICATION FACTOR ERROR	A duplication factor is not an absolute expression, or is zero in a literal: * in duplication factor expression; invalid syntax in expression.	12
IEU002	RELOCATABLE DUPLICATION FACTOR	A relocatable expression has been used to specify the duplication factor.	12
IEU003	LENGTH ERROR	The length specification is out of permissible range or specified invalidly; * in length expression; invalid syntax in expression; no left-parenthesis delimiter for expression.	12
IEU004	RELOCATABLE LENGTH	A relocatable expression has been used to specify length.	12
IEU005	S-TYPE CONSTANT IN LITERAL	S-type address constants may not be specified in a literal.	8
IEU006	INVALID ORIGIN	The location counter has been reset to a value less than the starting address of the control section; ORG operand is not a simply relocatable expression or specifies an address outside the control section.	12
IEU007	LOCATION COUNTER ERROR	The location counter has exceeded $2^{24}-1$, or passed out of control section in negative direction (3 byte arithmetic).	12
IEU008	INVALID DISPLACEMENT	The displacement in an explicit address is not an absolute value within the range of 0 to 4095.	8
IEU009	MISSING OPERAND	Statement requires an operand entry and none is present.	12
IEU010	INCORRECT REGISTER SPECIFICATION	The value specifying the register is not an absolute value within the range 0-15, an odd register is specified where an even register is required, or a register was used where none can be specified.	8
IEU011	SCALE MODIFIER ERROR	The scale modifier is not an absolute expression or is too large, negative scale modifier for floating point, * in scale modifier expression; invalid syntax or illegally specified scale modifier.	8
IEU012	RELOCATABLE SCALE MODIFIER	A relocatable expression has been used to specify the scale modifier.	8
IEU013	EXPONENT MODIFIER ERROR	The exponent is not specified as an absolute expression or is out of range; * in exponent modifier expression; invalid syntax; illegally specified exponent modifier.	8
IEU014	RELOCATABLE EXPONENT MODIFIER	A relocatable expression has been used to specify the exponent modifier.	8

<u>Code</u>	<u>Message</u>	<u>Explanation</u>	<u>Severity Code</u>
IEU015	INVALID LITERAL USAGE	A valid literal is used illegally, e.g., it specifies a receiving field or a register, or it is a Q-type constant.	8
IEU016	INVALID NAME	A name entry is incorrectly specified, e.g., it contains more than 8 characters, it does not begin with a letter, it has a special character imbedded, or--if the statement is OPSYN--the name entry is not an ordinary symbol or is an assembler operation mnemonic.	8
IEU017	DATA ITEM TOO LARGE	The constant is too large for the data type or for the explicit length; operand field for packed DC exceeds 32 characters and for zoned DC exceeds 16 characters (excluding decimal points).	8
IEU018	INVALID SYMBOL	The symbol is specified invalidly, e.g., it is longer than 8 characters or--if the statement is OPSYN--the operand entry is not an ordinary symbol or is an assembler operation mnemonic.	8
IEU019	EXTERNAL NAME ERROR	A CSECT and DSECT statement have the same name, or a symbol is used more than once in an EXTRN or the name field of DXD statements.	8
IEU020	INVALID IMMEDIATE FIELD	The value of the immediate operand exceeds 255, or the operand requires more than one byte of storage, or the operand is not an acceptable type.	8
IEU021	SYMBOL NOT PREVIOUSLY DEFINED	An expression requiring that all symbols be previously defined contains at least one symbol not previously defined.	8
IEU022	ESDTABLE OVERFLOW	The combined number of control sections and dummy sections plus the number of unique symbols in EXTRN statements and V-type constants exceeds 255. (A DSECT which appears as XD makes two entries).	12
IEU023	PREVIOUSLY DEFINED NAME	The symbol which appears in the name field has appeared in the name field of a previous statement.	8
IEU024	UNDEFINED SYMBOL	A symbol being referenced has not been defined in the program.	8
IEU025	RELOCATABILITY ERROR	A relocatable or complex relocatable expression is specified where an absolute expression is required, an absolute expression or complex relocatable expression is specified where a relocatable expression is required, or a relocatable term is involved in multiplication or division.	8
IEU026	TOO MANY LEVELS OF PARENTHESES	An expression specifies more than 5 levels of parentheses.	12
IEU027	TOO MANY TERMS	More than 16 terms are specified in an expression.	12
IEU028	REGISTER NOT USED	A register specified in a DROP statement is not currently in use.	4

<u>Code</u>	<u>Message</u>	<u>Explanation</u>	<u>Severity Code</u>
IEU029	CCW ERROR	Bits 37-39 of the CCW are set to non-zero.	8
IEU030	INVALID CNOP	An invalid combination of operands is specified.	12
IEU031	UNKNOWN TYPE	Incorrect type designation is specified in a DC, DS, or literal. If the DOS option is specified, type Q will be flagged as unknown. (See "Assembler Options".)	8
IEU032	OP-CODE NOT ALLOWED TO BE GENERATED	Operation code allowed only in source statement has been obtained through substitution of a value for a variable symbol.	8
IEU033	ALIGNMENT ERROR	Referenced address is not aligned to the proper boundary for this instruction, e.g., START operand not a multiple of 8. NOTE: If a register is explicitly specified in the reference, no message is issued, e.g., L 3,3(REG4)	4
IEU034	INVALID OP-CODE	Syntax error, e.g., more than 8 characters in operation field, not followed by blank on first card, missing.	8
IEU035	ADDRESSABILITY ERROR	The referenced address does not fall within the range of a USING instruction.	8
IEU036	(No message is assigned to this number)		
IEU037	MNOTE STATEMENT	This indicates that an MNOTE statement has been generated from a macro definition. The text and severity code of the MNOTE statement will be found in line in the listing.	Variable
IEU038	ENTRY ERROR	A symbol in the operand of an ENTRY statement appears in more than one ENTRY statement, it is undefined, it is defined in a dummy section or in blank common, or it is equated to a symbol defined by an EXTRN statement.	8
IEU039	INVALID DELIMITER	This message can be caused by any syntax error, e.g., missing delimiter, special character used which is not a valid delimiter, delimiter used illegally, operand missing, i.e., nothing between delimiters, unpaired parentheses, imbedded blank in expression.	12
IEU040	GENERATED RECORD TOO LONG	There are more than 236 characters in a generated statement.	12
IEU041	UNDECLARED VARIABLE SYMBOL	Variable symbol is not declared in a defined SET symbol statement or in a macro prototype.	8
IEU042	SINGLE TERM LOGICAL EXPRESSION IS NOT A SETB SYMBOL	The single term logical expression has not been declared as a SETB symbol.	8
IEU043	SET SYMBOL PREVIOUSLY DEFINED	Self-explanatory.	8
IEU044	SET SYMBOL USAGE INCONSISTENT WITH DECLARATION	A SET symbol has been declared as undimensioned, but is subscripted, or has been declared dimensioned, but is unsubscripted.	8

<u>Code</u>	<u>Message</u>	<u>Explanation</u>	<u>Severity Code</u>
IEU045	ILLEGAL SYMBOLIC PARAMETER	An attribute has been requested for a variable symbol which is not a legal symbolic parameter.	8
IEU046	AT LEAST ONE RELOCATABLE Y TYPE CONSTANT IN ASSEMBLY	One or more relocatable Y-type constants in assembly; relocation may result in address greater than 2 bytes in length.	4
IEU047	SEQUENCE SYMBOL PREVIOUSLY DEFINED	Self-explanatory.	12
IEU048	SYMBOLIC PARAMETER PREVIOUSLY DEFINED OR SYSTEM VARIABLE SYMBOL DECLARED AS SYMBOLIC PARAMETER	Self-explanatory.	12
IEU049	VARIABLE SYMBOL MATCHES A PARAMETER	Self-explanatory.	12
IEU050	INCONSISTENT GLOBAL DECLARATIONS	A global SET variable symbol, defined in more than one macro definition or defined in a macro definition and in the source program, is inconsistent in SET type or dimension.	8
IEU051	MACRO DEFINITION PREVIOUSLY DEFINED	Prototype operation field is the same as a machine or assembler instruction or a previous prototype. This message is not produced when a programmer macro matches a system macro. The programmer macro will be assembled with no indication of the corresponding system macro.	12
IEU052	NAME FIELD CONTAINS ILLEGAL SET SYMBOL	SET symbol in name field does not correspond to SET statement type.	8
IEU053	GLOBAL DICTIONARY FULL	The global dictionary is full, assembly terminated. See <u>Correction of Dictionary Overflow</u> .	12
IEU054	LOCAL DICTIONARY FULL	The local dictionary is full, current macro aborted. If in open code, assembly terminated. See <u>Correction of Dictionary Overflow</u> .	12
IEU055	INVALID ASSEMBLER OPTION(S) ON THE EXECUTE CARD	Self-explanatory.	8
IEU056	ARITHMETIC OVERFLOW	The intermediate or final result of an expression is not within the range of -2^{31} to $2^{31}-1$.	8
IEU057	SUBSCRIPT NOT WITHIN DIMENSIONS	&SYSLIST or symbolic parameter subscript exceeds 200, or is negative, or zero, or SET symbol subscript exceeds dimension specified in LCL/GBL statement.	8
IEU058	RE-ENTRANT CHECK FAILED	An instruction has been detected, which, when executed, might store data into a control section or a common area. This message is generated only when requested via control cards and merely indicates a possible reentrant error.	4
IEU059	UNDEFINED SEQUENCE SYMBOL	Self-explanatory.	12
IEU060	ILLEGAL ATTRIBUTE NOTATION	L', S', or I' requested for a parameter whose type attribute does not allow these attributes to be requested.	8

<u>Code</u>	<u>Message</u>	<u>Explanation</u>	<u>Severity Code</u>
IEU061	ACTR COUNTER EXCEEDED	Self-explanatory, conditional assembly terminated.	12
IEU062	GENERATED STRING GREATER THAN 255 CHARACTERS	Self-explanatory.	8
IEU063	EXPRESSION 1 OF SUB- STRING IS ZERO OR MINUS	Self-explanatory.	8
IEU064	EXPRESSION 2 OF SUB- STRING IS ZERO OR MINUS	Self-explanatory.	8
IEU065	INVALID OR ILLEGAL TERM IN ARITHMETIC EXPRESSION	The value of a SETC symbol used in the arithmetic expression is not composed of decimal digits, or the parameter is not a self-defining term.	8
IEU066	UNDEFINED OR DUP- PLICATE KEYWORD OPERAND OR EXCESSIVE POSITIONAL OPERANDS	The same keyword operand occurs more than once in the macro instruction; a keyword is not defined in a prototype statement; in a mixed mode macro instruction, more positional operands are specified than are specified in the prototype.	12
IEU067	EXPRESSION 1 OF SUB- STRING GREATER THAN LENGTH OF CHARACTER EXPRESSION	Self-explanatory.	8
IEU068	GENERATION TIME DICTIONARY AREA OVERFLOWED	<u>See Correction of Dictionary Overflow and Dictionary Size and Source Statement Complexity.</u>	12
IEU069	VALUE OF EXPRESSION 2 OF SUBSTRING GREATER THAN 8	Self-explanatory.	8
IEU070	FLOATING POINT CHARACTERISTIC OUT OF RANGE	Exponent too large for length of defining field, exponent modifier has caused loss of all significant digits.	12
IEU071	ILLEGAL OCCURRENCE OF LCL, GBL, OR ACTR STATEMENT	LCL, GBL, or ACTR statement is not in proper place in the program.	8
IEU072	ILLEGAL RANGE ON ISEQ STATEMENT	One or more columns to be sequence checked are between the "begin" and "end" columns of the statement.	4
IEU073	ILLEGAL NAME FIELD	Either a statement requires a name and the name field is blank or a statement has a name which should be blank or a name entry required to be a sequence symbol is not a sequence symbol.	8
IEU074	ILLEGAL STATEMENT IN COPY CODE OR SYSTEM MACRO	A statement brought in by a COPY statement is END, ICTL, ISEQ, MACRO, MEND, or COPY. A model statement in a system macro definition is END, ICTL, ISEQ, or PRINT.	8
IEU075	ILLEGAL STATEMENT OUTSIDE OF A MACRO DEFINITION	Statement allowed only in a macro definition encountered in OPEN code, e.g., period asterisk (*), mnote statement.	8

<u>Code</u>	<u>Message</u>	<u>Explanation</u>	<u>Severity Code</u>
IEU076	SEQUENCE ERROR	See "ISEQ--Input Sequence Checking" in the Assembler Language manual.	12
IEU077	ILLEGAL CONTINUATION CARD	Either there are too many continuation cards, or there are non-blanks between the begin and continue columns on the continuation card, or a card not intended as continuation was treated as such because of punch in continue column of preceding card.	8
IEU078	INCOMPATIBLE ASSEMBLER OPTIONS ON THE EXECUTE CARD	The DOS assembler option has been specified along with the options LOAD, TEST, RENT, or NOALGN. The assembler has used the default options NOLOAD, NOTEST, NORENT or ALGN.	8
IEU079	ILLEGAL STATEMENT IN MACRO DEFINITION	This operation is not allowed within a macro definition.	8
IEU080	ILLEGAL START CARD	Statements affecting or depending upon the location counter have been encountered before a START statement.	8
IEU081	ILLEGAL FORMAT IN GBL OR LCL STATEMENTS	An operand is not a variable symbol.	8
IEU082	ILLEGAL DIMENSION SPECIFICATION IN GBL OR LCL STATEMENT	Dimension is other than 1 to 2500.	8
IEU083	SET STATEMENT NAME FIELD NOT A VARIABLE SYMBOL	Self-explanatory.	8
IEU084	ILLEGAL OPERAND FIELD FORMAT	Syntax invalid, e.g., AIF statement operand does not start with a left parenthesis; operand of AGO is not a sequence symbol; operand of PUNCH, TITLE, MNOTE not enclosed in quotes.	8
IEU085	INVALID SYNTAX IN EXPRESSION	Invalid delimiter, too many terms in expression, too many levels of parentheses, two operators in succession, two terms in succession, or illegal character.	8
IEU086	ILLEGAL USAGE OF SYSTEM VARIABLE SYMBOL	A system variable symbol appears in the name field of a SET statement, is declared in a GBL or LCL statement, or is an unsubscripted &SYSLIST in a context other than N'&SYSLIST.	8
IEU087	NO ENDING APOSTROPHE	There is an unpaired apostrophe or ampersand in the statement.	8
IEU088	UNDEFINED OPERATION CODE	Symbol in operation code field does not correspond to a valid machine or assembler operation code or to any operation code in a macro prototype statement. If the statement is OPSYN, the operand entry is not a defined machine or extended operation code, or the operand entry is omitted and the name entry is not a defined machine or extended operation code. If the DOS option is in effect, DXD and CXD operation codes will be flagged as undefined. (See "Assembler Options".)	12
IEU089	INVALID ATTRIBUTE NOTATION	Syntax error inside a macro definition, e.g., the argument of the attribute reference is not a symbolic parameter.	8

<u>Code</u>	<u>Message</u>	<u>Explanation</u>	<u>Severity Code</u>															
IEU090	INVALID SUBSCRIPT	Syntax error, e.g., double subscript where single subscript is required or vice versa; not right parenthesis after subscript.	8															
IEU091	INVALID SELF-DEFINING TERM	Value is too large or is inconsistent with the data type, e.g., severity code greater than 255.	8															
IEU092	INVALID FORMAT FOR VARIABLE SYMBOL	The first character after the ampersand is not alphabetic, or the variable symbol contains more than 8 characters, or failure to use double ampersand in TITLE card or character self-defining term.	8															
IEU093	UNBALANCED PARENTHESIS OR EXCESSIVE LEFT PARENTHESES	End of statement or card encountered before all parenthesis levels are satisfied. May be caused by embedded blank or other unexpected terminator, or failure to have a punch in continuation column.	8															
IEU094	INVALID OR ILLEGAL NAME OR OPERATION IN PROTOTYPE STATEMENT	Name not blank or variable symbol, or variable symbol in name field is subscripted, or violation of rules for forming variable symbol (must begin with ampersand (&) followed by 1-7 letters and/or numbers first of which must be a letter), or statement following 'MACRO' is not a valid prototype statement.	12															
IEU095	ENTRY TABLE OVERFLOW	Number of ENTRY symbols, i.e., ENTRY instruction operands, exceeds 100.	8															
IEU096	MACRO INSTRUCTION OR PROTOTYPE OPERAND EXCEEDS 255 CHARACTERS IN LENGTH	Self-explanatory.	12															
IEU097	INVALID FORMAT IN MACRO INSTRUCTION OPERAND OR PROTOTYPE PARAMETER	<p>This message can be caused by:</p> <ol style="list-style-type: none"> 1. Illegal "=". 2. A single "&" appears somewhere in the standard value assigned to a prototype keyword parameter. 3. First character of a prototype parameter is not "&". 4. Prototype parameter is a subscripted variable symbol. 5. Invalid use of alternate format in prototype statement, e.g., <table style="margin-left: 40px;"> <tr> <td>10</td> <td>16</td> <td>72</td> </tr> <tr> <td>PROTO</td> <td>&A,&B,</td> <td></td> </tr> <tr> <td></td> <td>or</td> <td></td> </tr> <tr> <td>PROTO</td> <td>&A,&B,</td> <td>X</td> </tr> <tr> <td></td> <td>&C</td> <td></td> </tr> </table> 6. Unintelligible prototype parameter, e.g., "&A*" or "&A&&." 7. Illegal (non-assembler) character appears in prototype parameter or macro instruction operand. 	10	16	72	PROTO	&A,&B,			or		PROTO	&A,&B,	X		&C		12
10	16	72																
PROTO	&A,&B,																	
	or																	
PROTO	&A,&B,	X																
	&C																	
IEU098	EXCESSIVE NUMBER OF OPERANDS OR PARAMETERS	Either the prototype has more than 200 parameters, or the macro instruction has more than 200 operands.	12															
IEU099	POSITIONAL MACRO INSTRUCTION OPERAND, PROTOTYPE PARAMETER OR EXTRA COMMA FOLLOWS KEYWORD	Self-explanatory.	12															

<u>Code</u>	<u>Message</u>	<u>Explanation</u>	<u>Severity Code</u>
IEU100	STATEMENT COMPLEXITY EXCEEDED	More than 32 operands in a DC, DS, DXD, or literal DC, or more than 50 terms in a statement.	8
IEU101	EOD ON SYSIN	EOD before END card.	12
IEU102	INVALID OR ILLEGAL ICTL	The operands of the ICTL are out of range, or the ICTL is not the first statement in the input deck.	16
IEU103	ILLEGAL NAME IN OPERAND FIELD OF COPY CARD	Syntax error, e.g., symbol has more than 8 characters or has an illegal character.	12
IEU104	COPY CODE NOT FOUND	The operand of a COPY statement specified COPY text which cannot be found in the library.	12
IEU105	EOD ON SYSTEM MACRO LIBRARY	EOD before MEND card.	12
IEU106	NOT NAME OF DSECT OR DXD	Referenced symbol expected to be DSECT name, but it is not.	8
IEU107	INVALID OPERAND	Invalid syntax in DC operand, e.g., invalid hexadecimal character in hexadecimal DC; operand string too long for X, B, C, DC's; operand unrecognizable, contains invalid value, or incorrectly specified.	4
IEU108	PREMATURE EOD	Indicates an internal assembler error; should not occur.	16
IEU109	PRECISION LOST	Self-explanatory.	8
IEU110	EXPRESSION VALUE TOO LARGE	Value of expression greater than -16777216 to +16777215. Expressions in EQU and ORG statements are flagged if (1) they include terms previously defined as negative values, or (2) positive terms give a result of more than three bytes in magnitude. The error indication may be erroneous due to (1) the treatment of negative values as three-byte positive values, or (2) the effect of large positive values on the location counter if a control section begins with a START statement having an operand greater than zero, or a control section is divided into subsections.	8
IEU111	SYSGO DD CARD MISSING NOLOAD OPTION USED	Self-explanatory.	16
IEU112	SYPUNCH DD CARD MISSING NODECK OPTION USED	Self-explanatory.	16
IEU116	ILLEGAL OPSYN	An explicit or implicit machine operation, macro definition, or macro instruction preceded this statement.	8
IEU117	OPSYN TABLE OVERFLOW	No room exists in symbol table for this and following OPSYN definitions; generated operation codes may not be processed correctly.	8

<u>Code</u>	<u>Message</u>	<u>Explanation</u>	<u>Severity Code</u>
IEU997	SYSPRINT DD CARD MISSING NOLIST OPTION USED	Self-explanatory. Printed on console device.	0
IEU998	ASSEMBLY TERMINATED. MISSING DATA SET FOR (ddname)	It is printed on SYSPRINT if possible, otherwise it is printed on the console device.	20
IEU999	ASSEMBLY TERMINATED, jobname, stepname, unit address, device type, ddname, opera- tion attempted, error description	Indicates a permanent I/O error. This message is produced by a SYNADAF macro instruction. It is printed on SYSPRINT if possible, otherwise on the console device.	20

This page intentionally left blank.

TEXT (TXT) CARD FORMAT

The format of the TXT cards is as follows:

<u>Columns</u>	<u>Contents</u>
1	12-2-9 punch
2-4	TXT
5	Blank
6-8	Relative address of first instruction on card
9-10	Blank
11-12	Byte count -- number of bytes in information field (cc 17-72)
13-14	Blank
15-16	ESDID
17-72	56-byte information field
73-76	Deck ID (from first TITLE card)
77-80	Card sequence number

RLD CARD FORMAT

The format of the RLD card is as follows:


<u>Columns</u>	<u>Contents</u>
1	12-2-9 punch
2-4	RLD
5-10	Blank
11-12	Data field count -- number of bytes of information in data field (cc 17-72)
13-16	Blank
17-72	Data field:
17-18	Relocation ESDID
19-20	Position ESDID
21	Flag byte
22-24	Absolute address to be relocated
25-72	Remaining RLD entries
73-76	Deck ID (from first TITLE card)
77-80	Card sequence number

If the rightmost bit of the flag byte is set, the following RLD entry has the same Relocation ESDID and Position ESDID, and this information will not be repeated; if the rightmost bit of the flag byte is not set, the next RLD entry has a different Relocation ESDID and/or Position ESDID, and both ESDIDs will be recorded.

For example, if the RLD Entries 1, 2, and 3 of the program listing (Appendix C) contain the following information:

	<u>Pos.</u>	<u>Rel.</u>		
	<u>ESDID</u>	<u>ESDID</u>	<u>Flag</u>	<u>Address</u>
Entry 1	02	04	0C	000100
Entry 2	02	04	0C	000104
Entry 3	03	01	0C	000800

Columns 17-36 of the RLD card would appear as follows:



ESD CARD FORMAT

The format of the ESD card is as follows:

<u>Columns</u>	<u>Contents</u>
1	12-2-9 punch
2-4	ESD
5-10	Blank
11-12	Variable field count -- number of bytes of information in variable field (cc 17-64)
13-14	Blank
15-16	ESDID of first SD, XD, CM, PC, or ER in variable field
17-64	Variable field. One to three 16-byte items of the following format: 8 bytes -- Name, padded with blanks 1 byte -- ESD type code The hex value is: 00 SD 01 LD 02 ER 04 PC 05 CM 06 XD(PR) 3 bytes -- Address 1 byte -- Alignment if XD; otherwise blank 3 bytes -- Length, LDID, or blank
65-72	Blank
73-76	Deck ID (from first TITLE card)
77-80	Card sequence number

END CARD FORMAT

The format of the END card is as follows:

<u>Columns</u>	<u>Contents</u>
1	12-2-9 punch
2-4	END
5	Blank
6-8	Entry address from operand of END card in source deck (blank if no operand)

9-14 Blank
 15-16 ESDID of entry point (blank if no operand)
 17-39 Blank
 40-62 Version of the assembler (e.g., F 14FEB66, time of the assembly (hh.mm), and date of the assembly (mm/dd/yy). See "Assembler Listing" section.)

010 = dummy control section
 011 = common
 100 = instruction
 101 = CCW
 Bit 1 (if data type):
 0 = no multiplicity
 1 = multiplicity (indicates presence of M field)
 Bit 2 (if data type):
 0 = independent (not a packed or zoned decimal constant)
 1 = cluster (packed or zoned decimal constant)
 Bit 3 (if data type):
 0 = no scaling
 1 = scaling (indicates presence of S field)
 Bit 4:
 0 = name present
 1 = name not present
 Bits 5-7:

TESTRAN (SYM) CARD FORMAT

If requested by the user, the assembler punches out symbolic information for TESTRAN concerning the assembled program. This output appears ahead of all loader text. The format of the card images for TESTRAN output is as follows:

2. Address (3 bytes) - displacement from base of control section
3. Symbol Name (0-8 bytes) - symbolic name of particular item

<u>Columns</u>	<u>Contents</u>
1	12-2-9 punch
2-4	SYM
5-10	Blank
11-12	Variable field count -- number of bytes of text in variable field (cc 17-72)
13-16	Blank
17-72	Variable field (see below)
73-76	Deck ID (from first TITLE card)
77-80	Card sequence number

The variable field (columns 17-72) contains up to 56 bytes of TESTRAN text. The items making the text are packed together, consequently only the last card may contain less than 56 bytes of text in the variable field. The formats of a text card and an individual text item are shown in Figure 8. The contents of the fields within an individual entry are as follows:

- NOTE: The following fields are only present for data-type items.
4. Data Type (1 byte) - contents in hexadecimal
 - 00 = character
 - 04 = hexadecimal
 - 08 = binary
 - 10 = fixed point, full
 - 14 = fixed point, half
 - 18 = floating point, short
 - 1C = floating point, long
 - 20 = A-type or Q-type data
 - 24 = Y-type data
 - 28 = S-type data
 - 2C = V-type data
 - 30 = packed decimal
 - 34 = zoned decimal
 - 38 = L-type data
 5. Length (2 bytes for character, hexadecimal, or binary items; 1 byte for other types) - length of data item minus 1
 6. Multiplicity - M field (3 bytes) - equals 1 if not present
 7. Scale - signed integer - S field (2 bytes) - present only for F, H, E, D, P and Z type data, and only if scale is non-zero.

1. Organization (1 byte)
 - Bit 0:
 0 = non-data type
 1 = data type
 - Bits 1-3 (if non-data type):
 000 = space
 001 = control section




Figure 8. TESTRAN SYM Card Format

⑦
EXAM

⑨
PAGE 1

⑩
LOC

⑪
OBJECT CODE

⑫
ADDR1 ADDR2

⑬
STMT

⑭
SOURCE STATEMENT

⑮
F 14FEB66

⑯
4/11/66

1 ** THIS IS THE EXECUTABLE SAMPLE PROGRAM SHOWN IN THE SRL - *
2 ** ASSEMBLER LANGUAGE MANUAL. - *

10 LLC 11 OBJECT CODE 12 ADDR1 ADDR2 13 STMT 14 SOURCE STATEMENT

15 F 14FEB66 16 4/11/66

4	PRINT DATA	17	SAMPLO02
5 *			SAMPLO03
6 *	THIS IS THE MACRO DEFINITION		SAMPLO04
7 *			SAMPLO05
8	MACRO		SAMPLO06
9	MOVE &TO,&FROM		SAMPLO07
10 **			SAMPLO08
11 **	DEFINE SETC SYMBOL		SAMPLO09
12 **			SAMPLO10
13	LCLC &TYPE		SAMPLO11
14 **			SAMPLO12
15 **	CHECK NUMBER OF OPERANDS		SAMPLO13
16 **			SAMPLO14
17	AIF (N'&SYSLIST NE 2).ERROR1		SAMPLO15
18 **			SAMPLO16
19 **	CHECK TYPE ATTRIBUTES OF OPERANDS		SAMPLO17
20 **			SAMPLO18
21	AIF (T'&TO NE T'&FROM).ERROR2		SAMPLO19
22	AIF (T'&TO EQ 'C' OR T'&TO EQ 'G' OR T'&TO EQ 'K').TYPECGK		SAMPLO20
23	AIF (T'&TO EQ 'D' OR T'&TO EQ 'E' OR T'&TO EQ 'H').TYPEDEH		SAMPLO21
24	AIF (T'&TO EQ 'F').MOVE		SAMPLO22
25	AGO .ERROR3		SAMPLO23
26	.TYPEDEH ANOP		SAMPLO24
27 **			SAMPLO25
28 **	ASSIGN TYPE ATTRIBUTE TO SETC SYMBOL		SAMPLO26
29 **			SAMPLO27
30 &TYPE	SETC T'&TO		SAMPLO28
31 .MOVE	ANOP		SAMPLO29
32 *	NEXT TWO STATEMENTS GENERATED FOR MOVE MACRO		SAMPLO30
33	L&TYPE 2,&FROM		SAMPLO31
34	ST&TYPE 2,&TO		SAMPLO32
35	MEXIT		SAMPLO33
36 **			SAMPLO34
37 **	CHECK LENGTH ATTRIBUTES OF OPERANDS		SAMPLO35
38 **			SAMPLO36
39 .TYPECGK	AIF (L'&TO NE L'&FROM OR L'&TO GT 256).ERROR4		SAMPLO37
40 *	NEXT STATEMENT GENERATED FOR MOVE MACRO		SAMPLO38
41	MVC &TO,&FROM		SAMPLO39
42	MEXIT		SAMPLO40
43 **			SAMPLO41
44 **	ERROR MESSAGES FOR INVALID MOVE MACRO INSTRUCTIONS		SAMPLO42
45 **			SAMPLO43
46 .ERROR1	MNOTE 1,'IMPROPER NUMBER OF OPERANDS, NO STATEMENTS GENERATED'		SAMPLO44
47	MEXIT		SAMPLO45
48 .ERROR2	MNOTE 1,'OPERAND TYPES DIFFERENT, NO STATEMENTS GENERATED'		SAMPLO46
49	MEXIT		SAMPLO47
50 .ERROR3	MNOTE 1,'IMPROPER OPERAND TYPES, NO STATEMENTS GENERATED'		SAMPLO48
51	MEXIT		SAMPLO49
52 .ERROR4	MNOTE 1,'IMPROPER OPERAND LENGTHS, NO STATEMENTS GENERATED'		SAMPLO50
53	MEND		SAMPLO51
54 *			SAMPLO52
55 *	MAIN ROUTINE		SAMPLO53
56 *			SAMPLO54
57 SAMPLR	CSECT		SAMPLO55
58 BEGIN	SAVE (14,12),,*		SAMPLO56

000000

10 LUC 11 OBJECT CODE 12 ADDR1 ADDR2 13 STMT 14 SOURCE STATEMENT

15 F 14FEB66 16 4/11/66

0000AC	40E4D5E2E4C3C3C5									
0000B4	E2E2C6E4D3									
0000B9				108+1H80007	EQU	*				
0000BA				109+1H80007A	DS	OH				
0000BA	0A23			110+	SVC	35	ISSUE SVC			17
0000BC	47F0 C06E		0007E	111	B		EXIT			SAMPL079
0000C0	9680 5008		00008	112	NOTTHERE	DI	LSWITCH,NONE	TURN ON SWITCH IN LIST ENTRY		SAMPL080
0000C4	47F0 C028		00038	113	B		LISTLOOP	GO BACK AND LOOP		SAMPL081
0000C8	00000000			114	SAVE13	DC	F'0'			SAMPL082
0000CC	00			115	SWITCH	DC	X'00'			SAMPL083
000080				116	NONE	EQU	X'80'			SAMPL084
				117	*					SAMPL085
				118	*		BINARY SEARCH ROUTINE			SAMPL086
				119	*					SAMPL087
0000C0	00			120	SEARCH	NI	SWITCH,255-NONE	TURN OFF NOT FOUND SWITCH		SAMPL088
0000CE	947F C08C		000CC	121	LM	R1,R3,=F'128,4,128'		LOAD TABLE PARAMETERS		SAMPL089
0000D2	9813 C39C		003AC	122	LA	R1,TABLAREA-16(R1)		GET ADDRESS OF MIDDLE ENTRY		SAMPL090
0000D6	4111 C0E0		000F0	123	LOOP	SRL	R3,1	DIVIDE INCREMENT BY 2		SAMPL091
0000DA	8630 0001		00001	124	CLC	LNAME,TNAME		COMPARE LIST ENTRY WITH TABLE ENTRY		SAMPL092
0000DE	D507 5000	1008	00000	125	BH	HIGHER		BRANCH IF SHOULD BE HIGHER IN TABLE		SAMPL093
0000E4	4720 C0E4		000F4	126	BCR	8,R14		EXIT IF FOUND		SAMPL094
0000E8	078E			127	SR	R1,R3		OTHERWISE IT IS LOWER IN THE TABLE		X SAMPL095
								SO SUBTRACT INCREMENT		SAMPL096
0000EA	1B13			128	BCT	R2,LOOP		LOOP 4 TIMES		SAMPL097
0000EC	4620 C0CA		000DA	129	B	NOTFOUND		ARGUMENT IS NOT IN THE TABLE		SAMPL098
0000F0	47F0 C0EA		000FA	130	HIGHER	AR	R1,R3	ADD INCREMENT		SAMPL099
0000F4	1A13			131	BCT	R2,LOOP		LOOP 4 TIMES		SAMPL100
0000F6	462C C0CA		000DA	132	NOTFOUND	DI	SWITCH,NONE	TURN ON NOT FOUND SWITCH		SAMPL101
0000FA	9680 C08C		000CC	133	BR	R14		EXIT		SAMPL102
0000FE	07FE			134	*					SAMPL103
				135	*		THIS IS THE TABLE			SAMPL104
				136	*					SAMPL105
000100				137	DS	OD				SAMPL106
000100	0000000000000000			138	TABLAREA	DC	XL8'0',CL8'ALPHA'			SAMPL107
000108	C1D3D7C8C1404040			139	DC	XL8'0',CL8'BETA'				SAMPL108
000110	0000000000000000			140	DC	XL8'0',CL8'DELTA'				SAMPL109
000118	C2L5E3C140404040			141	DC	XL8'0',CL8'EPSILON'				SAMPL110
000120	8000000000000000			142	DC	XL8'0',CL8'ETA'				SAMPL111
000128	C4L5D3E3C1404040			143	DC	XL8'0',CL8'GAMMA'				SAMPL112
000130	0000000000000000			144	DC	XL8'0',CL8'IOTA'				SAMPL113
000138	C5D7E2C9D3D6D540			145	DC	XL8'0',CL8'KAPPA'				SAMPL114
000140	0000000000000000			146	DC	XL8'0',CL8'LAMBDA'				SAMPL115
000148	C5E3C14040404040			147	DC	XL8'0',CL8'MU'				SAMPL116
000150	0000000000000000			148	DC	XL8'0',CL8'NU'				SAMPL117
000158	C7C1D4D4C1404040									
000160	0000000000000000									
000168	C9D6E3C140404040									
000170	0000000000000000									
000178	D2C1D7D7C1404040									
000180	0000000000000000									
000188	D3C1D4C2C4C14040									
000190	0000000000000000									
000198	D4E4404040404040									
0001A0	0000000000000000									

(7) EXAM	(8) SAMPLE PROGRAM	(9) PAGE	5				
(10) LGC	(11) OBJECT CODE	(12) ADDR1	(13) ADDR2	(14) STMT	(15) SOURCE STATEMENT	(16) F 14FEB66	(17) 4/11/66
0001A8	D5E4404040404040						(17)
0001B0	0000000000000000			149	DC XL8'O',CL8'OMICRON'		SAMPL118
0001B8	D6D4C9C3D9D6D540						
0001C0	0000000000000000			150	DC XL8'O',CL8'PHI'		SAMPL119
0001C8	D7C8C94040404040						
0001D0	0000000000000000			151	DC XL8'O',CL8'SIGMA'		SAMPL120
0001D8	E2C9C7D4C1404040						
0001E0	0000000000000000			152	DC XL8'O',CL8'ZETA'		SAMPL121
0001E8	E9C5E3C140404040						
				153 *			SAMPL122
				154 *	THIS IS THE LIST		SAMPL123
				155 *			SAMPL124
0001F0	D3C1D4C2C4C14040			156	LISTAREA DC CL8'LAMBDA',X'0A',FL3'29',A(BEGIN)		SAMPL125
0001F8	0A00001D00000000						
000200	E9C5E3C140404040			157	DC CL8'ZETA',X'05',FL3'5',A(LOOP)		SAMPL126
000208	05000005000000DA						
000210	E3C8C5E3C1404040			158	DC CL8'THETA',X'02',FL3'45',A(BEGIN)		SAMPL127
000218	0200002D00000000						
000220	E3C1E44040404040			159	DC CL8'TAU',X'00',FL3'0',A(1)		SAMPL128
000228	0C00000000000001						
000230	D3C9E2E340404040			160	DC CL8'LIST',X'1F',FL3'465',A(0)		SAMPL129
000238	1F00C1D100000000						
000240	C1D3D7C8C1404040			161	LISTEND DC CL8'ALPHA',X'00',FL3'1',A(123)		SAMPL130
000248	0000001000000078						
				162 *			SAMPL131
				163 *	THIS IS THE CONTROL TABLE		SAMPL132
				164 *			SAMPL133
000250	0000010000000078			165	DS OD		SAMPL134
000258	C1D3D7C8C1404040			166	TESTTABL DC FL3'1',X'00',A(123),CL8'ALPHA'		SAMPL135
000260	0000000000000000						
000268	C2C5E3C140404040			167	DC XL8'O',CL8'BETA'		SAMPL136
000270	0000000000000000						
000278	C4C5D3E3C1404040			168	DC XL8'O',CL8'DELTA'		SAMPL137
000280	0C00000000000000						
000288	E5D7E2C9D3D6D540			169	DC XL8'O',CL8'EPSILON'		SAMPL138
000290	0000000000000000						
000298	C5E3C14040404040			170	DC XL8'O',CL8'ETA'		SAMPL139
0002A0	0000000000000000						
0002A8	C7C1D4D4C1404040			171	DC XL8'O',CL8'GAMMA'		SAMPL140
0002B0	0C00000000000000						
0002B8	C9D6E3C140404040			172	DC XL8'O',CL8'IOTA'		SAMPL141
0002C0	0000000000000000						
0002C8	D2C1D7D7C1404040			173	DC XL8'O',CL8'KAPPA'		SAMPL142
0002D0	0000100A00000000						
0002D8	D3C1D4C2C4C14040			174	DC FL3'29',X'0A',A(BEGIN),CL8'LAMBDA'		SAMPL143
0002E0	0000000000000000						
0002E8	D4E4404040404040			175	DC XL8'O',CL8'MU'		SAMPL144
0002F0	0000000000000000						
0002F8	D5E4404040404040			176	DC XL8'O',CL8'NU'		SAMPL145
000300	0000000000000000						
000308	D6D4C9C3D9D6D540			177	DC XL8'O',CL8'OMICRON'		SAMPL146
000310	0G00000000000000						
000318	D7C8C94040404040			178	DC XL8'O',CL8'PHI'		SAMPL147
000320	0000000000000000						
				179	DC XL8'O',CL8'SIGMA'		SAMPL148

(7)	(8)	(9)					
EXAM	SAMPLE PRUGRAM	PAGE 6					
(10)	(11)	(12)	(13)	(14)	(15)	(16)	(17)
LUC	OBJECT CODE	ADDR1	ADDR2	STMT	SOURCE STATEMENT	F 14FEB66	4/11/66
000328	E2C9C7D4C1404040			180	DC FL3'5',X'05',A(LOOP),CL8'ZETA'		
000330	000005G50000000A						
000338	E9C5E3C140404040						
				181 *			SAMPL149
				182 *	THIS IS THE CONTROL LIST		SAMPL150
				183 *			SAMPL151
000340	D3C104C2C4C14040			184	TESTLIST DC CL8'LAMBDA',X'0A',FL3'29',A(BEGIN)		SAMPL152
000348	0A000C1D00000000						SAMPL153
000350	E9C5E3C140404040			185	DC CL8'ZETA',X'05',FL3'5',A(LOOP)		SAMPL154
000358	050000050000000A						
000360	E3C8C5E3C1404040			186	DC CL8'THETA',X'82',FL3'45',A(BEGIN)		SAMPL155
000368	82000C2D00000000						
000370	E3C1E4404C404040			187	DC CL8'TAU',X'80',FL3'0',A(1)		SAMPL156
000378	8C00000000000001						
000380	D3C9E2E340404040			188	DC CL8'LIST',X'9F',FL3'465',A(10)		SAMPL157
000388	9F0001D100000000						
000390	C1D3D7C8C1404040			189	DC CL8'ALPHA',X'00',FL3'1',A(123)		SAMPL158
000398	00000010000007B						
				190 *			SAMPL159
				191 *	THESE ARE THE SYMBOLIC REGISTERS		SAMPL160
				192 *			SAMPL161
000000				193 R0	EQU 0		SAMPL162
000001				194 R1	EQU 1		SAMPL163
000002				195 R2	EQU 2		SAMPL164
000003				196 R3	EQU 3		SAMPL165
000005				197 R5	EQU 5		SAMPL166
000006				198 R6	EQU 6		SAMPL167
000007				199 R7	EQU 7		SAMPL168
00000C				200 R12	EQU 12		SAMPL169
00000D				201 R13	EQU 13		SAMPL170
00000E				202 R14	EQU 14		SAMPL171
00000F				203 R15	EQU 15		SAMPL172
				204 *			SAMPL173
				205 *	THIS IS THE FORMAT DEFINITION OF LIST ENTRIES		SAMPL174
				206 *			SAMPL175
000000				207 LIST	DSECT		SAMPL176
000000				208 LNAME	DS CL8		SAMPL177
000008				209 LSWITCH	DS C		SAMPL178
000009				210 LNUMBER	DS FL3		SAMPL179
00000C				211 LADDRESS	DS F		SAMPL180
				212 *			SAMPL181
				213 *	THIS IS THE FORMAT DEFINITION OF TABLE ENTRIES		SAMPL182
				214 *			SAMPL183
000000				215 TABLE	DSECT		SAMPL184
000000				216 TNUMBER	DS FL3		SAMPL185
000003				217 TSWITCH	DS C		SAMPL186
000004				218 TADDRESS	DS F		SAMPL187
000008				219 TNAME	DS CL8		SAMPL188
000000				220	END BEGIN		SAMPL189
0003A0							
0003A0							
0003A0	000001F0			221	=A(1,LISTAREA,16,LISTEND)		
0003A4	000008000000004			222	=F'128,4,128'		
0003AC	0000080						

⑦
EXAM

RELOCATION DICTIONARY

⑨
PAGE 1
⑩
4/11/66

⑧ PUS.ID	⑨ REL.ID	⑩ FLAGS	⑪ ADDRESS
01	01	0C	0001FC
01	01	0C	00020C
01	01	0C	00021C
01	01	0C	000204
01	01	0C	000334
01	01	0C	00034C
01	01	0C	00035C
01	01	0C	00036C
01	01	0C	0003A0

7
EXAM

CROSS-REFERENCE

9
PAGE 1
16
4/11/66

(22) SYMBLL	(23) LEN	(24) VALUE	(25) DEFN	(26) REFERENCES
BEGIN	00004	000000	0059	0156 0158 0174 0184 0186 0220
EXIT	00004	00007E	0096	0111
HIGHER	00002	000CF4	0130	0125
IMB0005	00001	00007B	0093	0090
IMB0005A	00002	00007C	0094	0089
IMB0007	00001	0000B9	0108	0105
IMB0007A	00002	0000BA	0109	0104
LADDRESS	00004	00000C	0211	0080
LIST	00001	000000	0207	0067
LISTAREA	00008	0001F0	0156	0066 0065 0221
LISTENU	00008	000240	0161	0066 0221
LISTLOOP	00004	000038	0082	0113
LNAME	00008	000000	0208	0124
LNUMBER	00003	000009	0210	0077
LOOP	00004	0000DA	0123	0128 0131 0157 0180 0185
LSWITCH	00001	000008	0209	0074 0112
MORE	00004	000018	0068	0082
NONE	00001	000080	0116	0069 0112 0120 0132
NOTFOUND	00004	0000FA	0132	0129
NULRIGHT	00004	00008C	0104	0084 0086
NUTHERE	00004	0000C0	0112	0070
R0	00001	000000	0193	
R1	00001	000001	0194	0071 0121 0122 0122 0127 0130
R12	00001	00000C	0200	0063 0064
R13	00001	00000D	0201	0096
R14	00001	00000E	0202	0068 0126 0133
R15	00001	00000F	0203	
R2	00001	000002	0195	0128 0131
R3	00001	000003	0196	0121 0123 0127 0130
R5	00001	000005	0197	0066 0067 0082
R6	00001	000006	0198	0082
R7	00001	000007	0199	0066
SAMPLR	00001	000000	0057	0220
SAVE13	00004	0000C8	0114	0065 0096
SEAKCH	00004	0000CE	0120	0068
SWITCH	00001	0000CC	0115	0069 0120 0132
TABLAREA	00008	000100	0138	0083 0122
TABLE	00001	000000	0215	0071
TADDRESS	00004	000004	0218	0081
TESTLIST	00008	000340	0184	0085
TESTTABL	00003	000250	0166	0083
TNAME	00008	000008	0219	0124
TNUMBER	00003	000000	0216	0077
TSWITCH	00001	0000C3	0217	0074

NO STATEMENTS FLAGGED IN THIS ASSEMBLY
 STATISTICS SOURCE RECORDS (SYSIN) = 225 SOURCE RECORDS (SYSLIB) = 40
 OPTIONS IN EFFECT LIST, NODECK, NULOAD, NJREVT, XREF, NUTEST, ALGN, US, LINECNT = 58
 351 PRINTED LINES

APPENDIX D. DYNAMIC INVOCATION OF THE ASSEMBLER

The Assembler can be invoked by a problem program at execution time through the use of the CALL, LINK, XCTL, or ATTACH macro instructions. If the XCTL macro instruction is used to invoke the Assembler, then no user options may be stated. The Assembler will use the standard default, as set during system generation, for each option.

If the Assembler is invoked by CALL, LINK, or ATTACH, the user may supply:

- 1) The Assembler options
- 2) The ddnames of the data sets to be used during processing

Name	Operation	Operand
[symbol]	CALL	IEUASM, (optionlist [,ddnamelist]), VL
	{ LINK ATTACH }	EP=IEUASM, PARAM=(optionlist [,ddnamelist]), VL=1

EP - specifies the symbolic name of the Assembler. The entry point at which execution is to begin is determined by the control program (from the library directory entry).

PARAM - specifies, as a sublist, address parameters to be passed from the problem program to the Assembler. The first word in the address parameter list contains the address of the option list. The second word contains the address of the ddname list.

optionlist - specifies the address of a variable length list containing the options. This address must be written even if no option list is provided.

The option list must begin on a halfword boundary. The first two bytes contain a count of the number of bytes in the remainder of the list. If no options are specified, the count must be zero. The option list is free form with each field separated by a comma. No blanks or zeros should appear in the list.

ddnamelist - specifies the address of a variable length list containing alternate ddnames for the data sets used during compiler processing. If standard ddnames are used then this operand may be omitted.

The ddname list must begin on a halfword boundary. The first two bytes contain a count of the number of bytes in the remainder of the list. Each name of less than eight bytes must be left-justified and padded with blanks. If an alternate ddname is omitted, the standard name will be assumed. If the name is omitted within the list, the 8-byte entry must contain binary zeros. Names can be omitted from the end merely by shortening the list. The sequence of the 8-byte entries in the ddname list is as follows:

Entry	Alternate Name
1	not applicable
2	not applicable
3	not applicable
4	SYSLIB
5	SYSIN
6	SYSPRINT
7	SYSPUNCH
8	SYSUT1
9	SYSUT2
10	SYSUT3
11	SYSGO

VL - specifies that the sign bit is to be set to 1 in the last word of the address parameter list.

This page intentionally left blank.

INDEX

Indexes to systems reference library manuals are consolidated in the publication IBM System/360 Operating System Systems Reference Library Master Index, Order No. GC28-6644. For additional information about any subject listed below, refer to other publications listed for the same subject in the Master Index.

Access methods	3	Diagnostics	
BPAM (basic partitioned)	3	listing	15
BSAM (basic sequential)	3	messages	25-33
QSAM (queued sequential)	3	Dictionaries	18-20
ASMFC, cataloged procedure for assembly	6	additional requirements	20
ASMFCG, cataloged procedure for assembly and loader-execution	9	global	18-20
ASMFCL, cataloged procedure for assembly and linkage editing	7	local	18-20
ASMFLG, cataloged procedure for assembly, linkage editing, and execution	8	overflow errors	20
Assembler cataloged procedures	6	Dictionary size and source statement complexity	17
Assembler data sets	2	Dynamic invocation of the assembler (Appendix D)	47
Assembler dynamic invocation	47	END card format	35
Assembler listing	11	ESD card format	35
(see also program listing)		EXEC statements	9
cross reference	14	External Symbol Dictionary (ESD)	
diagnostics	15	listing	11
external symbol dictionary	11	Global dictionary	
relocation dictionary	14	at collection time	19
source and object program	13	at generation time	19
statistical messages	11	IEBUPDAT utility program	17
Assembler options	2	Job control statements	1
default entry	2	Job steps	1
Assembler portion limitations	21	Linkage statements (Figure 5)	18
Blocking and buffering information	5	Listing, assembler	11
BPAM (Basic Partitioned Access Method)	3	Load module modification - entry point restatement	17
BSAM (Basic Sequential Access Method)	3	Loader-execution, ASMFCL cataloged procedure	9
Cataloged procedures	6	Local dictionary	
for assembling (ASMFC)	6	at collection time	19
for assembling and linkage editing (ASMFCL)	7	at generation time	20
for assembling, linkage editing, and execution (ASMFLG)	8	Macro-definition library additions	16
for assembling and loader-execution (ASMFCG)	9	Macro-definition local definition parameter table (Table 9)	20
overriding	9	Macro generation and conditional assembly limitations	21
COND= parameter	5, 7-9	Messages	
Cross reference listing	14	diagnostic	25-33
Data support of unaligned	23	statistical	11
Data constants, Type L	23	Model 85 Programming Considerations	22,23
Data sets	2-5	extended precision machine instructions	22
SYSGO	2,3	OPSYN instruction	22
SYSIN	2,3	Type L constant	23
SYSLIB	2,3	unaligned data	23
SYSPRINT	2,3	Model 91 Programming Considerations	21
SYSPUNCH	2,3	Model 195 Programming Considerations	23
SYSUT1, SYSUT2, SYSUT3	2,3	Object deck output	35-38
DCB macro instruction	3	END card	35
DD statements	9	ESD card	35
ddnames	3		
Default entry	2		
Defining data set characteristics	3		
Device naming conventions (Table 3)	6		

Object deck output (<u>continued</u>)		Sample program listing	38-46
RLD card	35	Saving and restoring general register	
TESTRAN SYM card	36	contents	16
TEXT (TXT) card	35	Severity code	
Object module linkage	17	for diagnostic messages	25-33
OPSYN - operation code equate		relation to return code	5
instruction	22	Source and object program	
Options, assembler	2	listing	13
default entry	2	Source statement complexity	21
Overflow		SPACE assembler instruction	11
dictionary	20	Statistical messages	11
symbol table	21	Symbol table, overflow	21
Overriding statements in cataloged		SYSGO	3
procedures	9	SYSIN	2,3
		SYSLIB	2,3
PARM field access	16	SYSPRINT	2,3
PARM parameter	2,9	SYSPUNCH	2,3
Procedure (definition)	1	SYSUT1,2,3	2,3
Program listing, assembler F	38-46		
Program termination	16	TESTRAN (SYM) Card format	36
		TEXT (TXT) card format	35
		Type designators	11
QSAM (Queued Sequential Access Method)	3	Type L data constants	23
		Types of ESD entries (Table 4)	11
Relocation Dictionary listing	14		
Return codes	5	Unaligned data, support of	23
RLD card format	31	Utility data sets	2,3

This page intentionally left blank.



International Business Machines Corporation
Data Processing Division
112 East Post Road, White Plains, N. Y. 10601
[USA Only]

IBM World Trade Corporation
821 United Nations Plaza, New York, New York 10017
[International]

READER'S COMMENT FORM

IBM System/360 Operating System
Assembler [F] Programmer's Guide

GC26-3756-4

- Your comments, accompanied by answers to the following questions, help us produce better publications for your use. If your answer to a question is "No" or requires qualification, please explain in the space provided below. Comments and suggestions become the property of IBM.

- | | Yes | No |
|--|--------------------------|--------------------------|
| • Does this publication meet your needs? | <input type="checkbox"/> | <input type="checkbox"/> |
| • Did you find the material: | | |
| Easy to read and understand? | <input type="checkbox"/> | <input type="checkbox"/> |
| Organized for convenient use? | <input type="checkbox"/> | <input type="checkbox"/> |
| Complete? | <input type="checkbox"/> | <input type="checkbox"/> |
| Well illustrated? | <input type="checkbox"/> | <input type="checkbox"/> |
| Written for your technical level? | <input type="checkbox"/> | <input type="checkbox"/> |
- What is your occupation? _____
 - How do you use this publication?

As an introduction to the subject?	<input type="checkbox"/>	As an instructor in a class?	<input type="checkbox"/>
For advanced knowledge of the subject?	<input type="checkbox"/>	As a student in a class?	<input type="checkbox"/>
For information about operating procedures?	<input type="checkbox"/>	As a reference manual?	<input type="checkbox"/>

Other _____

- Please give specific page and line references with your comments when appropriate.

COMMENTS

- Thank you for your cooperation. No postage necessary if mailed in the U.S.A.

YOUR COMMENTS, PLEASE...

This publication is one of a series which serves as reference sources for systems analysts, programmers and operators of IBM systems. Your answers to the questions on the back of this form together with your comments, will help us produce better publications for your use. Each reply will be carefully reviewed by the persons responsible for writing and publishing this material. All comments and suggestions become the property of IBM.

Please note: Requests for copies of publications and for assistance in utilizing your IBM system should be directed to your IBM representative or to the IBM sales office serving your locality.

fold


fold

FIRST CLASS
PERMIT NO. 2078
SAN JOSE, CALIF.

BUSINESS REPLY MAIL
NO POSTAGE STAMP NECESSARY IF MAILED IN U. S. A.

POSTAGE WILL BE PAID BY . . .

IBM Corporation
112 East Post Road
White Plains, N. Y. 10601



Attention: Dept. 813

fold

fold



International Business Machines Corporation
Data Processing Division
112 East Post Road, White Plains, N. Y. 10601
[USA Only]

IBM World Trade Corporation
821 United Nations Plaza, New York, New York 10017
[International]