


```

XX      XX  LL      AAAAAA  TTTTTTTTTT  EEEEEEEEEE
XX      XX  LL      AAAAAA  TTTTTTTTTT  EEEEEEEEEE
XX      XX  LL      AA        AA        TT        EE
XX      XX  LL      AA        AA        TT        EE
  XX    XX  LL      AA        AA        TT        EE
  XX    XX  LL      AA        AA        TT        EE
    XX  XX  LL      AA        AA        TT        EEEEEEEEE
    XX  XX  LL      AA        AA        TT        EEEEEEEEE
  XX    XX  LL      AAAAAAAAAA  TT        EE
  XX    XX  LL      AAAAAAAAAA  TT        EE
XX      XX  LL      AA        AA        TT        EE
XX      XX  LL      AA        AA        TT        EE
XX      XX  LLLLLLLLLL  AA        AA        TT        EEEEEEEEEE
XX      XX  LLLLLLLLLL  AA        AA        TT        EEEEEEEEEE

```

```

LL      IIIIII  SSSSSSSS
LL      IIIIII  SSSSSSSS
LL      II     SS
LL      II     SS
LL      II     SS
LL      II     SS
LL      II     SSSSSS
LL      II     SSSSSS
LL      II     SS
LL      II     SS
LL      II     SS
LL      II     SS
LLLLLLLL  IIIIII  SSSSSSSS
LLLLLLLL  IIIIII  SSSSSSSS

```

```

1 0001 0 %TITLE 'EDT$XLATE - Default XLATE routine'
2 0002 0 MODULE EDT$XLATE ( ! Default XLATE routine
3 0003 0 IDENT = 'V04-000' ! File: XLATE.B32 Edit: JBS1002
4 0004 0 ) =
5 0005 1 BEGIN
6 0006 1
7 0007 1 *****
8 0008 1 *
9 0009 1 * COPYRIGHT (c) 1978, 1980, 1982, 1984 BY *
10 0010 1 * DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS. *
11 0011 1 * ALL RIGHTS RESERVED. *
12 0012 1 *
13 0013 1 * THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED *
14 0014 1 * ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE *
15 0015 1 * INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER *
16 0016 1 * COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY *
17 0017 1 * OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY *
18 0018 1 * TRANSFERRED. *
19 0019 1 *
20 0020 1 * THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE *
21 0021 1 * AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT *
22 0022 1 * CORPORATION. *
23 0023 1 *
24 0024 1 * DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS *
25 0025 1 * SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL. *
26 0026 1 *
27 0027 1 *
28 0028 1 *****
29 0029 1
30 0030 1
31 0031 1 ++
32 0032 1 FACILITY: EDT -- The DEC Standard Editor
33 0033 1
34 0034 1 ABSTRACT:
35 0035 1
36 0036 1
37 0037 1 Default Xlate routine - simply returns the error code
38 0038 1 for invalid subcommand
39 0039 1
40 0040 1 ENVIRONMENT: Runs on Vax/Vms
41 0041 1
42 0042 1 AUTHOR: Shelly T. Solomon, CREATION DATE: 13-Aug-1982
43 0043 1
44 0044 1 MODIFIED BY:
45 0045 1
46 0046 1 1-001 - Original. STS 13-Aug-1982
47 0047 1 1-002 - Improve listing appearance. JBS 20-Jun-1983
48 0048 1 --
49 0049 1

```

EDT\$XLATE
V04-000

EDT\$XLATE - Default XLATE routine
Declarations

E 5
16-Sep-1984 02:20:59
14-Sep-1984 12:25:56

VAX-11 Bliss-32 V4.0-742
DISK\$VMSMASTER:[EDT.SRC]XLATE.B32;1 Page (2)

```

: 51 0050 1 %SBTTL 'Declarations'
: 52 0051 1
: 53 0052 1 | TABLE OF CONTENTS:
: 54 0053 1 |
: 55 0054 1 |
: 56 0055 1 FORWARD ROUTINE
: 57 0056 1 EDT$XLATE;
: 58 0057 1
: 59 0058 1 |
: 60 0059 1 | INCLUDE FILES:
: 61 0060 1 |
: 62 0061 1 |
: 63 0062 1 REQUIRE 'EDT$SRC:EDTREQ';
: 64 0197 1
: 65 0198 1 |
: 66 0199 1 | MACROS:
: 67 0200 1 |
: 68 0201 1 | NONE
: 69 0202 1 |
: 70 0203 1 | EQUATED SYMBOLS:
: 71 0204 1 |
: 72 0205 1 | NONE
: 73 0206 1 |
: 74 0207 1 | OWN STORAGE:
: 75 0208 1 |
: 76 0209 1 | NONE
: 77 0210 1 |
: 78 0211 1 | EXTERNAL REFERENCES:
: 79 0212 1 |
: 80 0213 1 | in the routine
: 81 0214 1 |

```

-\$2

LOA

EMU

EMU

LOA

EDT\$XLATE
V04-000

EDT\$XLATE - Default XLATE routine
EDT\$XLATE - default XLATE command

F 5
16-Sep-1984 02:20:59
14-Sep-1984 12:25:56

VAX-11 Bliss-32 V4.0-742
DISK\$VMSMASTER:[EDT.SRC]XLATE.B32;1

Page 3
(3)

```

: 83      0215 1 %SBTTL 'EDT$XLATE - default XLATE command'
: 84      0216 1
: 85      0217 1 GLOBAL ROUTINE EDT$XLATE (           ! Default XLATE command
: 86      0218 1     DESC                               ! String to be XLATED
: 87      0219 1     ) =
: 88      0220 1
: 89      0221 1 !++
: 90      0222 1 | FUNCTIONAL DESCRIPTION:
: 91      0223 1 |
: 92      0224 1 |     This routine is the default EDT XLATE routine. It is entered
: 93      0225 1 |     when the user has not supplied an XLATE routine. It simply
: 94      0226 1 |     returns the error code for invalid subcommand.
: 95      0227 1 |
: 96      0228 1 | FORMAL PARAMETERS:
: 97      0229 1 |
: 98      0230 1 |     DESC - Descriptor passed with xlate string (unused)
: 99      0231 1 |
: 100     0232 1 | IMPLICIT INPUTS:
: 101     0233 1 |
: 102     0234 1 |     NONE
: 103     0235 1 |
: 104     0236 1 | IMPLICIT OUTPUTS:
: 105     0237 1 |
: 106     0238 1 |     NONE
: 107     0239 1 |
: 108     0240 1 | COMPLETION STATUS:
: 109     0241 1 |
: 110     0242 1 |     EDT$_INVSUBCOM
: 111     0243 1 |
: 112     0244 1 | SIDE EFFECTS:
: 113     0245 1 |
: 114     0246 1 |     NONE
: 115     0247 1 |
: 116     0248 1 | --
: 117     0249 1 |
: 118     0250 2 BEGIN
: 119     0251 2 MESSAGES ((INVSUBCOM));
: 120     0252 2 RETURN (EDT$_INVSUBCOM);
: 121     0253 1 END;

```

! of routine EDT\$XLATE

```

.TITLE EDT$XLATE EDT$XLATE - Default XLATE routine
.IDENT \V04-000\
.EXTRN EDT$_INVSUBCOM
.PSECT _EDT$CODE,NOWRT, SHR, PIC,2
.ENTRY EDT$XLATE, Save nothing           : 0217
MOVL #EDT$_INVSUBCOM, R0                 : 0252
RET                                       : 0253

```

```

0000 00000
50 00000000G 8F D0 00002
04 00009

```

: Routine Size: 10 bytes, Routine Base: _EDT\$CODE + 0000

```

: 122     0254 1
: 123     0255 1 !<BLF/PAGE>

```

_\$2

Pse

\$\$\$

HAN

PC_

RES

_VA

_VA

_VA

EDT\$XLATE
V04-000

EDT\$XLATE - Default XLATE routine
EDT\$XLATE - default XLATE command

6 5
16-Sep-1984 02:20:59
14-Sep-1984 12:25:56

VAX-11 Bliss-32 V4.0-742
DISK\$VMSMASTER:[EDT.SRC]XLATE.B32;1

Page 4
(4)

: 125
: 126
: 127
0256 1 END
0257 1
0258 0 ELUDOM

! of module EDT\$XLATE

PSECT SUMMARY

Name	Bytes	Attributes
_EDT\$CODE	10	NOVEC,NOWRT, RD , EXE, SHR, LCL, REL, CON, PIC,ALIGN(2)

Library Statistics

File	Total	Symbols Loaded	Percent	Pages Mapped	Processing Time
_\$255\$DUA28:[EDT.SRC]EDT.L32;1	377	1	0	40	00:00.2
_\$255\$DUA28:[EDT.SRC]PSECTS.L32;1	2	1	50	7	00:00.1

COMMAND QUALIFIERS

BLISS/CHECK=(FIELD,INITIAL,OPTIMIZE)/NOTRACEBACK/LIS=LIS\$:XLATE/OBJ=OBJ\$:XLATE MSRC\$:XLATE.B32/UPDATE=(ENH\$:XLATE)

: Size: 10 code + 0 data bytes
: Run Time: 00:03.8
: Elapsed Time: 00:05.3
: Lines/CPU Min: 4106
: Lexemes/CPU-Min: 7607
: Memory Used: 15 pages
: Compilation Complete

