


```

EEEEEEEEEE XX XX CCCCCCCC MM MM SSSSSSSS GGGGGGGG
EEEEEEEEEE XX XX CCCCCCCC MM MM SSSSSSSS GGGGGGGG
EE XX XX CC MMMM MMMM SS GG
EE XX XX CC MMMM MMMM SS GG
EE XX XX CC MM MM SS GG
EE XX XX CC MM MM SS GG
EEEEEEEEEE XX XX CC MM MM SSSSSS GG
EEEEEEEEEE XX XX CC MM MM SSSSSS GG
EE XX XX CC MM MM SS GG GGGGGG
EE XX XX CC MM MM SS GG GGGGGG
EE XX XX CC MM MM SS GG GG
EEEEEEEEEE XX XX CCCCCCCC MM MM SSSSSSSS GGGGGG
EEEEEEEEEE XX XX CCCCCCCC MM MM SSSSSSSS GGGGGG

```

```

LL IIIIII SSSSSSSS
LL IIIIII SSSSSSSS
LL II SS
LL II SS
LL II SS
LL II SS
LL II SSSSSS
LL II SSSSSS
LL II SS
LL II SS
LL II SS
LL IIIIII SSSSSSSS
LLLLLLLLLLL IIIIII SSSSSSSS
LLLLLLLLLLL IIIIII SSSSSSSS

```

000008F8

```

1 .TITLE  exch$message
2 .IDENT  'V04-000'
3 .FACILITY  EXCHANGE,248 /PREFIX=EXCH$_
4
5
6 *****
7 *
8 *  COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
9 *  DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
10 *  ALL RIGHTS RESERVED.
11 *
12 *  THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
13 *  ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
14 *  INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
15 *  COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
16 *  OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
17 *  TRANSFERRED.
18 *
19 *  THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
20 *  AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
21 *  CORPORATION.
22 *
23 *  DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
24 *  SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
25 *
26 *
27 *****
28
29 ++
30 FACILITY:      EXCHANGE - Foreign volume interchange facility
31
32 ABSTRACT:      Error message definitions
33
34 ENVIRONMENT:   VAX/VMS User mode
35
36 AUTHOR:       CW Hobbs                CREATION DATE: 15-July-1982
37
38 MODIFIED BY:
39
40 V03-002  CWH3002      CW Hobbs      18-Mar-1984
41 Add EXCH$_NOREMOTE, EXCH$_NOTSAMEDEV and EXCH$_RT11_DIRSIZE
42 messages
43
44 --

```

```

45
46 .SEVERITY          FATAL
47
48 .SEVERITY          ERROR
49
08F8800A 50 BADLOGIC          <internal logic error detected, please report error !UL>/FAO_COUNT=1
08F88012 51 BLOCKCHECK        <block check, please report error !UL and the following:!/ address =
08F8801A 52 BLOCKCHECKO      <block check, please report error !UL>/FAO_COUNT=1
53
54 .SEVERITY          WARNING
55
08F88020 56 ACCESSFAIL       <access has failed for !AS>/FAO_COUNT=1
08F88028 57 BADFILENAME      <name !AS not suitable for !AF volume>/FAO_COUNT=3
08F88030 58 BADPAD           <bad format for PAD keyword on /RECORD FORMAT qualifier>
08F88038 59 BINCHKSUM        <a binary record failed checksum in !AF>/FAO_COUNT=2
08F88040 60 BINRECFMT       <an illegal binary record found in !AF>/FAO_COUNT=2
08F88048 61 CANCELED        <command was canceled by keyboard action>
08F88050 62 CLOSEERR        <an error occurred closing !AS>/FAO_COUNT=1
08F88058 63 CLOSEFOREIGN    <an error occurred closing the volume !AS>/FAO_COUNT=1
08F88060 64 CREATEVIRT      <error creating the virtual volume !AS>/FAO_COUNT=1
08F88068 65 DEVNOTSUIT      <the device !AS is not suitable for operations>/FAO_COUNT=1
08F88070 66 DIRE_ERROR      <above error occurred writing directory, volume might be corrupted>
08F88078 67 DOS11_BADLABEL  <volume on !AF has label with invalid format>/FAO_COUNT=2
08F88080 68 DOS11_BLOCKSIZE <volume on !AF has block larger than 512 bytes>/FAO_COUNT=2
08F88088 69 DOS11_IOERROR   <error during I/O on volume !AF>/FAO_COUNT=2
08F88090 70 FILENOTFOUND    <unable to locate file !AS>/FAO_COUNT=1
08F88098 71 ILLMTCOPY       <cannot specify same magtape for both input and output>
08F880A0 72 INVRECFMT       <record format specified inconsistent with volume format>
08F880A8 73 INVVOLFM        <volume format specified is not consistent with file spec>
08F880B0 74 MANY TO ONE     <input specifies multiple files, output a single file>
08F880B8 75 MOUNTERR        <error occurred during VMS mount on !AS>/FAO_COUNT=1
08F880C0 76 NOCOPBAD        <cannot create .BAD file with wildcard names>
08F880C8 77 NOCOPBADDEL     <cannot delete existing .BAD file>
08F880D0 78 NOCOPDUP        <already copied file with same output name in this command>
08F880D8 79 NOCOPLOCK       <cannot create files, volume !AF is write-locked>/FAO_COUNT=2
08F880E0 80 NOCOPNODEL      <file already exists and /NODELETE requested>
08F880E8 81 NOCOPPROT       <file with same name is protected against modification>
08F880F0 82 NOCOPSAMDEV     <illegal wildcard copy to same device>
08F880F8 83 NOCOPSYSDEL     <cannot delete existing .SYS file without /SYSTEM>
08F88100 84 NOCOPYBOOT      <unable to copy boot information>
08F88108 85 NODELLOCK       <file !AF not deleted, volume is write-locked>/FAO_COUNT=2
08F88110 86 NODEVICE        <missing or incorrect device name in !AS>/FAO_COUNT=1
08F88118 87 NOREMOTE        <remote node name not permitted in !AS>/FAO_COUNT=1
08F88120 88 NORENDEV        <cannot RENAME to a different device>
08F88128 89 NORENEXISTS     <file !AF not renamed, !AF already exists>/FAO_COUNT=4
08F88130 90 NORENLOCK       <file !AF not renamed, volume is write-locked>/FAO_COUNT=2
91 !\ NOTIMPLEMENT <feature not yet implemented, sorry>
08F88138 92 NOTMOUNTED      <volume !AS has not been mounted on EXCHANGE>/FAO_COUNT=1
08F88140 93 NOTSAMEDEV      <input and output must be same device for boot copy>
08F88148 94 OPENFOREIGN     <unable to open !AS as a foreign volume>/FAO_COUNT=1
08F88150 95 OPENVIRTUAL     <unable to open !AS as a virtual volume>/FAO_COUNT=1
08F88158 96 OPNOTPERDOS     <operation not permitted on DOS-11 volume !AS>/FAO_COUNT=1
08F88160 97 OPNOTPERF11    <operation not permitted on Files-11 volume !AS>/FAO_COUNT=1
98 !\ OPNOTPERRT11 <operation not permitted on RT-11 volume !AS>/FAO_COUNT=1
99 !\ OPNOTPERRTMT <operation not permitted on RT-11 tape volume !AS>/FAO_COUNT=1
08F88168 100 PARSEERR       <unable to parse input name !AS>/FAO_COUNT=1

```

HELP RECOVER command

08F88170	101	READCHECK	<read error detected during check on volume !AS>/FAO_COUNT=1
08F88178	102	RECOVER	<to save volume, follow procedure outlined by the
08F88180	103	RECTOOBIG	<record too large in !AF>/FAO_COUNT=2
08F88188	104	RT11_BADDIRECT	<volume !AF has invalid RT-11 directory>/FAO_COUNT=2
08F88190	105	RT11_DIRSIZE	<volume !AF has directory showing !UL blocks on a !UL block device>/FAO_COUN
08F88198	106	RT11_ERRLOCK	<volume will be write-locked to prevent corruption>
08F881A0	107	RT11_NOEND	<segment end marker is missing from RT-11 directory>
08F881A8	108	RT11_OVERFLOW	<directory is full, unable to add file>
08F881B0	109	RT11_STBLOCK	<file start block - segment header inconsistent>
08F881B8	110	RT11_UNKENT	<entry with unknown format in directory>
08F881C0	111	RTOUTEOF	<end-of-file on output !AF, insufficient space on volume>/FAO_COUNT=2
08F881C8	112	RTPROTECT	<file is protected against modification>
08F881D0	113	STMRECFMT	<illegal stream record format in !AF>/FAO_COUNT=2
08F881D8	114	STNOTAVAIL	<requested starting block number is not available>
08F881E0	115	STRTNOMULTI	<cannot request /START_BLOCK with multiple input files>
08F881E8	116	TOOMANYCOL	<too many columns, reduced number to fit listing width>
08F881F0	117	VOLMOUNT	<the volume !AS is already mounted>/FAO_COUNT=1
08F881F8	118	VOLUME FULL	<volume is full (insufficient space for the request)>
08F88200	119	WAITERR	<error waiting for RMS operation to complete>
08F88208	120	WRITECHECK	<write error detected during check on volume !AS>/FAO_COUNT=1
	121		
	122	.SEVERITY	INFORMATION
	123		
08F88213	124	DEVONLY	<using device name only, ignoring parts of !AS>/FAO_COUNT=1
08F88218	125	DOS11_POSITION	<rewinding tape to recover correct positioning>
08F88223	126	FIL11_NOREC	<ignoring /RECORD_FORMAT for Files-11 output>
08F88228	127	IGNORE_DIRE	<directory name ignored, not used for this volume type>
08F88233	128	IGNORE_VERS	<file version ignored, not used for this volume type>
08F88238	129	NOALLOC	<ignoring /ALLOCATION, not valid for output volume>
08F88243	130	NOCARRIAGE	<ignoring /CARRIAGE CONTROL, not valid for output volume>
08F88248	131	NOSYSACT	<no action on .SYS file(s)>
08F88253	132	NOTCOPIED	<file !AF not copied to !AF>/FAO COUNT=4
08F88258	133	NOTCOP_RETRY	<error copying !AF, will retry>/FAO_COUNT=2
08F88263	134	NOTDELETED	<file !AF not deleted>/FAO COUNT=2
08F88268	135	NOTVALLEN	<fixed record length of !UL is too large>/FAO_COUNT=1
08F88273	136	NOVOLUMES	<no volumes are currently mounted>
08F88278	137	PARTCOPIED	<file !AF partially copied to !AF, !UL !AS!XS>/FAO COUNT=6
08F88283	138	READCHECKREC	<read check error recovered on volume !AF>/FAO COUNT=2
08F88288	139	READERRREC	<read error recovered on volume !AF>/FAO_COUNT=2
08F88293	140	RT11_BADFILE	<bad block file created to cover bad block !UL>/FAO_COUNT=1
08F88298	141	RT11_BIGBADFILE	<directory segment full, file has some good blocks>
08F882A3	142	RT11_EXTRA	<extra words set to maximum of 119>
08F882AB	143	RT11_TOOMANYBLK	<too many blocks, using maximum allocation of !UL>/FAO_COUNT=1
08F882B3	144	RT11_TOOMANYSEG	<too many segments, reducing to !UL>/FAO_COUNT=1
08F882B8	145	TRACE	<status code is !XL>/FAO COUNT=1
08F882C3	146	VIRTNOCHANGE	<allocation of virtual device cannot be changed>
08F882CB	147	VMSMOUNT	<a '\$ MOUNT /FOREIGN !AS' command was done by Exchange>/FAO_COUNT=1
08F882D3	148	WRITECACHE	<writing directory cache for volume !AF>/FAO COUNT=2
08F882DB	149	WRITECHECKREC	<write check error recovered on volume !AF>/FAO COUNT=2
08F882E3	150	WRITEERRREC	<write error recovered on volume !AF>/FAO_COUNT=2
08F882EB	151	WRITELOCK	<volume !AF is write-locked>/FAO_COUNT=2
	152		
	153	.SEVERITY	SUCCESS
	154		
08F882F1	155	COPIED	<A/ copied to !AF, !UL !AS!XS>/FAO COUNT=6
08F882F9	156	COPYBOOT	<bootstrap data from !AF copied to !AF>/FAO COUNT=4
08F88301	157	COPNEWNAME	<!AF copied to !AF (new name), !UL !AS!XS>/FAO_COUNT=6

08F88309	158	DELETED	<file !AF deleted>/FAO COUNT=2	
08F88311	159	DELETEPREV	<previous copy of !AF deleted>/FAO COUNT=2	
08F88319	160	DISMOUNTED	<the !AF volume !AF has been dismounted>/FAO COUNT=4	
08F88321	161	INITIALIZED	<the !AF volume !AF has been initialized>/FAO COUNT=4	
08F88329	162	MOUNTED	<the !AF volume !AF has been mounted>/FAO COUNT=4	
08F88331	163	MOUNTVIR	<the RT-11 virtual volume !AF has been mounted!/ using the file !AF	
08F88339	164	RENAMED	<file !AF renamed to !AF>/FAO COUNT=4	
08F88341	165	TYPED	<file !AF typed, !UL record!%S>/FAO COUNT=3	
	166			
	167	.END		

There were 0 errors, 0 warnings, and 0 informational messages issued.
 MESSAGE/FILE_NAME=CLIUTLMSG/LIS=LIS:EXCMMSG/OBJ=OBJ\$:EXCMMSG MSRC\$:EXCMMSG

.....

This image displays a grid of 144 terminal windows, arranged in 12 rows and 12 columns. Each window contains text-based output from a system, likely related to the VAX/VMS operating system. The windows show various logs, including system boot sequences, error messages, and diagnostic information. Several windows are prominently labeled with the following titles:

- EXCMOUT LIS (bottom-left)
- EXCMOIN LIS (bottom-left)
- EXCPDP LIS (middle-bottom)
- EXCMSG LIS (middle)
- EXCRT11 LIS (top-right)

The text within the windows is dense and appears to be a mix of system status reports and error logs. Some windows show repetitive patterns of text, possibly indicating a loop or a specific type of diagnostic output. The overall appearance is that of a multi-user terminal session or a system-wide diagnostic display.