

[illegible][illegible]

```
FFFFFFFFF  AAAAAA  LL  RRRRRRRR  MM  MM  SSSSSSSS  DDDDDDDD  AAAAAA  PPPPPPPP
FFFFFFFFF  AAAAAA  LL  RRRRRRRR  MM  MM  SSSSSSSS  DDDDDDDD  AAAAAA  PPPPPPPP
FF  AA  AA  LL  RR  RR  MM  MM  SS  DD  DD  AA  AA  PP  PP
FF  AA  AA  LL  RR  RR  MM  MM  SS  DD  DD  AA  AA  PP  PP
FF  AA  AA  LL  RR  RR  MM  MM  SS  DD  DD  AA  AA  PP  PP
FF  AA  AA  LL  RR  RR  MM  MM  SS  DD  DD  AA  AA  PP  PP
FFFFFFFFF  AA  AA  LL  RRRRRRRR  MM  MM  SSSSSS  DD  DD  AA  AA  PPPPPPPP
FFFFFFFFF  AA  AA  LL  RRRRRRRR  MM  MM  SSSSSS  DD  DD  AA  AA  PPPPPPPP
FF  AAAAAAAAAA  LL  RR  RR  MM  MM  SS  DD  DD  AAAAAAAAAA  PP
FF  AAAAAAAAAA  LL  RR  RR  MM  MM  SS  DD  DD  AAAAAAAAAA  PP
FF  AA  AA  LL  RR  RR  MM  MM  SS  DD  DD  AA  AA  PP
FF  AA  AA  LL  RR  RR  MM  MM  SS  DD  DD  AA  AA  PP
FF  AA  AA  LL  RR  RR  MM  MM  SSSSSSSS  DDDDDDDD  AA  AA  PP
FF  AA  AA  LLLLLLLLLL  RR  RR  MM  MM  SSSSSSSS  DDDDDDDD  AA  AA  PP
FF  AA  AA  LLLLLLLLLL  RR  RR  MM  MM  SSSSSSSS  DDDDDDDD  AA  AA  PP

LL  I I I I I  SSSSSSSS
LL  I I I I I  SSSSSSSS
LL  I I  SS
LL  I I  SS
LL  I I  SS
LL  I I  SS
LL  I I  SSSSSS
LL  I I  SSSSSS
LL  I I  SS
LL  I I  SS
LL  I I  SS
LL  I I  SS
LL  I I  SS
LLLLLLLLLL  I I I I I  SSSSSSSS
LLLLLLLLLL  I I I I I  SSSSSSSS
```



(2) 63  
(3) 103

DECLARATIONS  
FAL\$ERROR\_TABLE - RMS TO DAP TABLE

```
0000 1      .TITLE  FALRMSDAP - RMS TO DAP ERROR CONVERSION
0000 2      .IDENT  'V04-000'
0000 3
0000 4
0000 5 *****
0000 6 *****
0000 7 *   COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
0000 8 *   DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
0000 9 *   ALL RIGHTS RESERVED.
0000 10
0000 11 *   THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
0000 12 *   ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
0000 13 *   INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
0000 14 *   COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
0000 15 *   OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
0000 16 *   TRANSFERRED.
0000 17
0000 18 *   THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
0000 19 *   AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
0000 20 *   CORPORATION.
0000 21
0000 22 *   DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
0000 23 *   SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
0000 24
0000 25 *****
0000 26 *****
0000 27
0000 28
0000 29 ++
0000 30 Facility: FAL (DECnet File Access Listener)
0000 31
0000 32 Abstract:
0000 33
0000 34 This module contains RMS completion codes and their corresponding
0000 35 DAP status codes.
0000 36
0000 37 Environment: VAX/VMS, user mode
0000 38
0000 39 Author: James A. Krycka,      Creation Date: 16-JUN-1977
0000 40
0000 41 Modified By:
0000 42
0000 43 V03-003 JEJ0045      J E Johnson      28-Jun-1984
0000 44 Eliminate the reference to the de-implemented
0000 45 RMS$_WSF error code.
0000 46
0000 47 V03-002 KRM0114      K Malik          08-Jun-1983
0000 48 Collapse CQE and COP into CJF.
0000 49
0000 50 V03-001 KRM0100      K Malik          04-May-1983
0000 51 Update to include new RMS/DAP error codes.
0000 52
0000 53 V02-012 JAK0028      J A Krycka      09-FEB-1982
0000 54 Update error codes to correspond to those defined in
0000 55 RMSDEF.MDL for VMS V3.0 field test 2.
0000 56
0000 57 V02-011 JAK0022      J A Krycka      25-AUG-1981
```



FALRMSDAP  
V04-000

- RMS TO DAP ERROR CONVERSION

J 13

16-SEP-1984 01:46:38 VAX/VMS Macro V04-00  
5-SEP-1984 01:17:24 [FAL.SRC]FALRMSDAP.MAR;1

Page 2  
(1)

0000 58 :  
0000 59 :  
0000 60 :  
0000 61 :--

Update error codes to correspond to those defined in  
RMSDEF.MDL for VMS V3.0 field test 1.

```
0000 63      .SBTTL  DECLARATIONS
0000 64
0000 65 :
0000 66 : Include Files:
0000 67 :
0000 68
0000 69      $RMSDEF                      ; Define RMS completion codes
0000 70
0000 71 :
0000 72 : Macros:
0000 73 :
0000 74
0000 75 :++
0000 76 : RMSDAP defines an entry in the RMS-to-DAP status code conversion table.
0000 77 : To conserve space, the two byte facility code portion of each RMS
0000 78 : completion code is overlaid by the corresponding DAP status code.
0000 79 :--
0000 80
0000 81      .MACRO  RMSDAP,RMSERR,DAPERR
0000 82      .LONG   <DAPERR@16>+<RMS$_RMSERR&^XFFFF>
0000 83      .ENDM   RMSDAP
0000 84
0000 85 :++
0000 86 : RMSDAPEND signals the end of the conversion table.
0000 87 :--
0000 88
0000 89      .MACRO  RMSDAPEND
0000 90      .LONG   0
0000 91      .ENDM   RMSDAPEND
0000 92
0000 93 :
0000 94 : Equated Symbols:
0000 95 :
0000 96 :      None
0000 97 :
0000 98 : Own Storage:
0000 99 :
0000 100 :      None
0000 101 :
```

```
0000 103 .SBTTL FAL$ERROR_TABLE - RMS TO DAP TABLE
00000000 104 .PSECT FAL$ERROR_TABLE SHR,NOEXE,RD,NOWRT,LONG
0000 105
0000 106 :++
0000 107 : Note: the definition of the symbolic RMS completion codes are documented
0000 108 : in the RMS-32 specification and in the VMS manual set; therefore, the
0000 109 : explanations will not be duplicated here.
0000 110 :--
0000 111
0000 112 FAL$RMS_TO_DAP:: ; Start of conversion table
0000 113
0000 114 :+
0000 115 : RMS-32 success completion codes:
0000 116 : (low order 3 bits = 001)
0000 117 :-
0000 118
0000 119 RMSDAP SUC,149
0004 120 RMSDAP NORMAL,135
0008 121 RMSDAP PENDING,142
000C 122 RMSDAP OK_DUP,136
0010 123 RMSDAP OK_IDX,137
0014 124 RMSDAP OK_RLK,138
0018 125 RMSDAP OK_RRL,139
001C 126 RMSDAP KFF,132
0020 127 RMSDAP OK_ALK,215
0024 128 RMSDAP OK_DEL,216
0028 129 RMSDAP OK_RNF,219
002C 130 RMSDAP OK_LIM,217
0030 131 RMSDAP OK_NOP,218
0034 132 RMSDAP OK_WAT,225
0038 133 RMSDAP CRE_STM,247
003C 134 RMSDAP CONTROLC,203
0040 135 RMSDAP CONTROL0,124
0044 136 RMSDAP CONTROLY,125
0048 137 RMSDAP CREATED,140
004C 138 RMSDAP SUPERSEDE,150
0050 139 RMSDAP OK_RULK,259
0054 140 RMSDAP OVRDSKQUOTA,260
0058 141 :+
0058 142 : RMS-32 warning completion codes:
0058 143 : (low order 3 bits = 000)
0058 144 :-
0058 145
0058 146 RMSDAP BOF,15
005C 147 RMSDAP RNL,97
0060 148 RMSDAP RTB,103
0064 149 RMSDAP TMO,152
0068 150 RMSDAP TNS,240
006C 151 RMSDAP BES,241
0070 152 RMSDAP PES,242
0074 153
0074 154 :+
0074 155 : RMS-32 error completion codes:
0074 156 : (low order 3 bits = 010)
0074 157 :-
0074 158
0074 159 RMSDAP ACT,3
```



|      |     |                                                                           |               |                                  |
|------|-----|---------------------------------------------------------------------------|---------------|----------------------------------|
| 0078 | 160 | RMSDAP                                                                    | DEL,28        |                                  |
| 007C | 161 | RMSDAP                                                                    | DNR,33        |                                  |
| 0080 | 162 | RMSDAP                                                                    | EOF,39        |                                  |
| 0084 | 163 | RMSDAP                                                                    | FEX,45        |                                  |
| 0088 | 164 | RMSDAP                                                                    | FLK,48        |                                  |
| 008C | 165 | RMSDAP                                                                    | FNF,50        |                                  |
| 0090 | 166 | RMSDAP                                                                    | PRV,85        |                                  |
| 0094 | 167 | RMSDAP                                                                    | REX,91        |                                  |
| 0098 | 168 | RMSDAP                                                                    | RLK,94        |                                  |
| 009C | 169 | RMSDAP                                                                    | RNF,96        |                                  |
| 00A0 | 170 | RMSDAP                                                                    | WLK,116       |                                  |
| 00A4 | 171 | RMSDAP                                                                    | EXP,41        |                                  |
| 00A8 | 172 | RMSDAP                                                                    | NMF,199       |                                  |
| 00AC | 173 | RMSDAP                                                                    | SUP,226       |                                  |
| 00B0 | 174 | RMSDAP                                                                    | RSA,101       |                                  |
| 00B4 | 175 | RMSDAP                                                                    | CRC,200       |                                  |
| 00B8 | 176 | RMSDAP                                                                    | WCC,243       |                                  |
| 00BC | 177 | RMSDAP                                                                    | IDR,244       |                                  |
| 00C0 | 178 | RMSDAP                                                                    | INCOMPSHR,261 |                                  |
| 00C4 | 179 | RMSDAP                                                                    | LWC,262       |                                  |
| 00C8 | 180 | ;+ RMS-32 error completion codes (where STV also contains an error code): |               |                                  |
| 00C8 | 181 | ; (low order 3 bits = 010)                                                |               |                                  |
| 00C8 | 182 | ;-                                                                        |               |                                  |
| 00C8 | 183 |                                                                           |               |                                  |
| 00C8 | 184 |                                                                           |               |                                  |
| 00C8 | 185 | RMSDAP                                                                    | ACC,2         |                                  |
| 00CC | 186 | RMSDAP                                                                    | CRE,24        |                                  |
| 00D0 | 187 | RMSDAP                                                                    | DAC,26        |                                  |
| 00D4 | 188 | RMSDAP                                                                    | ENT,37        |                                  |
| 00D8 | 189 | RMSDAP                                                                    | EXT,42        |                                  |
| 00DC | 190 | RMSDAP                                                                    | FND,49        |                                  |
| 00E0 | 191 | RMSDAP                                                                    | MKD,72        |                                  |
| 00E4 | 192 | RMSDAP                                                                    | DPE,34        |                                  |
| 00E8 | 193 | RMSDAP                                                                    | SPL,198       |                                  |
| 00EC | 194 | RMSDAP                                                                    | DNF,32        |                                  |
| 00F0 | 195 | RMSDAP                                                                    | JNF,255       |                                  |
| 00F4 | 196 | ;+ RMS-32 severe error completion codes:                                  |               |                                  |
| 00F4 | 197 | ; (low order 3 bits = 100)                                                |               |                                  |
| 00F4 | 198 | ;-                                                                        |               |                                  |
| 00F4 | 199 |                                                                           |               |                                  |
| 00F4 | 200 |                                                                           |               |                                  |
| 00F4 | 201 | ; ***** RMSDAP                                                            | TEMP2,1       | ; Defined but not used by RMS-32 |
| 00F4 | 202 | RMSDAP                                                                    | AID,4         |                                  |
| 00F8 | 203 | RMSDAP                                                                    | ALN,5         |                                  |
| 00FC | 204 | RMSDAP                                                                    | ALQ,6         |                                  |
| 0100 | 205 | RMSDAP                                                                    | ANI,7         |                                  |
| 0104 | 206 | RMSDAP                                                                    | AOP,8         |                                  |
| 0108 | 207 | RMSDAP                                                                    | BKS,12        |                                  |
| 010C | 208 | RMSDAP                                                                    | BKZ,13        |                                  |
| 0110 | 209 | RMSDAP                                                                    | BLN,14        |                                  |
| 0114 | 210 | RMSDAP                                                                    | BUG,18        |                                  |
| 0118 | 211 | RMSDAP                                                                    | BUG-DDI,119   |                                  |
| 011C | 212 | RMSDAP                                                                    | BUG-DAP,202   |                                  |
| 0120 | 213 | ; ***** RMSDAP                                                            | TEMP3,120     | ; Defined but not used by RMS-32 |
| 0120 | 214 | RMSDAP                                                                    | CCR,19        |                                  |
| 0124 | 215 | RMSDAP                                                                    | CHG,20        |                                  |
| 0128 | 216 | RMSDAP                                                                    | CHK,21        |                                  |



|      |             |        |          |                                  |
|------|-------------|--------|----------|----------------------------------|
| 012C | 217         | RMSDAP | COD,23   |                                  |
| 0130 | 218         | RMSDAP | CUR,25   |                                  |
| 0134 | 219         | RMSDAP | DAN,27   |                                  |
| 0138 | 220         | RMSDAP | DEV,29   |                                  |
| 013C | 221         | RMSDAP | DIR,30   |                                  |
| 0140 | 222         | RMSDAP | DME,31   |                                  |
| 0144 | 223         | RMSDAP | DNA,126  |                                  |
| 0148 | 224         | RMSDAP | DTP,35   |                                  |
| 014C | 225         | RMSDAP | DUP,36   |                                  |
| 0150 | 226         | RMSDAP | DVI,127  |                                  |
| 0154 | 227         | RMSDAP | ESA,128  |                                  |
| 0158 | 228         | RMSDAP | ESS,40   |                                  |
| 015C | 229         | RMSDAP | FAB,43   |                                  |
| 0160 | 230         | RMSDAP | FAC,44   |                                  |
| 0164 | 231         | RMSDAP | FLG,47   |                                  |
| 0168 | 232         | RMSDAP | FNA,129  |                                  |
| 016C | 233         | RMSDAP | FNM,51   |                                  |
| 0170 | 234         | RMSDAP | FSZ,130  |                                  |
| 0174 | 235         | RMSDAP | FOP,52   |                                  |
| 0178 | 236         | RMSDAP | FUL,53   |                                  |
| 017C | 237         | RMSDAP | IAL,131  |                                  |
| 0180 | 238         | RMSDAP | IAN,54   |                                  |
| 0184 | 239         | RMSDAP | IDX,208  |                                  |
| 0188 | 240         | RMSDAP | IFI,55   |                                  |
| 018C | 241         | RMSDAP | IMX,56   |                                  |
| 0190 | 242         | RMSDAP | IOP,58   |                                  |
| 0194 | 243         | RMSDAP | IRC,59   |                                  |
| 0198 | 244         | RMSDAP | ISI,60   |                                  |
| 019C | 245         | RMSDAP | KBF,61   |                                  |
| 01A0 | 246         | RMSDAP | KEY,62   |                                  |
| 01A4 | 247         | RMSDAP | KRF,63   |                                  |
| 01A8 | 248         | RMSDAP | KSZ,64   |                                  |
| 01AC | 249         | RMSDAP | LAN,65   |                                  |
| 01B0 | 250 ; ***** | RMSDAP | TEMP4,66 | ; Defined but not used by RMS-32 |
| 01B0 | 251         | RMSDAP | LNE,133  |                                  |
| 01B4 | 252 ; ***** | RMSDAP | TEMP5,70 | ; Defined but not used by RMS-32 |
| 01B4 | 253         | RMSDAP | MRN,73   |                                  |
| 01B8 | 254         | RMSDAP | MRS,74   |                                  |
| 01BC | 255         | RMSDAP | NAM,75   |                                  |
| 01C0 | 256         | RMSDAP | NEF,76   |                                  |
| 01C4 | 257 ; ***** | RMSDAP | TEMP6,77 | ; Defined but not used by RMS-32 |
| 01C4 | 258         | RMSDAP | NOD,134  |                                  |
| 01C8 | 259         | RMSDAP | NPK,78   |                                  |
| 01CC | 260         | RMSDAP | ORD,80   |                                  |
| 01D0 | 261         | RMSDAP | ORG,81   |                                  |
| 01D4 | 262         | RMSDAP | PBF,141  |                                  |
| 01D8 | 263         | RMSDAP | PLG,82   |                                  |
| 01DC | 264         | RMSDAP | POS,83   |                                  |
| 01E0 | 265 ; ***** | RMSDAP | TEMP7,84 | ; Defined but not used by RMS-32 |
| 01E0 | 266         | RMSDAP | QUO,143  |                                  |
| 01E4 | 267         | RMSDAP | RAB,86   |                                  |
| 01E8 | 268         | RMSDAP | RAC,87   |                                  |
| 01EC | 269         | RMSDAP | RAT,88   |                                  |
| 01F0 | 270         | RMSDAP | RBF,89   |                                  |
| 01F4 | 271         | RMSDAP | RFA,92   |                                  |
| 01F8 | 272         | RMSDAP | RFM,93   |                                  |
| 01FC | 273         | RMSDAP | RHB,144  |                                  |

|      |             |        |              |
|------|-------------|--------|--------------|
| 0200 | 274         | RMSDAP | RLF,145      |
| 0204 | 275         | RMSDAP | ROP,98       |
| 0208 | 276         | RMSDAP | RRV,100      |
| 020C | 277         | RMSDAP | RVU,223      |
| 0210 | 278         | RMSDAP | RSS,146      |
| 0214 | 279         | RMSDAP | RST,147      |
| 0218 | 280         | RMSDAP | RSZ,102      |
| 021C | 281         | RMSDAP | SEQ,104      |
| 0220 | 282         | RMSDAP | SHR,105      |
| 0224 | 283         | RMSDAP | SIZ,106      |
| 0228 | 284         | RMSDAP | SQO,148      |
| 022C | 285 ; ***** | RMSDAP | TEMP8,107    |
| 022C | 286         | RMSDAP | SYN,151      |
| 0230 | 287         | RMSDAP | TRE,109      |
| 0234 | 288         | RMSDAP | TYP,110      |
| 0238 | 289         | RMSDAP | UBF,111      |
| 023C | 290         | RMSDAP | USZ,112      |
| 0240 | 291         | RMSDAP | VER,113      |
| 0244 | 292 ; ***** | RMSDAP | VOL,114      |
| 0244 | 293         | RMSDAP | XAB,118      |
| 0248 | 294         | RMSDAP | ESL,205      |
| 024C | 295 ; ***** | RMSDAP | WSF,229      |
| 024C | 296         | RMSDAP | ENV,38       |
| 0250 | 297         | RMSDAP | PLV,220      |
| 0254 | 298         | RMSDAP | MBC,213      |
| 0258 | 299         | RMSDAP | RSL,222      |
| 025C | 300         | RMSDAP | WLD,228      |
| 0260 | 301         | RMSDAP | NET,214      |
| 0264 | 302         | RMSDAP | IBF,206      |
| 0268 | 303         | RMSDAP | REF,221      |
| 026C | 304         | RMSDAP | IFL,210      |
| 0270 | 305         | RMSDAP | DFL,204      |
| 0274 | 306         | RMSDAP | KNM,224      |
| 0278 | 307         | RMSDAP | IBK,207      |
| 027C | 308         | RMSDAP | KSI,212      |
| 0280 | 309         | RMSDAP | LEX,69       |
| 0284 | 310         | RMSDAP | SEG,224      |
| 0288 | 311         | RMSDAP | SNE,236      |
| 028C | 312         | RMSDAP | SPE,237      |
| 0290 | 313         | RMSDAP | UPI,238      |
| 0294 | 314         | RMSDAP | ACS,239      |
| 0298 | 315         | RMSDAP | STR,245      |
| 029C | 316         | RMSDAP | FTM,246      |
| 02A0 | 317         | RMSDAP | GBC,248      |
| 02A4 | 318         | RMSDAP | DEADLOCK,253 |
| 02A8 | 319         | RMSDAP | EXENQLM,254  |
| 02AC | 320         | RMSDAP | JOP,256      |
| 02B0 | 321         | RMSDAP | RUM,257      |
| 02B4 | 322         | RMSDAP | XNF,263      |
| 02B8 | 323         | RMSDAP | JNS,265      |
| 02BC | 324         | RMSDAP | NRU,266      |
| 02C0 | 325         |        |              |
| 02C0 | 326         |        |              |
| 02C0 | 327         |        |              |
| 02C0 | 328         |        |              |
| 02C0 | 329         |        |              |
| 02C0 | 330         |        |              |

; Defined but not used by RMS-32

; Defined by DAP but not by RMS-32

; Defined by DAP but not by RMS-32

: + RMS-32 severe completion codes (where STV also contains an error code):  
: (low order 3 bits = 100)  
: -



|      |     |           |             |
|------|-----|-----------|-------------|
| 02C0 | 331 | RMSDAP    | ATR,10      |
| 02C4 | 332 | RMSDAP    | ATW,11      |
| 02C8 | 333 | RMSDAP    | CCF,121     |
| 02CC | 334 | RMSDAP    | CDA,122     |
| 02D0 | 335 | RMSDAP    | CHN,123     |
| 02D4 | 336 | RMSDAP    | RER,90      |
| 02D8 | 337 | RMSDAP    | RMV,95      |
| 02DC | 338 | RMSDAP    | RPL,99      |
| 02E0 | 339 | RMSDAP    | SYS,108     |
| 02E4 | 340 | RMSDAP    | WER,115     |
| 02E8 | 341 | RMSDAP    | WPL,117     |
| 02EC | 342 | RMSDAP    | IFA,209     |
| 02F0 | 343 | RMSDAP    | WBE,227     |
| 02F4 | 344 | RMSDAP    | ENQ,249     |
| 02F8 | 345 | RMSDAP    | NETFAIL,250 |
| 02FC | 346 | RMSDAP    | SUPPORT,251 |
| 0300 | 347 | RMSDAP    | CRMP,252    |
| 0304 | 348 | RMSDAP    | NOJ,258     |
| 0308 | 349 | RMSDAP    | REENT,267   |
| 030C | 350 | RMSDAP    | CJF,268     |
| 0310 | 351 | RMSDAP    | TMR,269     |
| 0314 | 352 |           |             |
| 0314 | 353 | RMSDAPEND |             |
| 0318 | 354 |           |             |
| 0318 | 355 | .END      |             |

; Map to 'unspecified' DAP error  
; End of module

FALRMSDAP  
Symbol table

- RMS TO DAP ERROR CONVERSION

D 14

16-SEP-1984 01:46:38 VAX/VMS Macro V04-00  
5-SEP-1984 01:17:24 [FAL.SRC]FALRMSDAP.MAR;1

Page 9  
(3)

FALRMS TO\_DAP

|               |            |    |    |
|---------------|------------|----|----|
| RMSS_ACC      | = 0001C002 | RG | 02 |
| RMSS_ACS      | = 000187B4 |    |    |
| RMSS_ACT      | = 0001825A |    |    |
| RMSS_AID      | = 000183F4 |    |    |
| RMSS_ALN      | = 000183FC |    |    |
| RMSS_ALQ      | = 00018404 |    |    |
| RMSS_ANI      | = 0001840C |    |    |
| RMSS_AOP      | = 00018414 |    |    |
| RMSS_ATR      | = 0001C0CC |    |    |
| RMSS_ATW      | = 0001C0D4 |    |    |
| RMSS_BES      | = 000181C0 |    |    |
| RMSS_BKS      | = 0001841C |    |    |
| RMSS_BKZ      | = 00018424 |    |    |
| RMSS_BLN      | = 0001842C |    |    |
| RMSS_BOF      | = 00018198 |    |    |
| RMSS_BUG      | = 00018434 |    |    |
| RMSS_BUG_DAP  | = 00018444 |    |    |
| RMSS_BUG_DDI  | = 0001843C |    |    |
| RMSS_CCF      | = 0001C0DC |    |    |
| RMSS_CCR      | = 00018494 |    |    |
| RMSS_CDA      | = 0001C0E4 |    |    |
| RMSS_CHG      | = 0001849C |    |    |
| RMSS_CHK      | = 000184A4 |    |    |
| RMSS_CHN      | = 0001C0EC |    |    |
| RMSS_CJF      | = 0001C164 |    |    |
| RMSS_COD      | = 000184AC |    |    |
| RMSS_CONTROLC | = 00010651 |    |    |
| RMSS_CONTROLO | = 00010609 |    |    |
| RMSS_CONTROLY | = 00010611 |    |    |
| RMSS_CRC      | = 000182E2 |    |    |
| RMSS_CRE      | = 0001C00A |    |    |
| RMSS_CREATED  | = 00010619 |    |    |
| RMSS_CRE_STM  | = 00018069 |    |    |
| RMSS_CRMP     | = 0001C14C |    |    |
| RMSS_CUR      | = 000184B4 |    |    |
| RMSS_DAC      | = 0001C012 |    |    |
| RMSS_DAN      | = 000184BC |    |    |
| RMSS_DEADLOCK | = 000187D4 |    |    |
| RMSS_DEL      | = 00018262 |    |    |
| RMSS_DEV      | = 000184C4 |    |    |
| RMSS_DFL      | = 0001876C |    |    |
| RMSS_DIR      | = 000184CC |    |    |
| RMSS_DME      | = 000184D4 |    |    |
| RMSS_DNA      | = 000184DC |    |    |
| RMSS_DNF      | = 0001C04A |    |    |
| RMSS_DNR      | = 00018272 |    |    |
| RMSS_DPE      | = 0001C03A |    |    |
| RMSS_DTP      | = 000184E4 |    |    |
| RMSS_DUP      | = 000184EC |    |    |
| RMSS_DVI      | = 000184F4 |    |    |
| RMSS_ENQ      | = 0001C134 |    |    |
| RMSS_ENT      | = 0001C01A |    |    |
| RMSS_ENV      | = 00018724 |    |    |
| RMSS_EOF      | = 0001827A |    |    |
| RMSS_ESA      | = 000184FC |    |    |
| RMSS_ESL      | = 00018714 |    |    |

|                |            |
|----------------|------------|
| RMSS_ESS       | = 00018504 |
| RMSS_EXENQLM   | = 000187DC |
| RMSS_EXP       | = 000182C2 |
| RMSS_EXT       | = 0001C022 |
| RMSS_FAB       | = 0001850C |
| RMSS_FAC       | = 00018514 |
| RMSS_FEX       | = 00018282 |
| RMSS_FLG       | = 0001851C |
| RMSS_FLK       | = 0001828A |
| RMSS_FNA       | = 00018524 |
| RMSS_FND       | = 0001C02A |
| RMSS_FNF       | = 00018292 |
| RMSS_FNM       | = 0001852C |
| RMSS_FOP       | = 0001853C |
| RMSS_FSZ       | = 00018534 |
| RMSS_FTM       | = 000187C4 |
| RMSS_FUL       | = 00018544 |
| RMSS_GBC       | = 000187CC |
| RMSS_IAL       | = 0001854C |
| RMSS_IAN       | = 00018554 |
| RMSS_IBF       | = 00018754 |
| RMSS_IBK       | = 0001877C |
| RMSS_IDR       | = 000182F2 |
| RMSS_IDX       | = 0001855C |
| RMSS_IFA       | = 0001C124 |
| RMSS_IFI       | = 00018564 |
| RMSS_IFL       | = 00018764 |
| RMSS_IMX       | = 0001856C |
| RMSS_INCOMPSHR | = 0001826A |
| RMSS_IOP       | = 00018574 |
| RMSS_IRC       | = 0001857C |
| RMSS_ISI       | = 00018584 |
| RMSS_JNF       | = 0001C052 |
| RMSS_JNS       | = 000187F4 |
| RMSS_JOP       | = 000187E4 |
| RMSS_KBF       | = 0001858C |
| RMSS_KEY       | = 00018594 |
| RMSS_KFF       | = 00018031 |
| RMSS_KNM       | = 00018774 |
| RMSS_KRF       | = 0001859C |
| RMSS_KSI       | = 00018784 |
| RMSS_KSZ       | = 000185A4 |
| RMSS_LAN       | = 000185AC |
| RMSS_LEX       | = 0001878C |
| RMSS_LNE       | = 000185BC |
| RMSS_LWC       | = 000182FA |
| RMSS_MBC       | = 00018734 |
| RMSS_MKD       | = 0001C032 |
| RMSS_MRN       | = 000185CC |
| RMSS_MRS       | = 000185D4 |
| RMSS_NAM       | = 000185DC |
| RMSS_NEF       | = 000185E4 |
| RMSS_NET       | = 0001874C |
| RMSS_NETFAIL   | = 0001C13C |
| RMSS_NMF       | = 000182CA |
| RMSS_NOD       | = 000185F4 |
| RMSS_NOJ       | = 0001C154 |



FALRMSDAP  
Symbol table

- RMS TO DAP ERROR CONVERSION

E 14

16-SEP-1984 01:46:38 VAX/VMS Macro V04-00  
5-SEP-1984 01:17:24 [FAL.SRC]FALRMSDAP.MAR;1

Page 10  
(3)

|                  |            |                |            |
|------------------|------------|----------------|------------|
| RMSS_NORMAL      | = 00010001 | RMSS_SPE       | = 000187A4 |
| RMSS_NPK         | = 000185FC | RMSS_SPL       | = 0001C042 |
| RMSS_NRU         | = 000187FC | RMSS_SQO       | = 000186C4 |
| RMSS_OK_ALK      | = 00018039 | RMSS_STR       | = 000187BC |
| RMSS_OK_DEL      | = 00018041 | RMSS_SUC       | = 00010001 |
| RMSS_OK_DUP      | = 00018011 | RMSS_SUP       | = 000182D2 |
| RMSS_OK_IDX      | = 00018019 | RMSS_SUPERSEDE | = 00010631 |
| RMSS_OK_LIM      | = 00018051 | RMSS_SUPPORT   | = 0001C144 |
| RMSS_OK_NOP      | = 00018059 | RMSS_SYN       | = 000186D4 |
| RMSS_OK_RLK      | = 00018021 | RMSS_SYS       | = 0001C10C |
| RMSS_OK_RNF      | = 00018049 | RMSS_TMO       | = 000181B0 |
| RMSS_OK_RRL      | = 00018029 | RMSS_TMR       | = 0001C16C |
| RMSS_OK_RULK     | = 00018071 | RMSS_TNS       | = 000181B8 |
| RMSS_OK_WAT      | = 00018061 | RMSS_TRE       | = 000186DC |
| RMSS_ORD         | = 00018604 | RMSS_TYP       | = 000186E4 |
| RMSS_ORG         | = 0001860C | RMSS_UBF       | = 000186EC |
| RMSS_OVRDSKQUOTA | = 00010669 | RMSS_UPI       | = 000187AC |
| RMSS_PBF         | = 00018614 | RMSS_USZ       | = 000186F4 |
| RMSS_PENDING     | = 00018009 | RMSS_VER       | = 000186FC |
| RMSS_PES         | = 000181C8 | RMSS_WBE       | = 0001C12C |
| RMSS_PLG         | = 0001861C | RMSS_WCC       | = 000182EA |
| RMSS_PLV         | = 0001872C | RMSS_WER       | = 0001C114 |
| RMSS_POS         | = 00018624 | RMSS_WLD       | = 00018744 |
| RMSS_PRV         | = 0001829A | RMSS_WLK       | = 000182BA |
| RMSS_QUO         | = 00018634 | RMSS_WPL       | = 0001C11C |
| RMSS_RAB         | = 0001863C | RMSS_XAB       | = 0001870C |
| RMSS_RAC         | = 00018644 | RMSS_XNF       | = 00018704 |
| RMSS_RAT         | = 0001864C |                |            |
| RMSS_RBF         | = 00018654 |                |            |
| RMSS_REENT       | = 0001C15C |                |            |
| RMSS_REF         | = 0001875C |                |            |
| RMSS_RER         | = 0001C0F4 |                |            |
| RMSS_REX         | = 000182A2 |                |            |
| RMSS_RFA         | = 0001865C |                |            |
| RMSS_RFM         | = 00018664 |                |            |
| RMSS_RHB         | = 0001866C |                |            |
| RMSS_RLF         | = 00018674 |                |            |
| RMSS_RLK         | = 000182AA |                |            |
| RMSS_RMV         | = 0001C0FC |                |            |
| RMSS_RNF         | = 000182B2 |                |            |
| RMSS_RNL         | = 000181A0 |                |            |
| RMSS_ROP         | = 0001867C |                |            |
| RMSS_RPL         | = 0001C104 |                |            |
| RMSS_RRV         | = 00018684 |                |            |
| RMSS_RSA         | = 000182DA |                |            |
| RMSS_RSL         | = 0001873C |                |            |
| RMSS_RSS         | = 00018694 |                |            |
| RMSS_RST         | = 0001869C |                |            |
| RMSS_RSZ         | = 000186A4 |                |            |
| RMSS_RT8         | = 000181A8 |                |            |
| RMSS_RUM         | = 000187EC |                |            |
| RMSS_RVU         | = 0001868C |                |            |
| RMSS_SEG         | = 00018794 |                |            |
| RMSS_SEQ         | = 000186AC |                |            |
| RMSS_SHR         | = 000186B4 |                |            |
| RMSS_SIZ         | = 000186BC |                |            |
| RMSS_SNE         | = 0001879C |                |            |

+-----+  
! Psect synopsis !  
+-----+

| PSECT name       | Allocation       | PSECT No. | Attributes                                              |
|------------------|------------------|-----------|---------------------------------------------------------|
| ABS              | 00000000 ( 0.)   | 00 ( 0.)  | NOPIC USR CON ABS LCL NOSHR NOEXE NORD NOWRT NOVEC BYTE |
| \$ABSS           | 00000000 ( 0.)   | 01 ( 1.)  | NOPIC USR CON ABS LCL NOSHR EXE RD WRT NOVEC BYTE       |
| FAL\$ERROR_TABLE | 00000318 ( 792.) | 02 ( 2.)  | NOPIC USR CON REL LCL SHR NOEXE RD NOWRT NOVEC LONG     |

+-----+  
! Performance indicators !  
+-----+

| Phase                  | Page faults | CPU Time    | Elapsed Time |
|------------------------|-------------|-------------|--------------|
| Initialization         | 31          | 00:00:00.03 | 00:00:02.42  |
| Command processing     | 116         | 00:00:00.37 | 00:00:01.87  |
| Pass 1                 | 163         | 00:00:02.71 | 00:00:11.03  |
| Symbol table sort      | 0           | 00:00:00.09 | 00:00:00.91  |
| Pass 2                 | 70          | 00:00:00.69 | 00:00:02.53  |
| Symbol table output    | 23          | 00:00:00.09 | 00:00:00.11  |
| Psect synopsis output  | 2           | 00:00:00.01 | 00:00:00.01  |
| Cross-reference output | 0           | 00:00:00.00 | 00:00:00.00  |
| Assembler run totals   | 407         | 00:00:03.99 | 00:00:18.88  |

The working set limit was 1200 pages.  
17804 bytes (35 pages) of virtual memory were used to buffer the intermediate code.  
There were 10 pages of symbol table space allocated to hold 221 non-local and 0 local symbols.  
355 source lines were read in Pass 1, producing 14 object records in Pass 2.  
10 pages of virtual memory were used to define 9 macros.

+-----+  
! Macro library statistics !  
+-----+

| Macro library name                  | Macros defined |
|-------------------------------------|----------------|
| _\$255\$DUA28:[FAL.OBJ]FAL.MLB;1    | 0              |
| _\$255\$DUA28:[SYSLIB]STARLET.MLB;2 | 4              |
| TOTALS (all libraries)              | 4              |

282 GETS were required to define 4 macros.

There were no errors, warnings or information messages.

MACRO/LIS=LISS:FALRMSDAP/OBJ=OBJ\$:FALRMSDAP MSRC\$:FALRMSDAP/UPDATE=(ENH\$:FALRMSDAP)+LIB\$:FAL/LIB



0175 AH-BT13A-SE  
VAX/VMS V4.0

DIGITAL EQUIPMENT CORPORATION  
CONFIDENTIAL AND PROPRIETARY

