

NNN		NNN	IIIIIIIIII		CCCCCCCCCCCC	NNN		NNN	FFFFFFFFFFFFFF
NNN		NNN	IIIIIIIIII		CCCCCCCCCCCC	NNN		NNN	FFFFFFFFFFFFFF
NNN		NNN	IIIIIIIIII		CCCCCCCCCCCC	NNN		NNN	FFFFFFFFFFFFFF
NNN		NNN	III	CCC		NNN		NNN	FFF
NNN		NNN	III	CCC		NNN		NNN	FFF
NNN		NNN	III	CCC		NNN		NNN	FFF
NNNNNN		NNN	III	CCC		NNNNNN		NNN	FFF
NNNNNN		NNN	III	CCC		NNNNNN		NNN	FFF
NNNNNN		NNN	III	CCC		NNNNNN		NNN	FFF
NNN	NNN	NNN	III	CCC		NNN	NNN	NNN	FFFFFFFFFFFFFF
NNN	NNN	NNN	III	CCC		NNN	NNN	NNN	FFFFFFFFFFFFFF
NNN	NNN	NNN	III	CCC		NNN	NNN	NNN	FFFFFFFFFFFFFF
NNN		NNNNNN	III	CCC		NNN	NNNNNN	NNN	FFF
NNN		NNNNNN	III	CCC		NNN	NNNNNN	NNN	FFF
NNN		NNNNNN	III	CCC		NNN	NNNNNN	NNN	FFF
NNN		NNN	III	CCC		NNN	NNN	NNN	FFF
NNN		NNN	III	CCC		NNN	NNN	NNN	FFF
NNN		NNN	III	CCC		NNN	NNN	NNN	FFF
NNN		NNN	III	CCC		NNN	NNN	NNN	FFF
NNN		NNN	IIIIIIIIII		CCCCCCCCCCCC	NNN		NNN	FFF
NNN		NNN	IIIIIIIIII		CCCCCCCCCCCC	NNN		NNN	FFF
NNN		NNN	IIIIIIIIII		CCCCCCCCCCCC	NNN		NNN	FFF

```

CCCCCCCC NN    NN  FFFFFFFF MM    MM  SSSSSSSS  GGGGGGGG
CCCCCCCC NN    NN  FFFFFFFF MM    MM  SSSSSSSS  GGGGGGGG
CC        NN    NN  FF          MMMM  MMMM  SS          GG
CC        NN    NN  FF          MMMM  MMMM  SS          GG
CC        NNNN   NN  FF          MM   MM   SS          GG
CC        NNNN   NN  FF          MM   MM   SS          GG
CC        NN   NN  NN  FFFFFFFF MM    MM   SSSSSS   GG
CC        NN   NN  NN  FFFFFFFF MM    MM   SSSSSS   GG
CC        NN    NNNN FF          MM    MM    SS       GG  GGGGGG
CC        NN    NNNN FF          MM    MM    SS       GG  GGGGGG
CC        NN    NN  FF          MM    MM    SS       GG  GG
CC        NN    NN  FF          MM    MM    SS       GG  GG
CCCCCCCC NN    NN  FF          MM    MM  SSSSSSSS  GGGGGG
CCCCCCCC NN    NN  FF          MM    MM  SSSSSSSS  GGGGGG

```

```

LL        IIIIII  SSSSSSSS
LL        IIIIII  SSSSSSSS
LL        II      SS
LL        II      SS
LL        II      SS
LL        II      SS
LL        II      SSSSSS
LL        II      SSSSSS
LL        II      SS
LL        II      SS
LL        II      SS
LL        II      SS
LLLLLLLLLL IIIIII  SSSSSSSS
LLLLLLLLLL IIIIII  SSSSSSSS

```



```

1      .TITLE CNFMSG
2      .IDENT 'V04-000'
3
4      CNF MESSAGES
5
6      *****
7
8      *
9      * COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
10     * DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
11     * ALL RIGHTS RESERVED.
12     *
13     * THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
14     * ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
15     * INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
16     * COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
17     * OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
18     * TRANSFERRED.
19     *
20     * THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
21     * AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
22     * CORPORATION.
23     *
24     * DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
25     * SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
26     *
27     *
28     *****
29
30     AUTHOR:      Bob Grosso
31
32     DATE:        15-Oct-1982
33
34     MODIFIED BY:
35
36     V03-001 RPG0001      Bob Grosso      02-May-1983
37     Make CNFS_PRIV severity an ERROR instead of FATAL.
38     Add CNFS_TMPMBX and CNFS_NETMBX to indicate two required
39     privileges.
40
41     .FACILITY    NICONFIG,289 /SYSTEM /PREFIX=CNFS_
42
43     .SEVERITY    INFORMATIONAL
44
45     0121800B    GETVM/FAO_COUNT=1      <Allocated !UL bytes of virtual memory, total of !UL>
46     |
47     | If the VM bit is set in NICONFIG$LOG, then every time virtual memory
48     | is allocated, the amount will be tallied and the tally will be
49     | signalled.
50
51     01218013    FREEVM/FAO_COUNT=1     <Deallocated !UL bytes of virtual memory leaving !UL>
52     |
53     | If the VM bit is set in NICONFIG$LOG, then every time virtual memory
54     | is deallocated, the amount will be tallied and the tally will be
55     | signalled.
56

```

0000121

0121800B

01218013

CN
VO

00

74

```

0121801B 57      LOGIO          <NICONFIG requires LOG_IO privilege>
          58
          59      ! NICONFIG must run with LOG_IO privilege.  The simplest way to
          60      ! ensure that it does is to install it with this privilege.
          61
01218023 62      SYSNAM          <NICONFIG requires SYSNAM privilege>
          63
          64      ! NICONFIG must run with SYSNAM privilege in order to declare
          65      ! itself as a known image to be eligible for multiple connects.
          66      ! The simplest way to ensure that it does is to install it
          67      ! with this privilege.
          68
0121802B 69      NETMBX          <NICONFIG requires NETMBX privilege>
          70
          71      ! NICONFIG must run with NETMBX privilege in order to declare
          72      ! itself as a known image to be eligible for multiple connects.
          73      ! The simplest way to ensure that it does is to install it
          74      ! with this privilege.
          75
01218033 76      TMPMBX          <NICONFIG requires TMPMBX privilege>
          77
          78      ! NICONFIG must run with TMPMBX privilege in order to declare
          79      ! itself as a known image to be eligible for multiple connects.
          80      ! The simplest way to ensure that it does is to install it
          81      ! with this privilege.
          82
          83
          84      .SEVERITY  WARNING
01218038 85
          86      FAILGETVM/FAO_COUNT=1  <failed to allocate !UL bytes of virtual memory>
          87
          88      ! An error occurred when NICONFIG attempted to allocate virtual memory.
          89      ! Check the error message which should accompany it to determine
          90      ! whether the virtual address space has been exceeded, or whether
          91      ! a program error has been uncovered.  An invalid address or size
          92      ! for allocation would be indicative of a program error.
          93
01218040 94      FAILFREVM/FAO_COUNT=1  <failed to deallocate !UL bytes of virtual memory>
          95
          96      ! Error occurred when NICONFIG attempted to deallocate virtual memory.
          97      ! Check the error message which should accompany it to determine
          98      ! whether the virtual address space has been exceeded, or whether
          99      ! a program error has been uncovered.  An invalid address or size
          100     ! for deallocation would be indicative of a program error.
          101
          102     .SEVERITY  ERROR
0121804A 103
          104     LINK              <Error on logical link>
          105
          106     ! An error has occurred on a logical link, see accompanying message
          107     ! to determine course of action.
          108
01218052 109     SYSID              <Error while obtaining system ID message>
          110
          111     ! An error occurred during the read to the NI device driver.
          112     ! See accompanying message for appropriate action.
          113

```

```

0121805A 114 PRIV <Privilege error>
          115
          116 NICONFIG was not executing with all the privileges which it needs
          117 for proper execution. Messages enumerating the lacking privileges
          118 should accompany this message. NICONFIG should be installed with
          119 the required privileges before attempting execution.
          120
          121
          122 .SEVERITY FATAL
          123
01218064 124 LOGIC <Program logic error or unexpected condition>
          125
          126 A condition or circumstance was encountered which the NICONFIG
          127 logic was not prepared to handle. This is a programming error
          128 and should be reported.
          129
0121806C 130 NETASN <failed to declare name to network>
          131
          132 An error occurred when NICONFIG attempted to declare itself
          133 to the network as an known object. See the accompanying message
          134 to determine action.
          135
01218074 136 MAILBOX <Mailbox error>
          137
          138 An error has occurred reading a mailbox, see accompanying message
          139 to determine course of action.
          140
0121807C 141 CHAN <Error assigning or deassigning channel>
          142
          143 An error has occurred assigning or deassigning a channel, see
          144 accompanying message to determine course of action.
          145
01218084 146 DRVRSTRT <Error while issuing startup command to driver>
          147
          148 An error has occurred while attempting to issue the startup commands
          149 to the NI driver in preparation to reading the broadcast system ID
          150 messages. See the accompanying message to determine effective course
          151 of action.
          152
          153 .END

```

There were 0 errors, 0 warnings, and 0 informational messages issued.
 MESSAGE/LIS=L.ISS:CNFMSG/OBJ=OBJ\$:CNFMSG MSRC\$:CNFMSG

