


```

IIIIII  NN  NN  IIIIII  TTTTTTTTTT  MM  MM  SSSSSSSS  GGGGGGGG
IIIIII  NN  NN  IIIIII  TTTTTTTTTT  MM  MM  SSSSSSSS  GGGGGGGG
  II    NN  NN  II      TT      MMMM  MMMM  SS      GG
  II    NN  NN  II      TT      MMMM  MMMM  SS      GG
  II    NNNN NN  II      TT      MM  MM  SS      GG
  II    NNNN NN  II      TT      MM  MM  SS      GG
  II    NN  NN  II      TT      MM  MM  SSSSSS  GG
  II    NN  NN  II      TT      MM  MM  SSSSSS  GG
  II    NN  NN  II      TT      MM  MM  SS      GG
  II    NN  NN  II      TT      MM  MM  SS      GG
  II    NN  NN  II      TT      MM  MM  SS      GG
  II    NN  NN  IIIIII  TT      MM  MM  SSSSSSSS  GG
IIIIII  NN  NN  IIIIII  TT      MM  MM  SSSSSSSS  GG
IIIIII  NN  NN  IIIIII  TT      MM  MM  SSSSSSSS  GG

```

```

LL      IIIIII  SSSSSSSS
LL      IIIIII  SSSSSSSS
LL      II      SS
LL      II      SS
LL      II      SS
LL      II      SS
LL      II      SSSSSS
LL      II      SSSSSS
LL      II      SS
LL      II      SS
LL      II      SS
LL      II      SS
LLLLLLLLLLLL IIIIII  SSSSSSSS
LLLLLLLLLLLL IIIIII  SSSSSSSS

```

LI
VO
.....

```

1  INITMSG.MSG - system message file for INIT volume utility
2
3  Version:      'V04-000'
4
5  *****
6  *
7  *  COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
8  *  DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
9  *  ALL RIGHTS RESERVED.
10 *
11 *  THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
12 *  ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
13 *  INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
14 *  COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
15 *  OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
16 *  TRANSFERRED.
17 *
18 *  THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
19 *  AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
20 *  CORPORATION.
21 *
22 *  DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
23 *  SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
24 *
25 *
26 *****
27
28 ++
29
30 FACILITY:  VAX/VMS System Macro Libraries
31
32 ABSTRACT:
33
34     This file contains the MDL source for the INIT volume utility
35     messages.
36
37 ENVIRONMENT:
38
39     n/a
40
41 --
42
43
44 AUTHOR:  The VMS Group          CREATION DATE:  1-Aug-1976
45
46 MODIFIED BY:
47
48     V03-004 MCN0140          Maria del C. Nasr          27-Dec-1983
49           Add VALCNVERR error message to the common messages between
50           INIT and MOUNT.
51
52     V03-003 STJ3092          Steven T. Jeffreys,        26-Apr-1983
53           Added INITS_ERASEFAIL.
54
55     V03-002 MMD0124          Meg Dumont,              29-Mar-1983  0:50
56           Added new INIT msg code for BADOWNID (OWNER_IDENTIFIER)

```

57 |
58 | MODIFICATION HISTORY:
59 |
60 | 0005 DMW0013 David Michael Walp 25-Aug-1981
61 | Changed /ANSI to /LABEL
62 |
63 | 0004 DMW0011 David Michael Walp 30-Jul-1981
64 | Added MTLBLLONG and MTLBLNONA
65 |
66 | 0003 DMW0007 David Michael Walp 30-Apr-1981
67 | Added BADVOLLBL
68 |
69 | 0002 DMW0005 David Michael Walp, 10-Mar-1981
70 | Added /ANSI error. Mount common error.
71 | Added /ANSI=VOLUME_ACCESSIBILITY value error
72 |

```

73
74
75
76 Messages output by the INITVOL utility.
77
78
79
80
81
82 ***** Following messages are shared with MOUNT
83
84 When adding new messages in this section, use the Dx fill values.
85
0000075 86 .FACILITY INIT,117 /SYSTEM
87 .SEVERITY FATAL
88
0075800C 89 BADDATCHK <invalid keyword on /DATACHECK qualifier>
00758014 90 BADDENS <unknown value on /DENSITY qualifier>
0075801C 91 BADPRO <invalid syntax on /PROTECTION qualifier>
00758024 92 BADUIC <invalid UIC syntax>
0075802C 93 CONFQUAL <conflicting qualifiers>
00758034 94 ILLOPT <qualifier(s) not appropriate to this device>
0075803C 95 NONLOCAL <device is not a local device>
00758044 96 NOTRAN <logical name cannot be translated>
0075804C 97 UNKDEV <unknown device type>
00758054 98 BADLABELQ <invalid keyword on /LABEL qualifier>
0075805C 99 VALCNVERR <error converting value>
100 .LITERAL INITS_D3=7700580
101 .LITERAL INITS_D4=7700588
102 .LITERAL INITS_D5=7700596
103
104 ***** Preceding messages are shared with MOUNT
105
106
107 .BASE 15
108
0075807C 109 ALLOCFAIL <index file allocation failure>
00758084 110 BADBLOCKS <invalid syntax in bad block list>
0075808C 111 BADINDEX <invalid syntax on /INDEX qualifier>
00758094 112 BADRANGE <bad block address not on volume>
0075809C 113 CLUSTER <unsuitable cluster factor>
007580A4 114 DIAGPACK <disk is a diagnostic pack>
007580AC 115 FACTBAD <cannot read factory bad block data>
007580B4 116 INDEX <invalid index file position>
007580BC 117 MAXBAD <bad block table overflow>
118 .LITERAL INITS_S1=7700676
119
120 .BASE 25
121
007580CC 122 BADOVR <unknown keyword on /OVERRIDE qualifier>
007580D4 123 BADVOL1 <bad VOL1 ANSI label>
007580DC 124 LARGE CNT <disk too large to be supported>
007580E4 125 BADSTRUCT <invalid value on /STRUCTURE qualifier>
007580EC 126 NOTSTRUCT1 <qualifier(s) not available with structure level 1>
007580F4 127 BADVOLACC <invalid value on /LABEL=VOLUME ACCESSIBILITY qualifier>
007580FC 128 BADVOLLBL <invalid value for ANSI tape volume label>

```

00758104	129	MTLBLONG	<label specified for !AC!UW: is longer then 6 characters!/> /FA0=2
0075810C	130	MTLBLNONA	<label specified for !AC!UW: contains non-ANSI 'a' characters!/> /FA
00758114	131	BADOWNID	<invalid value on /LABEL=OWNER_IDENTIFIER qualifier>
	132		
	133		
	134	Warning messages	
	135		
	136		
	137	.SEVERITY	WARNING
	138	.BASE	512
	139		
00759000	140	BLKZERO	<block zero is bad - volume not bootable>
00759008	141	NOBADDATA	<bad block data not found on volume>
00759010	142	ERASEFAIL	<volume not completely erased>
	143	.END	

There were 0 errors, 0 warnings, and 0 informational messages issued.
MESSAGE/LIS=LIS\$:INITMSG/OBJ=OBJ\$:INITMSG MSRC\$:INITMSG

.....

