VMSLIB

```
LL          NN      NN  KK      KK  MM      MM   SSSSSSSS    GGGGGGGG
LL          NN      NN  KK      KK  MM      MM   SSSSSSSS    GGGGGGGG
LL          NN      NN  KK      KK  MMMM  MMMM  SS          GG
LL          NN      NN  KK      KK  MMMM  MMMM  SS          GG
LL          NNNN    NN  KK    KK    MM  MM  MM  SS          GG
LL          NNNN    NN  KK    KK    MM  MM  MM  SS          GG
LL          NN  NN  NN  KKKKK       MM      MM  SSSSSS      GG
LL          NN  NN  NN  KKKKK       MM      MM  SSSSSS      GG
LL          NN    NNNN  KK    KK    MM      MM        SS  GG  GGGGGG
LL          NN    NNNN  KK    KK    MM      MM        SS  GG  GGGGGG
LL          NN      NN  KK      KK  MM      MM        SS  GG      GG    ....
LL          NN      NN  KK      KK  MM      MM        SS  GG      GG    ....
LLLLLLLLLL  NN      NN  KK      KK  MM      MM  SSSSSSSS      GGGGGG    ....
LLLLLLLLLL  NN      NN  KK      KK  MM      MM  SSSSSSSS      GGGGGG    ....


LL              IIIIII      SSSSSSSS
LL              IIIIII      SSSSSSSS
LL                II      SS
LL                II      SS
LL                II      SS
LL                II        SSSSSS
LL                II        SSSSSS
LL                II              SS
LL                II              SS
LL                II              SS
LL                II              SS
LLLLLLLLLL      IIIIII    SSSSSSSS
LLLLLLLLLL      IIIIII    SSSSSSSS
```

LNKMSG   Message definitions   16-SEP-1984 02:30:56   VAX-11 Message V04-00   Page   1
                                                        5-SEP-1984 04:41:12   DISK$VMSMASTER:[VMSLIB.SRC]LNKMSG.MSG;1

K 9

```
     1          .TITLE   UTIL$LNK_MSGS Error messages for obj module dissector
     2          .IDENT   'V04-000'
     3  !
     4  !*******************************************************************************
     5  !*                                                                             *
     6  !*  COPYRIGHT (c) 1978, 1980, 1982, 1984 BY                                    *
     7  !*  DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.                     *
     8  !*  ALL RIGHTS RESERVED.                                                       *
     9  !*                                                                             *
    10  !*  THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED      *
    11  !*  ONLY IN  ACCORDANCE WITH  THE  TERMS  OF  SUCH  LICENSE  AND WITH THE      *
    12  !*  INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR  ANY  OTHER      *
    13  !*  COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY      *
    14  !*  OTHER PERSON.  NO TITLE TO AND OWNERSHIP OF  THE  SOFTWARE IS  HEREBY      *
    15  !*  TRANSFERRED.                                                               *
    16  !*                                                                             *
    17  !*  THE INFORMATION IN THIS SOFTWARE IS  SUBJECT TO CHANGE WITHOUT NOTICE      *
    18  !*  AND  SHOULD  NOT  BE  CONSTRUED AS  A COMMITMENT BY DIGITAL EQUIPMENT      *
    19  !*  CORPORATION.                                                               *
    20  !*                                                                             *
    21  !*  DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE  OR  RELIABILITY OF ITS      *
    22  !*  SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.                     *
    23  !*                                                                             *
    24  !*                                                                             *
    25  !*******************************************************************************
    26  !
    27  !
```

UTIL$LNK_MSGS   Error messages for obj modul 16-SEP-1984 02:30:57   VAX-11 Message V04-00   Page   2
                                                            5-SEP-1984 04:41:12   DISK$VMSMASTER:[VMSLIB.SRC]LNKMSG.MSG;1

```
                    28
      0000011E      29  .FACILITY        UTIL,286/SYSTEM /PREFIX=LNK$_
                    30
                    31  .SEVERITY        ERROR
                    32
      011E800A      33  BADCCC           <illegal compilation code (!UL.) in module !AC>/FAO=2
      011E8012      34  EOMERROR         <compilation errors in module !AC>/FAO=1
      011E801A      35  EOMFATAL         <fatal compilation errors in module !AC>/FAO=1
      011E8022      36  EOMWARN          <compilation warnings in module !AC>/FAO=1
      011E802A      37  GSDTYP           <illegal GSD record type (!UL.) in module !AC>/FAO=2
      011E8032      38  ILLFMLCNT        <minimum argument count exceeds maximum for procedure !AC in module !AC>/FAO
      011E803A      39  ILLMODNAM        <illegal module name length (!UL.) for module !AC>/FAO=2
      011E8042      40  ILLPSCLEN        <psect !AC has illegal length (!UL.) in module !AC>/FAO=3
      011E804A      41  ILLRECLEN        <illegal record length (!UL.) in module !AC>/FAO=2
      011E8052      42  ILLRECLN2        <illegal record length (!UL)>/FAO=1/ID=ILLRECLEN
      011E805A      43  ILLRECTYP        <illegal record type (!UL.) in module !AC>/FAO=2
      011E8062      44  ILLRECTY2        <illegal record type (!UL)>/FAO=1/ID=ILLRECTYP
      011E806A      45  ILLSYMLEN        <symbol !AC has illegal length (!UL.) in module !AC>/FAO=3
      011E8072      46  NOEOM            <module !AC does not contain end of module record>/FAO=1
      011E807A      47  RECTOOSML        <data overflows object record in module !AC>/FAO=1
      011E8082      48  SEQUENCE         <illegal record sequence in module !AC>/FAO=1
      011E808A      49  SEQUENCE2        <illegal record sequence>/ID=SEQUENCE
      011E8092      50  STRLVL           <illegal object language structure level in module !AC>/FAO=1
                    51
                    52          .END
```

There were 0 errors, 0 warnings, and 0 informational messages issued.
MESSAGE/LIS=LIS$:LNKMSG/OBJ=OBJ$:LNKMSG MSRC$:LNKMSG