

```

;-----
;
; VTermBugA -- Debugger for the Motorola 68000
;
; This flavor is terminal base APort, 20 lines with disassembler.
;
; 2/11/85 - twm added equates for new hardware and 68000
;-----

```

```

onMacTrue .EQU 0 ; NOT on a Macintosh
onLisaTrue .EQU 0 ; NOT on a Lisa (Mac XL) under MacWorks
onYaccTrue .EQU 1 ; Yes, it's on a Yacc
on68000 .EQU 0 ; NOT on a Mac or Lisa
noTerm .EQU 0 ; set to 0 if RS232 s/b used
aPort .EQU 1 ; use A Port for terminal
swapScreen .EQU 0 ; set 1 if screen swap
withDis .EQU 1 ; set 1 if disassembler
fullSized .EQU 1 ; full command set
heapPrint .EQU 1 ; set to zero if no heap printing
dLines .EQU 20 ; number of lines to display
NumIL .EQU 20 ; number of lines to IL (default)
DDBG .EQU 0 ; NOT debugging the debugger
Tnames .EQU 0 ; DONT show trap names

```

```

.PROC MACSBUG,0
.BORG 0

```

```

.NOLIST
.IF onMacTrue
.INCLUDE mac/tiasm-SYSEQU.TEXT
.INCLUDE mac/tiasm-GrafEQU.TEXT
.INCLUDE mac/tiasm-ToolEQU.TEXT
.INCLUDE mac/tiasm-HeapDefs.TEXT
.INCLUDE mac/tiasm-sysmacs.TEXT
.ELSE
.INCLUDE tiasm-SYSEQU.TEXT
.INCLUDE tiasm-GrafEQU.TEXT
.INCLUDE tiasm-ToolEQU.TEXT
.INCLUDE tiasm-HeapDefs.TEXT
.INCLUDE tiasm-sysmacs.TEXT
.ENDC

```

```

.LIST
.INCLUDE dbg-rom4EQU.TEXT ; equates/global defs
.INCLUDE dbg-init.TEXT ; basic debugger, init
.INCLUDE dbg-cmds.TEXT ; more commands
.INCLUDE dbg-io.TEXT ; rs232/display stuff
.INCLUDE dbg-atrap.TEXT ; atrap stuff
.INCLUDE dbg-heap.TEXT ; heap stuff
.INCLUDE dbg-dm.text ; memory display code
.INCLUDE dbg-print.TEXT ; printing utilities

```

```

.IF FullSized
.INCLUDE dbg-syms.text ; symbols code/table
.ENDC

```

```

.IF withDis
.INCLUDE dbg-D.TEXT ; disassembler
.ENDC

```

```
.IF      Tnames  
.INCLUDE dbg-trapnames.text      ; A-trap names  
.ENDC  
  
.END
```