

DDDDDDDDDDDD		CCCCCCCCCCCC	LLL
DDDDDDDDDDDD		CCCCCCCCCCCC	LLL
DDDDDDDDDDDD		CCCCCCCCCCCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDD	DDD	CCC	LLL
DDDDDDDDDDDD		CCCCCCCCCCCC	LLLLLLLLLLLLLLLL
DDDDDDDDDDDD		CCCCCCCCCCCC	LLLLLLLLLLLLLLLL
DDDDDDDDDDDD		CCCCCCCCCCCC	LLLLLLLLLLLLLLLL

```

IIIIII      MM      MM      AAAAAA      GGGGGGGG      EEEEEEEEEE      CCCCCCCC      TTTTTTTTTT      RRRRRRRR      LL
IIIIII      MM      MM      AAAAAA      GGGGGGGG      EEEEEEEEEE      CCCCCCCC      TTTTTTTTTT      RRRRRRRR      LL
  II        MMMM    MMMM    AA      AA      GG          EE          CC          TT          RR      RR      LL
  II        MMMM    MMMM    AA      AA      GG          EE          CC          TT          RR      RR      LL
  II        MM     MM     AA      AA      GG          EE          CC          TT          RR      RR      LL
  II        MM     MM     AA      AA      GG          EE          CC          TT          RR      RR      LL
  II        MM     MM     AA      AA      GG          EEEEEEEE      CC          TT          RRRRRRRR      LL
  II        MM     MM     AA      AA      GG          EEEEEEEE      CC          TT          RRRRRRRR      LL
  II        MM     MM     AAAAAAAAAA      GG      GGGGGG      EE          CC          TT          RR      RR      LL
  II        MM     MM     AAAAAAAAAA      GG      GGGGGG      EE          CC          TT          RR      RR      LL
  II        MM     MM     AA      AA      GG          GG          EE          CC          TT          RR      RR      LL
  II        MM     MM     AA      AA      GG          GG          EE          CC          TT          RR      RR      LL
IIIIII      MM     MM     AA      AA      GG          GGGGGG      EEEEEEEEEE      CCCCCCCC      TT          RR      RR      LL
IIIIII      MM     MM     AA      AA      GG          GGGGGG      EEEEEEEEEE      CCCCCCCC      TT          RR      RR      LL

```

```

LL          IIIIII      SSSSSSSS
LL          IIIIII      SSSSSSSS
LL          II         SS
LL          II         SS
LL          II         SS
LL          II         SS
LL          II         SSSSSS
LL          II         SSSSSS
LL          II         SS
LL          II         SS
LL          II         SS
LL          II         SS
LLLLLLLLLLL IIIIII      SSSSSSSS
LLLLLLLLLLL IIIIII      SSSSSSSS

```

IMAGECTRL
Table of contents

- IMAGE CONTROL

J 11

15-SEP-1984 23:53:05 VAX/VMS Macro V04-00

Page 0

(3)	85	CONTINUE IMAGE EXECUTION
(4)	113	DEBUG IMAGE EXECUTION
(5)	160	STOP IMAGE EXECUTION
(6)	240	TEST PREVIOUS MODE
(7)	260	SAVE/RESTORE IMAGE PRIVILEGES
(8)	294	RUN DOWN IMAGE AND INDIRECT LEVELS
(9)	355	SHUT DOWN IMAGE
(10)	405	RMS RUNDOWN AN IMAGE

```

0000 1 .TITLE IMAGECTRL - IMAGE CONTROL
0000 2 .IDENT 'V04-000'
0000 3
0000 4
0000 5 *****
0000 6 *
0000 7 * COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
0000 8 * DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
0000 9 * ALL RIGHTS RESERVED.
0000 10 *
0000 11 * THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
0000 12 * ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
0000 13 * INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
0000 14 * COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
0000 15 * OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
0000 16 * TRANSFERRED.
0000 17 *
0000 18 * THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
0000 19 * AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
0000 20 * CORPORATION.
0000 21 *
0000 22 * DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
0000 23 * SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
0000 24 *
0000 25 *
0000 26 *****
0000 27
0000 28 IMAGE CONTROL DCLS COMMAND EXECUTION
0000 29
0000 30 CONTINUE IMAGE EXECUTION
0000 31 DEBUG IMAGE EXECUTION
0000 32 STOP IMAGE EXECUTION
0000 33
0000 34 D. N. CUTLER 4-APR-77
0000 35
0000 36 MODIFIED BY:
0000 37
0000 38 V03-006 HWS0071 Harold Schultz 04-Jun-1984
0000 39 When finished with skipping data records in the input
0000 40 stream of an image being run down, set EOL in the input
0000 41 buffer following the last record read.
0000 42
0000 43 V03-005 HWS0036 Harold Schultz 21-Mar-1984
0000 44 Use PRC_V_IRUNDWN to indicate whether or not an image
0000 45 has been run down by DCL
0000 46
0000 47 V03-004 HWS0026 Harold Schultz 09-Mar-1984
0000 48 When shutting down an image, check if device is a
0000 49 record-oriented device rather than a terminal.
0000 50
0000 51 V03-003 PCG0005 Peter George 15-Jun-1983
0000 52 Create DCL$RMSRUNDN.
0000 53
0000 54 V03-002 PCG0004 Peter George 24-Feb-1983
0000 55 Remove SETBIT WRK_V_NOSTAT from CONTINUE and STOP.
0000 56
0000 57 V03-001 PCG0003 Peter George 21-Jan-1983

```

IMAGECTRL
V04-000

- IMAGE CONTROL

L 11

15-SEP-1984 23:53:05 VAX/VMS Macro V04-00
4-SEP-1984 23:41:00 [DCL.SRC]IMAGECTRL.MAR;1

Page 2
(1)

0000 58 :
0000 59 :
0000 60 :---

Remove code that is duplicated in DCL\$LOGOUT
from DCL\$STOP.

```

0000 62 :
0000 63 : MACRO LIBRARY CALLS
0000 64 :
0000 65 :
0000 66 $PPDEF ;PROCESS PERMANENT DATA AREA
0000 67 PRCDEF ;DEFINE PROCESS WORK AREA
0000 68 WRKDEF ;DEFINE COMMAND WORK AREA
0000 69 PTRDEF ;DEFINE RESULT PARSE DESCRIPTOR FORMAT
0000 70 $DEVDEF ;DEFINE DEVICE CHARACTERISTIC BITS
0000 71 $PSLDEF ;DEFINE PROCESSOR STATUS FIELDS
0000 72 $RABDEF ;DEFINE RAB OFFSETS
0000 73 $SSDEF ;DEFINE SYSTEM STATUS VALUES
0000 74 $CLMSGDEF ;DEFINE ERROR/STATUS VALUES
0000 75 :
0000 76 : LOCAL DATA
0000 77 :
0000 78 :
0000 79 : HEX CONVERSION TABLE
0000 80 :
0000 81 :
00000000 82 .PSECT DCL$ZCODE, BYTE, RD, NOWRT
34 35 36 37 38 39 41 42 43 44 45 46 0000 83 HEXTAB: .ASCII /FEDCBA9876543210/ ;
30 31 32 33 000C

```

```

0010 85 .SBTTL CONTINUE IMAGE EXECUTION
0010 86 :+
0010 87 : DCL$CONTINUE - CONTINUE IMAGE EXECUTION
0010 88 :
0010 89 : THIS ROUTINE IS CALLED AS AN INTERNAL COMMAND TO EXECUTE THE CONTINUE DCLS
0010 90 : COMMAND.
0010 91 :
0010 92 : INPUTS:
0010 93 :
0010 94 : R8 = ADDRESS OF SCRATCH BUFFER DESCRIPTOR.
0010 95 : R9 = ADDRESS OF SCRATCH STACK.
0010 96 : R10 = BASE ADDRESS OF COMMAND WORK AREA.
0010 97 : R11 = BASE ADDRESS OF PROCESS WORK AREA.
0010 98 :
0010 99 : OUTPUTS:
0010 100 :
0010 101 : IF A PREVIOUS IMAGE WAS INTERRUPTED VIA A CONTROL Y AST, THEN THE
0010 102 : CURRENT COMMAND CONTEXT IS REMOVED FROM THE STACK AND CONTROL IS
0010 103 : RETURNED TO THE IMAGE. OTHERWISE THIS COMMAND IS A NOPERATION.
0010 104 :-
0010 105 :
0010 106 .ENABL LSB
0010 107 DCL$CONTINUE:: ;CONTINUE IMAGE EXECUTION
03 00AF CB 00B9 30 0010 108 BSBW TESTMODE ;TEST PREVIOUS MODE
00DE 04 E1 0013 109 BBC #PRC_V_PRIV,PRC_B_FLAGS2(R11),10$ ;BR IF UNPRIVILEGED IMAGE
00DE 30 0019 110 BSBW RESTORE_PRIVS ;RESTORE IMAGE PRIVILEGE
00DE 04 001C 111 10$: RET ;

```

```

001D 113 .SBTTL DEBUG IMAGE EXECUTION
001D 114 :+
001D 115 : DCL$DEBUG - DEBUG IMAGE EXECUTION
001D 116 :
001D 117 : THIS ROUTINE IS CALLED AS AN INTERNAL COMMAND TO EXECUTE THE DEBUG DCLS
001D 118 : COMMAND.
001D 119 :
001D 120 : INPUTS:
001D 121 :
001D 122 : R8 = ADDRESS OF SCRATCH BUFFER DESCRIPTOR.
001D 123 : R9 = ADDRESS OF SCRATCH STACK.
001D 124 : R10 = BASE ADDRESS OF COMMAND WORK AREA.
001D 125 : R11 = BASE ADDRESS OF PROCESS WORK AREA.
001D 126 :
001D 127 : OUTPUTS:
001D 128 :
001D 129 : IF A PREVIOUS IMAGE WAS INTERRUPTED VIA A CONTROL Y AST, THEN A
001D 130 : DEBUG EXCEPTION IS GENERATED FOR THE IMAGE. OTHERWISE THIS COMMAND
001D 131 : IS A NOPERATION.
001D 132 :-
001D 133
001D 134 DCL$DEBUG.: ;DEBUG IMAGE EXECUTION
10 AD 00AC 30 001D 135 BSBW TESTMODE ;TEST PREVIOUS MODE
7E CB 16 78 0020 136 MOVAB B^20$,16(FP) ;RESET AST RETURN ADDRESS
FO AF 9F 0025 137 ASHL #PSL$V_PVMOD,#<PSL$C_SUPER@2>! - ;CONSTRUCT PROPER PSL
02 0029 138 PSL$C_USER,-(SP)
002C 139 PUSHAB 10$ ;SET PC
002D 140 REI
002D 141
002D 142 :
002D 143 : CONTROL IS REGAINED AT THIS POINT WITH:
002D 144 :
002D 145 : 00(SP) = NUMBER OF AST ARGUMENTS (ALWAYS 5).
002D 146 : 04(SP) = AST PARAMETER.
002D 147 : 08(SP) = SAVED R0.
002D 148 : 12(SP) = SAVED R1.
002D 149 : 16(SP) = IMAGE PC.
002D 150 : 20(SP) = IMAGE PSL.
002D 151 :
002D 152 :
5E 08 C0 002D 153 20$: ADDL #8,SP ;REMOVE NUMBER OF ARGUMENTS AND PARAMETER
7E 046C 8F 3C 0030 154 POPR #^M<R0,R1> ;RESTORE SAVED REGISTERS
00000000'9F 17 DD 0032 155 MOVZWL #SS$_DEBUG,-(SP) ;SET EXCEPTION NAME
0037 156 PUSHL #3 ;SET NUMBER OF EXCEPTION ARGUMENTS
0039 157 JMP @#EXES$REFLECT ;REFLECT EXCEPTION
003F 158 .DSABL LSB

```



```

003F 160 .SBTTL STOP IMAGE EXECUTION
003F 161 :
003F 162 : DCL$STOP - STOP IMAGE EXECUTION
003F 163 :
003F 164 : THIS ROUTINE IS CALLED AS AN INTERNAL COMMAND TO EXECUTE THE STOP DCL$
003F 165 : COMMAND.
003F 166 :
003F 167 : INPUTS:
003F 168 :
003F 169 : R8 = ADDRESS OF SCRATCH BUFFER DESCRIPTOR.
003F 170 : R9 = ADDRESS OF SCRATCH STACK.
003F 171 : R10 = BASE ADDRESS OF COMMAND WORK AREA.
003F 172 : R11 = BASE ADDRESS OF PROCESS WORK AREA.
003F 173 :
003F 174 : OUTPUTS:
003F 175 :
003F 176 : IF A PROCESS NAME OR IDENTIFICATION IS SPECIFIED, THEN THAT PROCESS IS
003F 177 : DELETED.
003F 178 :
003F 179 : IF THE JOB IS A NONINTERACTIVE JOB, THEN THE JOB IS LOGGED OFF THE SYSTEM
003F 180 : WITH A STATUS OF NORMAL COMPLETION. OTHERWISE ALL INDIRECT FILE LEVELS ARE
003F 181 : UNSTACKED AND A TEST IS MADE TO DETERMINE IF AN IMAGE WAS INTERRUPTED VIA
003F 182 : A CONTROL C/Y. IF A PREVIOUS IMAGE WAS INTERRUPTED, THEN THE CONTEXT OF THE
003F 183 : RUN COMMAND THAT INITIATED IMAGE EXECUTION IS REMOVED FROM THE STACK AND
003F 184 : RMS-32 IS CALLED TO CLOSE ALL OPEN IMAGE FILES. OTHERWISE NO OPERATION IS
003F 185 : PERFORMED.
003F 186 : -
003F 187 :
003F 188 DCL$STOP:
003F 189 BSBW DCL$GETDVAL ;STOP IMAGE EXECUTION
55 04 D1 0042 190 CMPL #PTR_K_ENDLINE,R5 ;GET DESCRIPTOR VALUES
3E 12 0045 191 BNEQ 40$ ;END OF LINE?
5C AB D5 0047 192 10$: TSTL PRC_L_INDEPTH(R11) ;IF NEQ NO
05 13 004A 193 BEQL 20$ ;INDIRECT LEVEL ZERO?
FFB1' 30 004C 194 BSBW DCL$UNSTACK ;IF EQL YES
F6 11 004F 195 BRB 10$ ;UNSTACK INDIRECT LEVEL
06 E1 0051 196 20$: BBC #PRC_V_MODE,- ;IF SET, NONINTERACTIVE JOB
03 68 AB 0053 197 PRC_Q_FLAGS(R11),25$
FFA7' 31 0056 198 BRW DCL$ABORT ;LOG PROCESS OUT
0070 30 0059 199 25$: BSBW TESTMODE ;TEST PREVIOUS MODE
5A FC AA D0 005C 200 MOVL WRK_L_SAVFP(R10),R10 ;RESTORE SAVED WRK ADDRESS
0151 30 0060 201 BSBW DCL$SHUTDOWN ;CLOSE FILES OF PREVIOUS IMAGE
00000000'GF D4 0063 202 CLRL G^CTL$GL_CLINTOWN ;ZERO CLINT OWN STORAGE POINTER
00000000'GF D4 0069 203 CLRL G^CTL$GL_DCLPRSOWN ;ZERO DCL PARSE OWN STORAGE
18 8A 006F 204 $RUNDOWN_S #PSL$C_USER ;RUN DOWN PREVIOUS IMAGE
00AF CB 007A 205 BICB #<PRC_M_EXEONLY ! PRC_M_PRIV>,- ;SINCE IMAGE IS NOW GONE
007D 206 PRC_B_FLAGS2(R11) ;NO NEED TO PROTECT IT
5D 5A D0 0081 207 CLRBIT PRC_V_IRUNDWN,PRC_B_IMGFLAG(R11) ;INDICATE THAT IMAGE IS RUNDOWN
0084 208 MOVL R10,FP ;RESET FP SO YLEVEL WRK IS DEALLOCATED
05 0084 209 RSB ;ON RETURN TO DCL$RESTART.
0085 210 :
0085 211 :
0085 212 :
0085 213 : DELETE PROCESS
0085 214 :
0085 215 :
79 D4 0085 216 40$: CLRL -(R9) ;CLEAR PROCESS IDENTIFICATION

```

	57	58	D0	0087	217	MOVL	R8,R7	; COPY ADDRESS OF SCRATCH DESCRIPTOR
	55	00	D1	008A	218	CMPL	#PTR_K_COMDQUAL,R5	; COMMAND QUALIFIER SPECIFIED?
		26	12	008D	219	BNEQ	70\$; IF NEQ NO
		FF6E'	30	008F	220	BSBW	DCL\$GETDVAL	; GET VALUE PARAMETERS
	52	51	7D	0092	221	MOVQ	R1,R2	; SAVE VALUE PARAMETERS
		52	D7	0095	222	DECL	R2	; ANY MORE CHARACTERS TO CONVERT?
		12	19	0097	223	BLSS	60\$; IF LSS NO
FF61 CF	10	83	3A	0099	224	LOCC	(R3)+,#16,HEXTAB	; SEARCH FOR HEX CHARACTER MATCH
		23	13	009F	225	BEQL	80\$; IF EQL VALUE SYNTAX ERROR
	69	10	C4	00A1	226	MULL	#16,(R9)	; SCALE ACCUMULATED RESULT
	69	50	C0	00A4	227	ADDL	R0,(R9)	; ADD IN NEXT DIGIT
		69	D7	00A7	228	DECL	(R9)	; SUBTRACT OUT CHARACTER COUNT
		EA	11	00A9	229	BRB	50\$; .
		FF52'	30	00AB	230	BSBW	DCL\$GETDVAL	; GET DESCRIPTOR VALUES
	55	04	D1	00AE	231	CMPL	#PTR_K_ENDLINE,R5	; END OF LINE?
		02	12	00B1	232	BNEQ	70\$; IF NEQ NO
		57	D4	00B3	233	CLRL	R7	; CLEAR DESCRIPTOR ADDRESS
	68	51	7D	00B5	234	MOVQ	R1,(R8)	; SAVE PROCESS NAME PARAMETERS
				00B8	235	\$DELPRC_S	(R9),(R7)	; DELETE PROCESS
			05	00C3	236	RSB		; .
				00C4	237	STATUS	IVVALU	; SET INVALID VALUE SYNTAX STATUS
			05	00CB	238	RSB		; .

```

00CC 240 .SBTTL TEST PREVIOUS MODE
00CC 241 :
00CC 242 : SUBROUTINE TO TEST PREVIOUS MODE AND DISABLE CONTROL Y AST
00CC 243 :
00CC 244 :
00CC 245 TESTMODE: ;TEST PREVIOUS MODE
00CC 246 SETBIT PRC_V_DISABL,PRC_W_FLAGS(R11) ;DISABLE CONTROL Y AST
0A 68 AB 0B E5 00D0 247 BBCC #PRC_Q_YLEVEL,PRC_Q_FLAGS(R11),10$ ;IF CLR, NOT AT CONTROL Y/C LEVEL
05 00 BB 18 E1 00D5 248 BBC #PSL$V_CURMOD,@PRC_L_SAVAP(R11),10$ ;IF CLR, PREVIOUS MODE SUPERVISO
6B F8 AA 7D 00DA 249 MOVQ WRK_L_SAVAP(R10),PRC_L_SAVAP(R11) ;RESTORE ARGUMENT AND FRAME POINTE
05 00DE 250 RSB ;
00DF 251 :
00DF 252 :
00DF 253 : PREVIOUS MODE SUPERVISOR
00DF 254 :
00DF 255 :
8E D5 00DF 256 10$: TSTL (SP)+ ;REMOVE RETURN FROM STACK
00E1 257 STATUS NORMAL ;SET COMPLETION STATUS
05 00E8 258 RSB ;

```

```

00E9 260 .SBTTL SAVE/RESTORE IMAGE PRIVILEGES
00E9 261 :
00E9 262 : DCL$SAVE_PRIVS - SAVE PRIVILEGED IMAGE PRIVILEGES
00E9 263 : SET IMAGE PRIVILEGES TO PROCESS PRIVILEGES
00E9 264 : RESTORE_PRIVS - RESTORE PRIVILEGED IMAGE PRIVILEGES FROM
00E9 265 : SAVED COPY
00E9 266 :
00E9 267 : INPUTS:
00E9 268 :
00E9 269 : R11 = BASE ADDRESS OF PROCESS WORK AREA.
00E9 270 : PRC_Q_SAVEPRIV(R11) - SAVED IMAGE PRIVILEGE TO BE USED BY
00E9 271 : RESTORE_PRIVS
00E9 272 :
00E9 273 : OUTPUTS:
00E9 274 :
00E9 275 : R0,R1,R2 DESTROYED OTHERS PRESERVED
00E9 276 : PRC_Q_SAVEPRIV(R11) - PREVIOUS VALUE OF IMAGE PRIVILEGES
00E9 277 :
00E9 278 DCL$SAVE_PRIVS::
00E9 279 $SETPRV_S PRMFLG=#1,- :READ PROCESS PERMANENT PRIVILEGES
00E9 280 PRVPRV=PRC_Q_SAVEPRIV(R11)
00FA 281 RESTORE_PRIVS:
7E 01 CE 00FA 282 MNEGL #1,-(SP) :FORM MASK OF ALL PRIVS FOR DISABLE
7E 01 CE 00FD 283 MNEGL #1,-(SP)
52 7E 7E 0100 284 MOVAB -(SP),R2 :RESERVE 2ND MASK, R2 = ADR
0103 285 $SETPRV_S ENBFLG=#0,- :DISABLE ALL PROCESS PRIVILEGES
0103 286 PRVADR=8(R2),-
0103 287 PRVPRV=(R2) :SAVING OLD COPY
0113 288 $SETPRV_S ENBFLG=#1,- :ENABLE THE SAVED PRIVILEGES
0113 289 PRVADR=PRC_Q_SAVEPRIV(R11)
00E8 CB 62 7D 0124 290 MOVAB (R2),PRC_Q_SAVEPRIV(R11) :SAVE PREVIOUS PRIVILEGES
5E 10 C0 0129 291 ADDL #16,SP :CLEAN OFF 2 PRIV MASKS
05 012C 292 RSB

```

```

012D 294 .SBTTL RUN DOWN IMAGE AND INDIRECT LEVELS
012D 295 :+
012D 296 : DCL$RUNDOWN - RUN DOWN IMAGE AND INDIRECT LEVELS
012D 297 :
012D 298 : THIS SUBROUTINE IS CALLED TO CHECK WHETHER INDIRECT LEVELS SHOULD BE RUN DOWN
012D 299 : AND TO CLOSE RMS-32 FILES AND RUN DOWN THE PREVIOUS IMAGE.
012D 300 :
012D 301 : INPUTS:
012D 302 :
012D 303 : NONE.
012D 304 :
012D 305 : OUTPUTS:
012D 306 :
012D 307 : IF THE CURRENT LEVEL IS CONTROL Y/C, THEN ALL INDIRECT FILES ARE UNSTACKED.
012D 308 : IF THE PREVIOUS MODE WAS USER, THEN THE USER IMAGE EXIT HANDLERS ARE
012D 309 : EXECUTED. THE PREVIOUS IMAGE IS ALWAYS RUNDOWN.
012D 310 :-
012D 311 .ENABL LSB
012D 312
012D 313 DCL$RUNDWNI:: :RUN DOWN BUT PRESERVE INDIRECT LEVEL
50 A0'AF 9E 012D 314 MOVAB B*20$,R0 :SET EXIT HANDLER RETURN ADDRESS
04 11 0131 315 BRB 5$ :
0133 316
0133 317 DCL$RUNDOWN:: :RUN DOWN IMAGE AND INDIRECT LEVELS
50 96'AF 9E 0133 318 MOVAB B*10$,R0 :SET EXIT HANDLER RETURN ADDRESS
0137 319 5$: SETBIT PRC_V_DISABL,PRC_W_FLAGS(R11) :DISABLE CONTROL Y/C AST'S
60 68 AB 0B E5 013B 320 BBCC #PRC_V_YLEVEL,PRC_W_FLAGS(R11),20$ :IF CLR, NOT AT CONTROL Y/C LEVEL
50 50 DD 0140 321 PUSHL R0 :PUSH PROPER RETURN ADDRESS
4D 60 6B D0 0142 322 MOVL PRC_L_SAVAP(R11),R0 :GET ADDRESS OF PREVIOUS PSL
03 A0 C8 8F 8A 0149 323 BBC #PSL$V_CURMOD,(R0),10$ :IF CLR, PREVIOUS MODE SUPERVISOR
70 0000000'9F 9E 014E 324 BICB #<PSL$M_FPD!PSL$M_IP!PSL$M_CM>@-24,3(R0) :RESET BITS IN PSL
F8 A0 0980 8F 3C 0155 325 MOVAB @EXE$EXIT_IMAGE,=(R0) :SET USER RETURN ADDRESS
F4 AA 5E 5A C3 015B 326 MOVZWL #SS$ CLIFRTEXT,-8(R0) :SET EXIT CAUSE INTO SAVED R0
58 F8 AA 7D 0160 327 SUBL3 R10,SP,WRK_L_SAVSP(R10) :SAVE RELATIVE ADDRESS OF TOP OF STACK
6B 58 7D 0164 328 MOVQ WRK_L_SAVAP(R10),R8 :RETRIEVE PREVIOUS ARGUMENT AND FRAME POINTE
BA AA 5A C2 0167 330 SUBL R10,WRK_L_RSLNXT(R10) :SAVE IN PROCESS WORK AREA
B6 AA 5A C2 016B 331 SUBL R10,WRK_L_RSLEND(R10) :CONVERT PARSE POINTER TO RELATIVE ADDRESS
57 08 A0 9E 016F 332 MOVAB 8(R0),R7 :CONVERT END POINTER TO RELATIVE ADDRESS
57 5D C2 0173 333 SUBL FP,R7 :GET ADDRESS OF END OF ARGUMENT LIST + 4
5E 57 C2 0176 334 SUBL R7,SP :CALCULATE LENGTH OF CALL FRAME AND ARGLIST
6E 6D 57 28 0179 335 MOVC R7,(FP),(SP) :CALCULATE NEW TOP OF STACK ADDRESS
57 5D 5E C3 017D 336 SUBL3 SP,FP,R7 :MOVE CALL FRAME AND ARGUMENT LIST
5D 59 57 C3 0181 337 SUBL3 R7,R9,FP :CALCULATE LENGTH OF COMMAND BUFFER AND ARGL
6D 6E 57 28 0185 338 MOVC R7,(SP),(FP) :CALCULATE NEW TOP OF STACK ADDRESS
F4 A9 59 C0 0189 339 ADDL R9,WRK_L_SAVSP(R9) :COLLAPSE STACK REMOVING FIRST COMMAND CONTE
BA A9 59 C0 018D 340 ADDL R9,WRK_L_RSLNXT(R9) :CALCULATE NEW COMMAND STACK POINTER
B6 A9 59 C0 0191 341 ADDL R9,WRK_L_RSLEND(R9) :CONVERT PARSE POINTER TO REAL ADDRESS
04 0195 342 RET :CONVERT END POINTER TO REAL ADDRESS
0196 343 :RETURN TO EXE$EXIT IMAGE
5C AB D5 0196 344 10$: TSTL PRC_L_INDEPTH(R11) :INDIRECT LEVEL ZERO?
05 13 0199 345 BEQL 20$ :IF EQL YES
FE62' 30 019B 346 BSBW DCL$UNSTACK :UNSTACK INDIRECT LEVEL
F6 11 019E 347 BRB 10$ :
0E 78 AB 00 E5 01A0 348 20$: BBCC #PRC_V_IRUNDWN,PRC_B_IMGFLAG(R11),30$ :SKIP IF IMAGE ALREADY RUNDOWN
01A5 349 $RUNDWN_S #PSL$C_USER :RUN DOWN IMAGE (THE HARD WAY)
18 8A 01AE 350 BICB #<PRC_M_EXEONLY ! PRC_M_PRIV>,- :SINCE IMAGE IS NOW GONE

```

IMAGECTRL
V04-000

- IMAGE CONTROL
RUN DOWN IMAGE AND INDIRECT LEVELS

M 12

15-SEP-1984 23:53:05 VAX/VMS Macro V04-00
4-SEP-1984 23:41:00 [DCL.SRC]IMAGECTRL.MAR;1

Page 11
(8)

00AF CB

05 01B0 351
01B3 352
01B4 353

30\$:

RSB
.DSABL

PRC_B_FLAGS2(R11)

LSB

;NO NEED TO PROTECT IT
;

```

01B4 355      .SBTTL SHUT DOWN IMAGE
01B4 356      :
01B4 357      : DCL$SHUTDOWN - SHUT DOWN IMAGE
01B4 358      :
01B4 359      : THIS ROUTINE IS CALLED TO CLOSE ALL FILES OPENED BY THE JUST EXECUTED IMAGE
01B4 360      : AND TO CLOSE THE IMAGE ACTIVATION FILE.
01B4 361      :
01B4 362      : INPUTS:
01B4 363      :
01B4 364      :     R10 = BASE ADDRESS OF COMMAND WORK AREA.
01B4 365      :     R11 = BASE ADDRESS OF PROCESS WORK AREA.
01B4 366      :
01B4 367      : OUTPUTS:
01B4 368      :
01B4 369      :     ALL FILES OPENED BY THE JUST EXECUTED IMAGE ARE CLOSED BY CALLING RMS-32,
01B4 370      :     DATA RECORDS ARE SKIPPED IN THE INPUT STREAM, AND THE IMAGE FILE IS CLOSED.
01B4 371      :     IF ANY DATA RECORDS ARE SKIPPED, THE INPUT BUFFER POINTER IS ADJUSTED
01B4 372      :     AND EOL SET FOR THE LAST RECORD READ (FOR POSSIBLE FUTURE DCL$FLUSH
01B4 373      :     OPERATION).
01B4 374      :
01B4 375      :     R4 DESTROYED
01B4 376      :     R2 = NUMBER OF DATA RECORDS SKIPPED IN THE INPUT STREAM.
01B4 377      :
01B4 378      :
01B4 379      DCL$SHUTDOWN::
01B4 380      BSBB      DCL$RMSRUNDWN      : SHUT DOWN IMAGE
01B4 381      MOVL      PRC_L_INDINPRAB(R11),R3      : RUNDOWN RMS-32 FILES
01B4 382      MOVQ      RAB$W_RFA(R3),-(SP)      : GET ADDRESS OF INDIRECT RAB
01B4 383      BBS      #DEV$V_REC,RAB$L_CTX(R3),30$      : SAVE RFA OF LAST COMMAND
01B4 384      BITB      #PRC_M_CHAIN!PRC_M_CMD,-      : IF SET, RECORD ORIENTED DEVICE
01B4 385      PRC_B_FLAGS2(R11)      : CHAIN A/O COMMAND?
01B4 386      BNEQ      30$-      :
01B4 387      SETBIT    RAB$V_PPF_IND,RAB$W_ISI(R3)      : NO SKIP IF EITHER IS PENDING
01B4 388      INCL      R2      : CONVERT TO NONPRIVILEGED ISI
01B4 389      $GET      RAB=(R3)      : INCREMENT NUMBER OF RECORDS SKIPPED
01B4 390      BLBC      R0,25$      : GET NEXT RECORD FROM INDIRECT FILE
01B4 391      MOVZWL    RAB$W_RSZ(R3),R4      : IF LBC FINISHED
01B4 392      BRB      20$      : SAVE LENGTH OF RECORD
01E3 393      :
01E3 394      25$:    CLRBIT    RAB$V_PPF_IND,RAB$W_ISI(R3)      : CONVERT BACK TO PRIVILEGED ISI
01E8 395      DECL      R2      : ADJUST FOR LAST RECORD
01EA 396      BEQL      30$      : SKIP IF NO RECORDS READ IN
01EC 397      MOVAB    @RAB$L_RBF(R3)[R4],R4      : GET ADDR. OF END OF LAST RECORD
01F1 398      CLRB      (R4)      : SET EOL IN BUFFER
01F3 399      MOVAB    -1(R4),WRK_L_CHARPTR(R10)      : ADJUST 'GET CHARACTER' POINTER
01F9 400      :
01F9 401      30$:    MOVQ      (SP)+,RAB$W_RFA(R3)      : RESTORE RFA OF LAST COMMAND
01FD 402      RSB      :
01FE 403      :

```

```

53 14 AB 10
7E 10 A3 7D
36 18 A3 00 E0
03 93 01C3
00AF CB 01C5
2F 12 01C8
52 D6 01CA
01CF 388 20$:
01D1 389
54 06 50 E9 01DA
22 A3 3C 01DD
EC 11 01E1
01E3 393
52 D7 01E8
0D 13 01EA
54 28 B344 9E 01EC
64 94 01F1
F48E CA FF A4 9E 01F3
10 A3 8E 7D 01F9
05 01FD 402
01FE 403

```

```

01FE 405 .SBTTL RMS RUNDOWN AN IMAGE
01FE 406 :+
01FE 407 : DCL$RMSRUNDWN - RMS RUNDOWN AN IMAGE
01FE 408 :
01FE 409 : THIS ROUTINE IS CALLED TO CLOSE ALL FILES OPENED BY THE JUST EXECUTED IMAGE
01FE 410 : AND TO CLOSE THE IMAGE ACTIVATION FILE.
01FE 411 :
01FE 412 : INPUTS:
01FE 413 :
01FE 414 : NONE
01FE 415 :
01FE 416 : OUTPUTS:
01FE 417 :
01FE 418 : ALL FILES OPENED BY THE JUST EXECUTED IMAGE ARE CLOSED BY CALLING RMS-32,
01FE 419 : DATA RECORDS ARE SKIPPED IN THE INPUT STREAM, AND THE IMAGE FILE IS CLOSED.
01FE 420 :
01FE 421 :-
01FE 422 :
01FE 423 DCL$RMSRUNDWN:: ;RMS RUNDOWN THE IMAGE
        BSBW DCL$ALLOCBUF ;ALLOCATE BUFFER AND DESCRIPTOR
        10$: MOVZBL #WRK_C_MSGBUFSIZ,(R2) ;RESET SIZE OF MESSAGE BUFFER
        PUSHL #0 ;RUN DOWN ONLY IMAGE FILES
        PUSHAB (R2) ;SET ADDRESS OF MESSAGE BUFFER DESCR
        CALLS #2,@#SYSS$RMSRUNDWN ;RUNDOWN RMS-32 FILES
        BLBC R0,10$ ;IF RUNDOWN FAILURE CONTINUE WITH NE
        MOVAB WRK_C_MSGBUFSIZ+8(SP),SP ;DEALLOCATE MESSAGE BUFFER AND DESCR
        CLRL R2 ;CLEAR COUNT OF RECORDS SKIPPED
        RSB ;RETURN
01FE 424
01FE 425
01FE 426
01FE 427
01FE 428
01FE 429
01FE 430
01FE 431
01FE 432
01FE 433
01FE 434 .END

```

<pre> FDFF' 30 62 84 8F 9A 00 DD 00000000'9F 02 FB EE 50 E9 SE 008C CE 9E 52 D4 05 021A 021B 433 021B 434 </pre>	<pre> 01FE 424 0201 425 0205 426 0207 427 0209 428 0210 429 0213 430 0218 431 021A 432 021B 433 021B 434 </pre>
--	---

IMAGECTRL
Symbol table

- IMAGE CONTROL

K 12

15-SEP-1984 23:53:05 VAX/VMS Macro V04-00
4-SEP-1984 23:41:00 [DCL.SRC]IMAGECTRL.MAR;1

```

SS.TMP1          = 00000001
SS.TMP2          = 00000063
CLIS_IVVALU     = 00038088
CLIS_NORMAL     = 00030001
CTLSGL_CLINTOWN ***** X 02
CTLSGL_DCLPRSOWN ***** X 02
DCL$ABORT       ***** X 02
DCL$ALLOCBUF    ***** X 02
DCL$CONTINUE    00000010 RG 02
DCL$DEBUG       0000001D RG 02
DCL$GETDVAL     ***** X 02
DCL$SRMSRUNDWN 000001FE RG 02
DCL$SRUNDOWN    00000133 RG 02
DCL$SRUNDWNI    0000012D RG 02
DCL$SAVE_PRIVS 000000E9 RG 02
DCL$SHUTDOWN    000001B4 RG 02
DCL$STOP        0000003F RG 02
DCL$UNSTACK     ***** X 02
DEVS$V_REC      = 00000000
EXE$EXIT_IMAGE ***** X 02
EXE$REFLECT     ***** X 02
HEXTAB         00000000 R 02
PPD$B_NPROCS    0000001C
PPD$C_LENGTH    00000168
PPD$K_LENGTH    00000168
PPD$L_INPDEV    00000044
PPD$L_LGI       00000014
PPD$L_LSTSTATUS 00000018
PPD$L_OUTDEV    00000064
PPD$L_PRC       00000008
PPD$Q_CLIREG    00000004
PPD$Q_CLISYMTBL 0000000C
PPD$T_FILENAME 00000068
PPD$T_INPDVI   00000028
PPD$T_OUTDVI   00000048
PPD$W_FLAGS    00000002
PPD$W_INPCHAN  0000001E
PPD$W_INPDID   0000003E
PPD$W_INPFID   00000038
PPD$W_INPFI    00000020
PPD$W_INPISI   00000022
PPD$W_OUTDID   0000005E
PPD$W_OUTFID   00000058
PPD$W_OUTIFI   00000024
PPD$W_OUTISI   00000026
PPD$W_SIZE     00000000
PRC_B_CONTINUE 000000F3
PRC_B_DEFRADIX 000000AE
PRC_B_EXMDEPMOD 000000AD
PRC_B_EXMDEPWID 000000AC
PRC_B_EXONLYL  0000012D
PRC_B_FLAGS2    000000AF
PRC_B_IMGFLAG   00000078
PRC_B_OUTFLAGS 0000012C
PRC_B_PROMPTLEN 000000F0
PRC_C_LENGTH    00000534
PRC_G_COMMANDS 00000133

```

```

PRC_G_PROMPT    000000F4
PRC_K_LENGTH    00000534
PRC_L_CURRKEY   00000048
PRC_L_EXMDEPADR 000000A8
PRC_L_EXTARG    00000094
PRC_L_EXTBLK    0000008C
PRC_L_EXTCOD    0000009C
PRC_L_EXTHND    00000090
PRC_L_EXTPRM    00000098
PRC_L_IDFLNK    000000BC
PRC_L_IMGACTSTS 00000080
PRC_L_INDCLOCK  0000007C
PRC_L_INDEPTH   0000005C
PRC_L_INDFAB    0000001C
PRC_L_INDIRPRAB 00000014
PRC_L_INDOUTRAB 00000018
PRC_L_INPRAB    00000008
PRC_L_LASTKEY   0000004C
PRC_L_LSTSTATUS 000000B0
PRC_L_ONCTLY    000000B8
PRC_L_ONERROR   0000006C
PRC_L_OUTOFBAND 000000B4
PRC_L_OUTRAB    0000000C
PRC_L_OUTRABCTX 00000118
PRC_L_PPFLIST   00000070
PRC_L_RECALLPTR 0000012F
PRC_L_RESTART   00000058
PRC_L_SAVAP     00000000
PRC_L_SAVFP     00000004
PRC_L_SEVERITY  00000050
PRC_L_SPWN      000000C0
PRC_L_STACKLMB 000000A4
PRC_L_STACKPT   000000A0
PRC_L_STATUS    00000054
PRC_L_STS       00000084
PRC_L_STV       00000088
PRC_L_SYMBOL    00000060
PRC_L_TMBX      00000074
PRC_L_TRMLIST   00000010
PRC_M_CHAIN     = 00000002
PRC_M_CMD       = 00000001
PRC_M_EXEONLY   = 00000008
PRC_M_PRIV      = 00000010
PRC_Q_ALLOCREG  00000020
PRC_Q_COMMAND   000000E0
PRC_Q_FLUSHTIME 000000D0
PRC_Q_GLOBAL    00000028
PRC_Q_IMAGENAME 000000D8
PRC_Q_KEYPAD    00000040
PRC_Q_LABEL     00000030
PRC_Q_LOCAL     00000038
PRC_Q_SAVEPRIV  000000E8
PRC_T_OUTDVI    0000011C
PRC_V_DISABL    = 00000002
PRC_V_IRUNDWN   = 00000000
PRC_V_MODE      = 00000006
PRC_V_PRIV      = 00000004

```

IMAGECTRL
Symbol table

- IMAGE CONTROL

L 12

15-SEP-1984 23:53:05 VAX/VMS Macro V04-00
4-SEP-1984 23:41:00 [DCL.SRC]IMAGECTRL.MAR;1

Page 15
(10)

```

PRC_V_YLEVEL          = 0000000B
PRC_W_ASTIOSB         = 000000C6
PRC_W_ASTRETN        = 000000C8
PRC_W_ASTSTATUS      = 000000C4
PRC_W_ATTMBX         = 0000007A
PRC_W_FLAGS          = 00000068
PRC_W_INPCHAN        = 00000064
PRC_W_ONLEVEL        = 0000006A
PRC_W_OUTIFI         = 00000114
PRC_W_OUTISI         = 00000116
PRC_W_OUTMBXCHN      = 000000CA
PRC_W_OUTMBXREF      = 000000CE
PRC_W_OUTMBXSIZ      = 000000CC
PRC_W_PMPTCTRL       = 000000F1
PRC_W_WAITIOSB       = 00000066
PSL$C_SUPER          = = 00000002
PSL$C_USER           = = 00000003
PSL$M_CM             = = 80000000
PSL$M_FPD            = = 08000000
PSL$M_TP             = = 40000000
PSL$V_CURMOD         = = 00000018
PSL$V_PRVMOD         = = 00000016
PTR_B_LEVEL          = 00000004
PTR_B_NUMBER         = 00000005
PTR_B_PARMCNT        = 000000C6
PTR_B_VALUE          = 00000000
PTR_C_LENGTH         = 0000000C
PTR_K_COMDQUAL       = = 00000000
PTR_K_ENDLINE        = = 00000004
PTR_K_LENGTH         = 0000000C
PTR_L_DESCR          = 00000000
PTR_L_ENTITY         = 00000008
RAB$L_CTX            = = 00000018
RAB$L_RBF            = = 00000028
RAB$V_PPF_IND        = = 0000000E
RAB$W_ISI            = = 00000002
RAB$W_RFA            = = 00000010
RAB$W_RSZ            = = 00000022
RESTORE PRIVS        = 000000FA R    02
SS$CLIFRCEXT         = = 00000980
SS$DEBUG             = = 0000046C
SYS$DELPRC           = ***** GX    02
SYS$GET              = ***** GX    02
SYS$RMSRUNDWN        = ***** X    02
SYS$RUNDWN           = ***** GX    02
SYS$SETPRV           = ***** GX    02
TESTMODE             = 000000CC R    02
WRK_B_CMDOPT         = FFFFFFFC3
WRK_B_MAXPARM        = FFFFFFFD0
WRK_B_MINPARM        = FFFFFFFD1
WRK_B_PARMCNT        = FFFFFFFCE
WRK_B_PARMSUM        = FFFFFFFCF
WRK_B_RECALLCNT      = FFFFFFFC5
WRK_B_VALLEV         = FFFFFFFC4
WRK_B_VERBTYP        = FFFFFFFC2
WRK_C_LENGTH         = FFFFF486
WRK_C_MSGBUFSIZ     = = 00000084

```

```

WRK_G_BUFFER         = FFFFF492
WRK_G_INPBUF         = FFFFF896
WRK_G_RESULT         = FFFFF9B6
WRK_K_LENGTH         = FFFFF486
WRK_L_CHARPTR        = FFFFF48E
WRK_L_DISALLOW       = FFFFFFFE6
WRK_L_ERRORRTN       = FFFFF9AE
WRK_L_EXPANDPTR      = FFFFF486
WRK_L_IMAGE          = FFFFFFFE2
WRK_L_MARKPTR        = FFFFF48A
WRK_L_PAROUT         = FFFFFFFD2
WRK_L_PMPTADDR       = FFFFF9A2
WRK_L_PROMPTRN       = FFFFF9A6
WRK_L_PROPTR         = FFFFFFFC6
WRK_L_QUABLK         = FFFFFFFCA
WRK_L_READRTN        = FFFFF9AA
WRK_L_RECALLPTR      = FFFFFFFEA
WRK_L_RSLEND         = FFFFFFFB6
WRK_L_RSLNXT         = FFFFFFFBA
WRK_L_SAVAP          = FFFFFFFF8
WRK_L_SAVFP          = FFFFFFFFC
WRK_L_SAVSP          = FFFFFFFF4
WRK_L_SIGNALRTN      = FFFFFFFD6
WRK_L_SPECRTN        = FFFFF9B2
WRK_L_TAB_VEC        = FFFFFFFDE
WRK_L_VERB           = FFFFFFFBE
WRK_W_FLAGS          = FFFFFFFF0
WRK_W_FLAGS2         = FFFFFFFF2
WRK_W_IMGCHAN        = FFFFFFFEE
WRK_W_PMPTLEN        = FFFFF99E
_$$_                 = 000000EF

```

! Psect synopsis !

PSECT name	Allocation	PSECT No.	Attributes
. ABS .	00000000 (0.)	00 (0.)	NOPIC USR CON ABS LCL NOSHR NOEXE NORD NOWRT NOVEC BYTE
\$ABSS	FFFFFFFFC (0.)	01 (1.)	NOPIC USR CON ABS LCL NOSHR EXE RD WRT NOVEC BYTE
DCL\$ZCODE	0000021B (539.)	02 (2.)	NOPIC USR CON REL LCL NOSHR EXE RD NOWRT NOVEC BYTE

! Performance indicators !

Phase	Page faults	CPU Time	Elapsed Time
Initialization	11	00:00:00.05	00:00:00.97
Command processing	88	00:00:00.70	00:00:06.64
Pass 1	318	00:00:12.28	00:00:43.86
Symbol table sort	0	00:00:01.66	00:00:06.20
Pass 2	85	00:00:02.20	00:00:08.02
Symbol table output	23	00:00:00.20	00:00:00.72
Psect synopsis output	2	00:00:00.03	00:00:00.10
Cross-reference output	0	00:00:00.00	00:00:00.00
Assembler run totals	527	00:00:17.12	00:01:06.52

The working set limit was 1350 pages.
62782 bytes (123 pages) of virtual memory were used to buffer the intermediate code.
There were 60 pages of symbol table space allocated to hold 1143 non-local and 19 local symbols.
434 source lines were read in Pass 1, producing 14 object records in Pass 2.
43 pages of virtual memory were used to define 28 macros.

! Macro library statistics !

Macro library name	Macros defined
-\$255\$DUA28:[SYSLIB]SYSBLDMLB.MLB;1	0
-\$255\$DUA28:[DCL.OBJ]DCL.MLB;1	9
-\$255\$DUA28:[SYS.OBJ]LIB.MLB;1	0
-\$255\$DUA28:[SYSLIB]STARLET.MLB;2	13
TOTALS (all libraries)	22

1370 GETS were required to define 22 macros.

There were no errors, warnings or information messages.

MACRO/LIS=LIS\$:IMAGECTRL/OBJ=OBJ\$:IMAGECTRL MSRC\$:IMAGECTRL/UPDATE=(ENH\$:IMAGECTRL)+EXECML\$/LIB+LIB\$:DCL/LIB+SYSS\$LIBRARY:SYSBLDMLB/L

0070

AH-BT13A-SE
VAX/VMS V4.0

DIGITAL EQUIPMENT CORPORATION
CONFIDENTIAL AND PROPRIETARY

Table with multiple columns of data, including headers like 'GETKEYNAM', 'GOTO', 'EXPRESS LIS', 'HANDLE LIS', 'IMAGECTRL LIS', 'INITIAL LIS', 'INDIRECT LIS', 'FILECMDS LIS', and 'IMAGEXECT LIS'.