


```

IIIIII  NN    NN    IIIIII  TTTTTTTTTT  TTTTTTTTTT  AAAAAA  PPPPPPPP  EEEEEEEEE
IIIIII  NN    NN    IIIIII  TTTTTTTTTT  TTTTTTTTTT  AAAAAA  PPPPPPPP  EEEEEEEEE
  II    NN    NN    II      TT           TT           AA      AA  PP      PP  EE
  II    NN    NN    II      TT           TT           AA      AA  PP      PP  EE
  II    NN    NN    II      TT           TT           AA      AA  PP      PP  EE
  II    NNNN  NN    II      TT           TT           AA      AA  PP      PP  EE
  II    NNNN  NN    II      TT           TT           AA      AA  P        P  EE
  II    NN   NN  NN    II      TT           TT           AA      AA  P        P  EE
  II    NN   NN  NN    II      TT           TT           AA      AA  P        P  EE
  II    NN   NN  NN    II      TT           TTTTTTTTTT  P        P  EE
  II    NN   NN  NN    II      TT           TTTTTTTTTT  P        P  EE
  II    NN   NN  NN    IIIIII  TTTTTTTTTT  P        P  EE
  II    NN   NN  NN    IIIIII  TTTTTTTTTT  P        P  EE
IIIIII  NN    NN    IIIIII  TTTTTTTTTT  P        P  EE
IIIIII  NN    NN    IIIIII  TTTTTTTTTT  AA      AA  P        P  EEEEEEEEE
            .....
            .....
            .....
            .....

```

```

LL      IIIIII  SSSSSSSS
LL      IIIIII  SSSSSSSS
LL      II      SS
LL      II      SS
LL      II      SS
LL      II      SS
LL      II      SSSSSS
LL      II      SSSSSS
LL      II      SS
LL      II      SS
LL      II      SS
LLLLLLLLLL  IIIIII  SSSSSSSS
LLLLLLLLLL  IIIIII  SSSSSSSS

```


Subroutine ERFTAPINI (Array_addr, Array_size)

```
0001
0002
0003 C
0004 C Version: 'V04-000'
0005 C
0006 C*****
0007 C*
0008 C* COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
0009 C* DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
0010 C* ALL RIGHTS RESERVED.
0011 C*
0012 C* THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
0013 C* ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
0014 C* INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
0015 C* COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
0016 C* OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
0017 C* TRANSFERRED.
0018 C*
0019 C* THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
0020 C* AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
0021 C* CORPORATION.
0022 C*
0023 C* DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
0024 C* SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
0025 C*
0026 C*
0027 C*****
0028 C
0029 C
0030 C
0031 C AUTHOR: Elliott A. Drayton CREATION DATE: 27-Jan-1983
0032 C
0033 C Functional description:
0034 C
0035 C This is the initialization module for the loadable image ERFTAPE.EXE.
0036 C After ERFTAPE has been loaded this routine is called to return
0037 C the information from it tables. These tables specify which error
0038 C log packets this loadable image will process. The tables consist of:
0039 C
0040 C ENTRY TYPE, DEVICE CLASS, MODULE VERSION, TRANSFER VECTOR OFFSET
0041 C
0042 C The ENTRY TYPE value is the packet type identifier for the packets that
0043 C this loadable image will process.
0044 C
0045 C The DEVICE CLASS value specifies the class of the packet that will
0046 C be process by this loadable image.
0047 C
0048 C The MODULE VERSION is used to determine if the module in this image
0049 C is the one to use. This is accomplished by the root image comparing
0050 C this value against the value in the master tables in the root image.
0051 C
0052 C The TRANSFER VECTOR OFFSET is the index to the transfer vector to
0053 C be used for a specific device or entry type. For example, the transfer
0054 C vectors for the disk image are ordered as:
0055 C
0056 C INITDISK 0 ! a routine similar to this one
0057 C MASSDISK 1 ! a device specific routine
```

I 14
16-Sep-1984 00:04:44
5-Sep-1984 13:58:54

VAX-11 FORTRAN V3.4-56
DISK\$VMSMASTER:[ERF.SRC]INIT_TAPE.FOR;1

0058 C RKDISK 2
0059 C RLDISK 3
0060 C ECT.
0061 C
0062 C Modified by:
0063 C
0064 C**


```

0065      Parameter DCS_TAPE = '00000002'X
0066      !
0067      TAPE DEVICES
0068      !
0069      PARAMETER DTS_TE16 = '00000001'X      ! TE16 MAGTAPE
0070      PARAMETER DTS_TU45 = '00000002'X      ! TU45 MAGTAPE
0071      PARAMETER DTS_TU77 = '00000003'X      ! TU77 MAGTAPE
0072      PARAMETER DTS_TS11 = '00000004'X      ! TS11 MAGTAPE
0073      PARAMETER DTS_TU78 = '00000005'X      ! TU78 MAGTAPE
0074      PARAMETER DTS_TA78 = '00000006'X      ! TA78 MAGTAPE
0075      PARAMETER DTS_TU80 = '00000007'X      ! TU80 MAGTAPE
0076      PARAMETER DTS_TU81 = '00000008'X      ! TU81 MAGTAPE
0077      PARAMETER DTS_TA81 = '00000009'X      ! TA81 MAGTAPE
0078
0079      Parameter V1 = 1                        ! device module version number
0080
0081      Parameter      Maxtypes = 5
0082
0083      Integer*4      Array_addr, Array_size
0084
0085      Integer*2      Tape_codes ( 4 * Maxtypes )
0086
0087      Data           Tape_codes /
0088      1 DTS_TE16, DCS_TAPE, V1, 1,      ! TE16 MAGTAPE
0089      2 DTS_TU45, DCS_TAPE, V1, 1,      ! TU45 MAGTAPE
0090      3 DTS_TU77, DCS_TAPE, V1, 1,      ! TU77 MAGTAPE
0091      4 DTS_TS11, DCS_TAPE, V1, 2,      ! TS11 MAGTAPE
0092      5 DTS_TU78, DCS_TAPE, V1, 3,      ! TU78 MAGTAPE
0093
0094      ! The following devices are handled by ERFPROC1.EXE:
0095      !
0096      !
0097      !
0098      !
0099      !
0100      Array_addr = %LOC (Tape_codes(1))
0101      Array_size = Maxtypes
0102
0103      Return
0104      End

```

PROGRAM SECTIONS

| Name | Bytes | Attributes |
|-----------------------|-------|---|
| 0 \$CODE | 19 | PIC CON REL LCL SHR EXE RD NOWRT LONG |
| 2 \$LOCAL | 40 | PIC CON REL LCL NOSHR NOEXE RD WRT LONG |
| Total Space Allocated | 59 | |

ENTRY POINTS

| Address | Type | Name |
|------------|------|-----------|
| 0-00000000 | | ERFTAPINI |

VARIABLES

| Address | Type | Name | Address | Type | Name |
|--------------|------|------------|--------------|------|------------|
| AP-00000004@ | I*4 | ARRAY_ADDR | AP-00000008@ | I*4 | ARRAY_SIZE |

ARRAYS

| Address | Type | Name | Bytes | Dimensions |
|------------|------|------------|-------|------------|
| 2-00000000 | I*2 | TAPE_CODES | 40 | (20) |

COMMAND QUALIFIERS

FORTRAN /LIS=LISS:INIT_TAPE/OBJ=OBJ\$:INIT_TAPE MSRCS:INIT_TAPE

/CHECK=(NOBOUNDS,OVERFLOW,NOUNDERFLOW)

/DEBUG=(NOSYMBOLS,TRACEBACK)

/STANDARD=(NOSYNTAX,NOSOURCE FORM)

/SHOW=(NOPREPROCESSOR,NOINCLUDE,MAP)

/F77 /NOG_FLOATING /I4 /OPTIMIZE /WARNINGS /NOD_LINES /NOCROSS_REFERENCE /NOMACHINE_CODE /CONTINUATIONS=19

COMPILATION STATISTICS

Run Time: 0.79 seconds
 Elapsed Time: 3.20 seconds
 Page Faults: 85
 Dynamic Memory: 155 pages

