

Val  
---  
001  
001  
001  
001  
001  
001  
001  
001  
7FF  
7FF  
7FF  
7FF  
7FF  
7FF  
7FF  
7FF

SSSSSSSSSSSSSS	MMM	MMM	GGGGGGGGGGGG	RRRRRRRRRRRR	TTTTTTTTTTTTTT	LLL			
SSSSSSSSSSSSSS	MMM	MMM	GGGGGGGGGGGG	RRRRRRRRRRRR	TTTTTTTTTTTTTT	LLL			
SSSSSSSSSSSSSS	MMM	MMM	GGGGGGGGGGGG	RRRRRRRRRRRR	TTTTTTTTTTTTTT	LLL			
SSS	MMMMMM	MMMMMM	GGG	RRR	RRR	TTT	LLL		
SSS	MMMMMM	MMMMMM	GGG	RRR	RRR	TTT	LLL		
SSS	MMMMMM	MMMMMM	GGG	RRR	RRR	TTT	LLL		
SSS	MMM	MMM	MMM	GGG	GGG	GGG	TTT	LLL	
SSS	MMM	MMM	MMM	GGG	GGG	GGG	TTT	LLL	
SSS	MMM	MMM	MMM	GGG	GGG	GGG	TTT	LLL	
SSS	MMM	MMM	MMM	GGG	GGG	GGG	TTT	LLL	
SSSSSSSSSS	MMM	MMM	GGG	RRRRRRRRRRRR	RRR	RRR	TTT	LLL	
SSSSSSSSSS	MMM	MMM	GGG	RRRRRRRRRRRR	RRR	RRR	TTT	LLL	
SSSSSSSSSS	MMM	MMM	GGG	RRRRRRRRRRRR	RRR	RRR	TTT	LLL	
SSS	MMM	MMM	GGG	GGGGGGGGGG	RRR	RRR	RRR	TTT	LLL
SSS	MMM	MMM	GGG	GGGGGGGGGG	RRR	RRR	RRR	TTT	LLL
SSS	MMM	MMM	GGG	GGGGGGGGGG	RRR	RRR	RRR	TTT	LLL
SSS	MMM	MMM	GGG	GGG	RRR	RRR	RRR	TTT	LLL
SSS	MMM	MMM	GGG	GGG	RRR	RRR	RRR	TTT	LLL
SSS	MMM	MMM	GGG	GGG	RRR	RRR	RRR	TTT	LLL
SSSSSSSSSSSSSS	MMM	MMM	GGGGGGGGGG	RRR	RRR	RRR	TTT	LLLLLLLLLLLLLLLL	
SSSSSSSSSSSSSS	MMM	MMM	GGGGGGGGGG	RRR	RRR	RRR	TTT	LLLLLLLLLLLLLLLL	
SSSSSSSSSSSSSS	MMM	MMM	GGGGGGGGGG	RRR	RRR	RRR	TTT	LLLLLLLLLLLLLLLL	

```

SSSSSSSS MM MM GGGGGGGG MM MM SSSSSSSS GGGGGGGG PPPPPPPP TTTTTTTTTT RRRRRRRR
SSSSSSSS MM MM GGGGGGGG MM MM SSSSSSSS GGGGGGGG PPPPPPPP TTTTTTTTTT RRRRRRRR
SS MMMM MMMM GG MM MM SSSSSSSS GG GGGGGG PP PP TT RR RR
SS MMMM MMMM GG MM MM SSSSSSSS GG GGGGGG PP PP TT RR RR
SS MM MM MM GG MM MM SSSSSSSS GG GGGGGG PP PP TT RR RR
SSSSSSS MM MM GG MM MM SSSSSSSS GG GGGGGG PP PP TT RRRRRRRR
SSSSSSS MM MM GG MM MM SSSSSSSS GG GGGGGG PP PP TT RRRRRRRR
SS MM MM MM GG GGGGGG MM MM SSSSSSSS GG GGGGGG PP TT RR
SS MM MM MM GG GGGGGG MM MM SSSSSSSS GG GGGGGG PP TT RR
SS MM MM MM GG GG MM MM SSSSSSSS GG GGGGGG PP TT RR
SS MM MM MM GG GG MM MM SSSSSSSS GG GGGGGG PP TT RR
SSSSSSSS MM MM GGGGGG MM MM SSSSSSSS GGGGGG PP PP TT RR
SSSSSSSS MM MM GGGGGG MM MM SSSSSSSS GGGGGG PP PP TT RR

```

```

LL          IIIIII SSSSSSSS
LL          IIIIII SSSSSSSS
LL          II      SS
LL          II      SS
LL          II      SS
LL          II      SS
LL          II      SSSSSS
LL          II      SSSSSS
LL          II      SS
LL          II      SS
LL          II      SS
LL          II      SS
LLLLLLLLLL IIIIII SSSSSSSS
LLLLLLLLLL IIIIII SSSSSSSS

```

```

1
2
3 .TITLE SMG$MSGDEF SMG$ facility messages
4 .IDENT '1-026' ! File: SMGMSG.MSG Edit: PLL1026
5
6 *****
7 *
8 * COPYRIGHT (c) 1978, 1980, 1982, 1984 BY *
9 * DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS. *
10 * ALL RIGHTS RESERVED. *
11 *
12 * THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED *
13 * ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE *
14 * INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER *
15 * COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY *
16 * OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY *
17 * TRANSFERRED. *
18 *
19 * THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE *
20 * AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT *
21 * CORPORATION. *
22 *
23 * DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS *
24 * SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL. *
25 *
26 *****
27
28
29 1-026 Add comments for my messages. PLL 23-Apr-1984
30 1-025 Add comments concerning user actions. STAN 9-Apr-1984.
31 1-024 Add TRMNOTANS. PLL 6-Apr-1984
32 1-023 Change wording for STRTERESC. STAN 22-Mar-1984.
33 1-022 Add INVDIR. PLL 15-Mar-1984
34 1-021 More messages for the termtable compiler. PLL 1-Mar-1984
35 1-020 Add back in NOMOREKEYS. LEB 22-Feb-1984
36 1-019 Add UNDTERTYP. PLL 9-Feb-1984
37 1-018 Added FAIOPEFIL. PLL 2-Feb-1984
38 1-017 Add INVEXP. PLL 19-Jan-1984
39 1-016 More messages for ft support. PLL 19-Jan-1984
40 1-015 Add SMG$ EXCTABSIZ and SMG$ MISTERNAM. PLL 8-Dec-1983
41 1-014 More messages for foreign terminal support. PLL 29-Nov-1983
42 1-013 Add messages for foreign terminal support. PLL 16-Nov-1983
43 1-012 Add warning message (no change in virtual display). PLL 11-Oct-1983
44 1-011 Add line drawing message (diagonal line not allowed). PLL 26-Sep-1983
45 1-010 More of same. STAN 25-Aug-1983.
46 1-009 Change pasteboard characteristics messages. STAN 22-Aug-1983.
47 1-008 File error messages. STAN 18-Jun-1983.
48 1-007 Mailbox messages. STAN 13-Jun-1983.
49 1-006 Add NOT A TRM. STAN 1-Jun-1983.
50 1-005 Add PASTLREXI. RKR 25-May-1983.
51 1-004 Add STRTERESC. PLL 4-May-1983
52 1-003 Some messages having to do with batching. STAN 3-May-1983
53 1-002 Add messages for input. SBL 25-Mar-1983
54 1-001 Original. PLL 16-Mar-1983
55
56

```

57 |  
58 | + Symbols are defined following the standard for global names:  
59 |  
60 |       SMGS\_abcmnoxyz  
61 |  
62 | In addition, the library standards specify that the letters 'abc', 'mno',  
63 | and 'xyz' are the first three letters of the first three words of the error  
64 | message, not counting articles and prepositions.  
65 |  
66 | The names of all procedures using each error condition value should appear  
67 | in the comments included with each error definition.  
68 |  
69 |  
70 | MACRO-32 Programming:  
71 |  
72 | The macros call:  
73 |  
74 |       \$SMGDEF  
75 |  
76 | will cause all symbols to be made available to the module.  
77 | The Run-time Library declares these symbols as EXTERNAL;  
78 | the macros are provided only for the convenience of the user.  
79 |  
80 | -

```

81
82 | Template for documenting messages.
83 | Each explanation follows the message it applies to and
84 | is followed by a blank line.
85 | Be sure not to use the sequence "++" after a "!" in regular comments
86 | as this sequence begins a documentation sequence and can be
87 | searched for if and when the process of extracting the
88 | documentation becomes automated.
89
90 | ++
91 | FACILITY:      SMG
92 | EXPLANATION:  x
93 | USER ACTION:  y
94 | --
95
96 | ; Set LH to 18 (decimal).
00000012 | .FACILITY      SMG,18 /SYSTEM
97 | .SEVERITY      SUCCESS
98
99
100 | .BASE          0
101
102 | NORMAL        <normal successful completion>
103 | ++
104 | FACILITY:      SMG
105 | EXPLANATION:  Normal successful completion.
106 | USER ACTION:  none
107 | --
108
109 | .BASE          2
110
10128001 | PREDEFREP     <previous key-definition replaced>
111 | ++
112 | FACILITY:      SMG
113 | EXPLANATION:  A previous key definition was replaced by a new
114 |               definition.
115 | USER ACTION:  none
116 | --
117
118
119 | +
120 | The next three messages are used by the "batching"
121 | procedures, SMG$BEGIN_DISPLAY_UPDATE and SMG$END_DISPLAY_UPDATE.
122 | The text of the messages should change if we decide not
123 | to publicly use the term "batching".
124 | -
125
10128019 | BATSTIPRO     <batching is still in progress>
126 | ++
127 | FACILITY:      SMG
128 | EXPLANATION:  A user tried to end batching (updating) with
129 |               a call to SMG$END_DISPLAY_UPDATE or
130 |               SMG$END_PASTEBBOARD_UPDATE. This did not
131 |               terminate batching because there were more calls
132 |               made to begin batching than to end batching.
133 | USER ACTION:  None. Some outer level routine probably still
134 |               wants batching to be in effect.
135 | --
136

```

```

00128021 137
          138      BATWASOFF      <batching was off>
          139      ++
          140      FACILITY:      SMG
          141      EXPLANATION:   A program tried to turn off batching when
          142      batching was already off.
          143      USER ACTION:   Probably none. Check that there was one call
          144      to turn on batching for each call to turn it off.
          145      --
00128029 146
          147      BATWAS_ON     <batching was on>
          148      ++
          149      FACILITY:      SMG
          150      EXPLANATION:   A program tried to turn on batching when
          151      batching was already on. This is normal in
          152      a modular environment.
          153      USER ACTION:   None. Check that there was one call
          154      to turn on batching for each call to turn it off.
          155      --
00128031 156
          157      PASALREXI     <pasteboard already exists for this device>
          158      ++
          159      FACILITY:      SMG
          160      EXPLANATION:   A user tried to create a pasteboard for a device,
          161      when one was already created. This is normal in
          162      a modular environment. The existing pasteboard id
          163      is returned.
          164      USER ACTION:   None. Make sure you don't delete a pasteboard
          165      that you actually didn't create.
          166      --
00128039 167
          168      NOT_A_TRM     <pasteboard attached to a device that is not a terminal>
          169      ++
          170      FACILITY:      SMG
          171      EXPLANATION:   This is an informational message telling you that
          172      the pasteboard has been created, but the output
          173      device is not a terminal.
          174      USER ACTION:   None.
          175      --
00128041 176
          177      NO_MORMSG     <no more broadcast messages are available>
          178      ++
          179      FACILITY:      SMG
          180      EXPLANATION:   A call to SMG$GET_BROADCAST_MESSAGE found that
          181      there were no more messages to be obtained.
          182      USER ACTION:   None.
          183      --
00128049 184
          185      WILUSERMS     <output will be performed by RMS later>
          186      ++
          187      FACILITY:      SMG
          188      EXPLANATION:   Normally the screen is updated at the end of
          189      every output operation. If, however, the 'device'
          190      is actually a file or an unknown terminal, then
          191      this message is given at the time output would
          192      have been sent to the screen.
          193      USER ACTION:   none

```

```

194      |
195      |
00128051 196      |NOTRMSOUT      <RMS is not being used to perform output>
197      |      ++
198      |      FACILITY:      SMG
199      |      EXPLANATION:  SMG$SNAPSHOT is used with files and unknown devices
200      |      |              to capture the contents of the pasteboard at various
201      |      |              times.  If SMG$SNAPSHOT is called for a pasteboard
202      |      |              associated with a video terminal, then it takes no
203      |      |              action and returns this informational message.
204      |      USER ACTION: none
205      |      |--
206      |
00128059 207      |NO_CHADIS      <no change in virtual display>
208      |      +--+
209      |      FACILITY:      SMG
210      |      EXPLANATION:  The requested number of columns to change was zero,
211      |      |              so nothing in the virtual display was changed.
212      |      USER ACTION: none
213      |      |--
214      |
00128061 215      |PRISECMAP      <private terminal table used>
216      |      ++
217      |      FACILITY:      SMG
218      |      EXPLANATION:  The requested terminal definition was found in
219      |      |              the caller's private copy of Termtable.
220      |      USER ACTION: none
221      |      |--
222      |
00128069 223      |GBLSECMAP      <system terminal table used>
224      |      ++
225      |      FACILITY:      SMG
226      |      EXPLANATION:  The requested terminal definition was found in
227      |      |              the system Termtable.  (Requested terminal definition
228      |      |              did not exist in the caller's private Termtable.)
229      |      USER ACTION: none
230      |      |--
231      |
232      |
233      |      .SEVERITY      FATAL
234      |      .BASE        64
235      |
00128204 236      |FATERRLIB      <fatal error in library>
237      |      ++
238      |      FACILITY:      SMG
239      |      EXPLANATION:  An internal error has occurred within SMG.
240      |      USER ACTION:  Submit an SPR describing the problem.
241      |      |--
242      |
0012820C 243      |INVARG        <invalid argument>
244      |      ++
245      |      FACILITY:      SMG
246      |      EXPLANATION:  The value of some argument is not in the correct range.
247      |      USER ACTION:  Examine each argument. Determine which one is
248      |      |              out of range and correct your program.
249      |      |--
250      |

```

```

00128214 251 INVCOL <invalid column>
          252 ++
          253 FACILITY: SMG
          254 EXPLANATION: An invalid column number was specified. It was either
          255 less than 0 or larger than the number of columns
          256 in the virtual display.
          257 USER ACTION: Specify a valid column number. Columns are numbered
          258 beginning with 1.
          259 --
          260
0012821C 261 INVDIS_ID <invalid display-id>
          262 ++
          263 FACILITY: SMG
          264 EXPLANATION: An invalid display-id was specified.
          265 USER ACTION: Check that you are passing the display id by reference
          266 not by value. Ensure that the display id was
          267 previously set up by a call to SMG$CREATE_VIRTUAL_DISPLAY.
          268 --
          269
00128224 270 INVPAS_ID <invalid pasteboard-id>
          271 ++
          272 FACILITY: SMG
          273 EXPLANATION: An invalid pasteboard id was specified.
          274 USER ACTION: Check that you are passing the pasteboard id by reference
          275 not by value. (A reference to a 0 is valid, since 0
          276 is a legal pasteboard id.) Ensure that the pasteboard
          277 was previously set up by a call to
          278 SMG$CREATE_PASTEBOARD and that the pasteboard has not
          279 been deleted.
          280 --
          281
0012822C 282 INVROW <invalid row>
          283 ++
          284 FACILITY: SMG
          285 EXPLANATION: An invalid row number was specified. It was either
          286 less than 0 or larger than the number of rows
          287 in the virtual display.
          288 USER ACTION: Specify a valid row number. Rows are numbered
          289 beginning with 1.
          290 --
          291
00128234 292 TOOMANDIS <too many displays>
          293 ++
          294 FACILITY: SMG
          295 EXPLANATION: An internal limit on the number of virtual displays
          296 that your program may have has been exceeded.
          297 The limit is currently 255. This includes any
          298 virtual displays that some outer routine may be using.
          299 This includes displays on all pasteboards.
          300 USER ACTION: Use fewer virtual displays.
          301 Make sure that your program is not in a loop
          302 creating virtual displays. Be sure that you delete
          303 a virtual display when you are all done with it.
          304 --
          305
0012823C 306 TOOMANPAS <too many pasteboards>
          307 ++
  
```



```

308 | FACILITY: SMG
309 | EXPLANATION: An internal limit on the number of pasteboards
310 |               that your program may have has been exceeded.
311 |               The limit is currently 16.
312 | USER ACTION: Use fewer pasteboards.
313 | --
00128244 314 |
315 | WRONUMARG <wrong number of arguments>
316 | ++
317 | FACILITY: SMG
318 | EXPLANATION: An SMG routine was called with too few arguments
319 |               (less than the number of required arguments)
320 |               or too many arguments.
321 | USER ACTION: Correct the code to call the routine with
322 |               the proper number of arguments.
323 | --
0012824C 324 |
325 | INVKBD_ID <invalid keyboard-id>
326 | ++
327 | FACILITY: SMG
328 | EXPLANATION: An invalid keyboard id was passed.
329 | USER ACTION: Check that you are passing the keyboard id by reference
330 |               not by value. Ensure that the keyboard id was
331 |               previously set up by a call to
332 |               SMG$CREATE_VIRTUAL_KEYBOARD.
333 | --
00128254 334 |
335 | INVKTBL_ID <invalid key-table-id>
336 | ++
337 | FACILITY: SMG
338 | EXPLANATION: An invalid key table id was passed.
339 | USER ACTION: Check that you are passing the key table id by reference
340 |               not by value. Ensure that the key table id was
341 |               previously set up by a call to
342 |               SMG$CREATE_KEY_TABLE.
343 | --
0012825C 344 |
345 | INVMAXLEN <invalid maximum length (greater than 512)>
346 | ++
347 | FACILITY: SMG
348 | EXPLANATION: The maximum length specified for an input string
349 |               was too long.
350 | USER ACTION: Correct your program so that it requests an input
351 |               string of 512 characters or less.
352 | --
00128264 353 |
354 | FILTOOLON <file-specification is too long (over 255 characters)>
355 | ++
356 | **** This message should be removed from here and from
357 | **** SMGKEYPAD.B32. It's referenced as an external but
358 | **** it's never used in the code. Be careful to make both
359 | **** edits at the same time (to avoid build problems).
360 | --
0012826C 361 |
362 | PROTOOLON <prompt-string is too long>
363 | ++
364 | FACILITY: SMG

```

```

365 | EXPLANATION: The length of a prompt string exceeded 512 characters.
366 | USER ACTION: Shorten the prompt to 512 characters or less.
367 | --
00128274 | 368
369 | NOTPASTED <given display is not pasted to given pasteboard>
370 | ++
371 | FACILITY: SMG
372 | EXPLANATION: An attempt was made to unpaste or move a display
373 | that was not pasted to the specified pasteboard.
374 | USER ACTION: Check that you are referencing the correct virtual
375 | display. Verify that the display has not been
376 | unpasted or that you forgot to paste it.
377 | --
0012827C | 378
379 | PBDIN_USE <operation invalid while pasteboard is buffered>
380 | ++
381 | FACILITY: SMG
382 | EXPLANATION: The operation you have tried to perform is not
383 | legal while output to the pasteboard is being batched.
384 | For example, you can't change the pasteboard
385 | characteristics while the pasteboard is batched.
386 | USER ACTION: Turn off pasteboard batching before attempting the
387 | operation. You may turn batching on again after the
388 | operation.
389 | --
00128284 | 390
391 | INVWIDARG <width of 0 is not permitted>
392 | ++
393 | FACILITY: SMG
394 | EXPLANATION: An attempt was made to change the characteristics
395 | of the terminal, setting it's width to 0.
396 | USER ACTION: Correct the code. A width of 0 is illegal.
397 | --
0012828C | 398
399 | INVPAARG <height of 0 is not permitted>
400 | ++
401 | FACILITY: SMG
402 | EXPLANATION: An attempt was made to change the characteristics
403 | of the terminal, setting it's height (page size) to 0.
404 | USER ACTION: Correct the code. A height of 0 is illegal.
405 | --
00128294 | 406
407 | INVCOLARG <unknown color specified>
408 | ++
409 | FACILITY: SMG
410 | EXPLANATION: An attempt was made to change the characteristics
411 | of the terminal, changing its background color
412 | to a value that was not legal.
413 | USER ACTION: Check the symbolic name for the background color
414 | desired. Specify it correctly.
415 | --
0012829C | 416
417 | DIALINNOT <diagonal line not allowed>
418 | ++
419 | FACILITY: SMG
420 | EXPLANATION: The vertices specified will result in a diagonal line,
421 | rather than a vertical or horizontal line.

```

```

422      | USER ACTION: Re-specify the vertices so that the line drawn will be
423      | vertical or horizontal.
424      | --
001282A4 425      |
426      | TABID_MIS      <terminal table id mismatch>
427      | ++
428      | FACILITY:      SMG
429      | EXPLANATION:   The Termtable internal consistency check failed. The
430      |               routines which fetch information from Termtable have
431      |               a different version number than the Termtable data.
432      | USER ACTION: Probably the routines which fetch the data are newer
433      |               than your Termtable.exe. Re-compile Termtable.txt to
434      |               update your Termtable.exe.
435      | --
001282AC 436      |
437      | UNDTERNAM     <undefined terminal name>
438      | ++
439      | FACILITY:      SMG
440      | EXPLANATION:   The requested terminal definition was not found in
441      |               the caller's private copy of Termtable or the system
442      |               copy of Termtable.
443      | USER ACTION: If you intended to use a private terminal definition,
444      |               make sure that Termtable.exe exists in your private
445      |               directory and that the logical name TERMSTABLOC points
446      |               to it. If you expected your terminal to be defined in
447      |               the system Termtable, check with your system manager.
448      | --
001282B4 449      |
450      | INVTERTAB     <invalid terminal table>
451      | ++
452      | FACILITY:      SMG
453      | EXPLANATION:   An invalid terminal table address was specified.
454      | USER ACTION: Check that you are passing the terminal table argument
455      |               by reference and not by value. Make sure the terminal
456      |               table address was acquired by calling
457      |               SMG$INIT_TERM_TABLE.
458      | --
001282BC 459      |
460      | INVREQCOD     <invalid request code>
461      | ++
462      | FACILITY:      SMG
463      | EXPLANATION:   Data is requested from Termtable via request codes
464      |               which are available as symbolic names. The code you
465      |               have specified is invalid.
466      | USER ACTION: Check the spelling of the symbolic name you are using.
467      | --
001282C4 468      |
469      | NOTBOOCAP     <not a boolean capability>
470      | ++
471      | FACILITY:      SMG (termtable compiler)
472      | EXPLANATION:   The Termtable compiler expected a boolean capability
473      |               name but encountered something else.
474      | USER ACTION: Check your terminal definition. Perhaps you have
475      |               misspelled the boolean capability name or omitted
476      |               another statement such as STRING or NUMERIC which
477      |               would have terminated boolean capabilities.
478      | --

```

```

001282CC 479
          480 SYNERR          <syntax error>
          481 ++
          482 FACILITY:      SMG (termtable compiler)
          483 EXPLANATION:    The Termtable compiler encountered an invalid
          484                syntax.  For instance, there may be a misplaced or
          485                missing equals sign.
          486 USER ACTION:    Check your terminal definition.
          487 --
001282D4 488
          489 UNDTERTYP      <undefined terminal type>
          490 ++
          491 FACILITY:      SMG
          492 EXPLANATION:    The definition for the requested terminal type was
          493                not found in the caller's private copy of Termtable
          494                or the system Termtable.
          495 USER ACTION:    If you intended to use a private definition, make
          496                sure that Termtable.exe exists in your private directory
          497                and that the logical name TERMSTABLOC points to it.
          498                If you expected your terminal definition to exist in
          499                the system Termtable, consult your system manager.
          500 --
001282DC 501
          502 MISTERNAM      <definition must begin with a terminal name>
          503 ++
          504 FACILITY:      SMG (termtable compiler)
          505 EXPLANATION:    Capabilities were not preceeded by the name of a
          506                terminal.
          507 USER ACTION:    Check your terminal definitions.  Make sure that
          508                each definition starts with NAME = <terminal_name>.
          509 --
001282E4 510
          511 INVCTRL        <unrecognized control code>
          512 ++
          513 **** This should not be documented because I think it will go
          514 **** away when the official V4 is released.
          515 --
001282EC 516
          517 ILLVAL         <Boolean value must be 0 or 1>
          518 ++
          519 FACILITY:      SMG (termtable compiler)
          520 EXPLANATION:    A boolean capability was given a value other than
          521                0 or 1.
          522 USER ACTION:    Check your terminal definitions.  Boolean capabilities
          523                must be 0 or 1 (off or on, respectively).
          524 --
001282F4 525
          526 INVEXP         <invalid expression>
          527 ++
          528 FACILITY:      SMG (termtable compiler)
          529 EXPLANATION:    The Termtable compiler encountered an invalid
          530                arithmetic expression.
          531 USER ACTION:    Check your definition.  Make sure that you have
          532                used only valid operators and operands in your
          533                expressions.
          534 --
          535

```

```

001282FC 536 ERRAT_LIN <Error in line !UL at or near '!AF'> /FAO=3
          537
          538
          539 FACILITY: SMG (termtable compiler)
          540 EXPLANATION: General information message included with many
          541 Termtable compiler messages. Attempts to identify
          542 specifically where an error occurred.
          543 USER ACTION: Check the specified line in your definition.
          544
00128304 545 ERRLIN <Error in line !UL> /FAO=1
          546
          547 FACILITY: SMG (termtable compiler)
          548 EXPLANATION: General information message included with many
          549 Termtable compiler messages. Attempts to identify
          550 specifically which line contained an error.
          551 USER ACTION: Check the specified line in your definition.
          552
0012830C 553
          554 UNDTERNOP <undefined terminal - couldn't access private terminal table>
          555
          556 FACILITY: SMG
          557 EXPLANATION: The requested terminal definition was not found in the
          558 caller's private copy of Termtable or the system
          559 Termtable. The caller's private Termtable couldn't be
          560 be accessed, either because it didn't exist or because
          561 RMS could not open the file.
          562 USER ACTION: If you intended to use a definition from your private
          563 Termtable, make sure that Termtable.exe exists in your
          564 private directory and that the logical name TERM$TABLOC
          565 points to it. Make sure that you have read access to
          566 the file.
          567
00128314 568
          569 UNDTERNOS <undefined terminal - couldn't access system terminal table>
          570
          571 FACILITY: SMG
          572 EXPLANATION: The requested terminal definition was not found in
          573 the caller's private Termtable or the system Termtable.
          574 The system Termtable was unavailable.
          575 USER ACTION: The system Termtable should be mapped as a global
          576 section and therefore should always be available.
          577 Consult your system manager regarding this.
          578
0012831C 579
          580 MISFILSPE <missing file specification in REQUIRE statement>
          581
          582 FACILITY: SMG (termtable compiler)
          583 EXPLANATION: The REQUIRE statement needs a file name in order to
          584 locate external definitions which should become part
          585 of your Termtable.
          586 USER ACTION: Check your Termtable.txt. Add a file name to the
          587 REQUIRE statement.
          588
00128324 589
          590 UNRECSTA <unrecognized statement>
          591
          592 FACILITY: SMG (termtable compiler)

```

```

593      | EXPLANATION: The Termtable compiler encountered a statement that
594      |           it does not recognize.
595      | USER ACTION: Check your definition. Make sure you have spelled
596      |           keywords correctly and that statements appear only
597      |           in valid sequences.
598      | --
0012832C 600      | FAIOPEFIL      <failed to open file !AF> /FA0=2
601      | ++
602      | FACILITY:     SMG (termtable compiler)
603      | EXPLANATION: The Termtable compiler could not open the file
604      |           specified in a REQUIRE.
605      | USER ACTION: Make sure that the specified file exists and that
606      |           you have read access to it.
607      | --
00128334 608      |
609      | NO_ARGS      <missing arguments for substitution>
610      | ++
611      | FACILITY:     SMG
612      | EXPLANATION: You requested a capability that requires user
613      |           arguments (such as a row and column number) but
614      |           did not provide any.
615      | USER ACTION: Check the number of arguments required by this
616      |           capability and correct your call to SMG$GET_TERM_DATA.
617      | --
0012833C 618      |
619      | NOTNUMCAP    <not a numeric capability>
620      | ++
621      | FACILITY:     SMG (termtable compiler)
622      | EXPLANATION: The Termtable compiler expected a numeric capability
623      |           name but encountered something else.
624      | USER ACTION: Check your terminal definition. Perhaps you have
625      |           misspelled the numeric capability name or omitted
626      |           another statement such as STRING or BOOLEAN which
627      |           would have terminated numeric capabilities.
628      | --
00128344 629      |
630      | NOTSTRCAP    <not a string capability>
631      | ++
632      | FACILITY:     SMG (termtable compiler)
633      | EXPLANATION: The Termtable compiler expected a string capability
634      |           name but encountered something else.
635      | USER ACTION: Check your terminal definition. Perhaps you have
636      |           misspelled the string capability name or omitted
637      |           another statement such as BOOLEAN or NUMERIC which
638      |           would have terminated string capabilities.
639      | --
0012834C 640      |
641      | MISENDSTA    <missing END statement>
642      | ++
643      | FACILITY:     SMG (termtable compiler)
644      | EXPLANATION: The Termtable compiler expected an END statement
645      |           to terminate the current terminal definition and
646      |           this END statement was missing.
647      | USER ACTION: Check your terminal definitions.
648      | --
649

```

```

00128354 650 MISNAMREQ <expected NAME or REQUIRE>
          651 ++
          652 ! FACILITY: SMG (termtable compiler)
          653 ! EXPLANATION: The Termtable compiler expected Termtable.txt to
          654 ! begin with a terminal definition (NAME statement)
          655 ! or a REQUIRE. Something else was encountered.
          656 ! USER ACTION: Check your Termtable.txt.
          657 ! --
          658
0012835C 659 ILLBATFNC <operation not permitted while display is batched>
          660 ++
          661 ! FACILITY: SMG
          662 ! EXPLANATION: An attempt was made to perform an operation that
          663 ! is not permitted while a virtual display is being
          664 ! batched (for example, performing input or MOVING
          665 ! the virtual display).
          666 ! USER ACTION: Terminate batching first by calling
          667 ! SMG$END_DISPLAY_UPDATE.
          668 ! --
          669
00128364 670 INVDIR <invalid directive>
          671 ++
          672 ! FACILITY: SMG (termtable compiler)
          673 ! EXPLANATION: The Termtable compiler accepts only a few FAO
          674 ! directives. It encountered one that it does not
          675 ! handle.
          676 ! USER ACTION: Check your terminal definition. Make sure that
          677 ! you use only valid FAO directives.
          678 ! --
          679
0012836C 680 TRMNOTANS <terminal is not ANSI compatible>
          681 ++
          682 ! FACILITY: SMG
          683 ! EXPLANATION: A call to SMG$GET_PHYSICAL_CURSOR was made
          684 ! specifying that the terminal is to be queried
          685 ! to determine where the cursor is.
          686 ! This could not be done because the terminal
          687 ! was not ANSI, and this feature is available
          688 ! only on ANSI terminals.
          689 ! USER ACTION: Rerun your application on an ANSI terminal,
          690 ! such as a VT100.
          691 ! --
          692
          693 ! .SEVERITY ERROR
          694 ! .BASE 128
          695
00128402 696 EOF <end-of-file>
          697 ++
          698 ! FACILITY: SMG
          699 ! EXPLANATION: End of file condition was detected on input.
          700 ! USER ACTION: If necessary, modify your program to recognize this
          701 ! condition and respond to it.
          702 ! --
          703
0012840A 704 KEYDEFPRO <key definition is protected - cannot be changed or deleted>
          705 ++
          706 ! FACILITY: SMG

```

```

707      : EXPLANATION: The specified key is already defined, and since its
708      :               definition is protected, it can not be changed or
709      :               re-defined.
710      : USER ACTION: none
711      : --
00128412 712      :
713      : INVDEFATT      <invalid key-definition attributes>
714      : ++
715      : FACILITY:      SMG
716      : EXPLANATION:  When a key is defined, attributes such as NOECHO may be
717      :               specified with the definition. An attempt was made to
718      :               specify an unknown attribute.
719      : USER ACTION:  Check the list of valid attributes and correct your
720      :               program.
721      : --
0012841A 722      :
723      : INVKEYNAM      <invalid key name>
724      : ++
725      : FACILITY:      SMG
726      : EXPLANATION:  The specified key name was less than 1 character or
727      :               more than 31 characters.
728      : USER ACTION:  Choose a key name with 1 to 31 characters.
729      : --
00128422 730      :
731      : INVSTANAM      <invalid state name>
732      : ++
733      : FACILITY:      SMG
734      : EXPLANATION:  The specified state name was less than 1 character or
735      :               more than 31 characters.
736      : USER ACTION:  Choose a state name with 1 to 31 characters.
737      : --
738      :
739      : .SEVERITY      WARNING
740      : .BASE          512
00129000 741      :
742      : KEYNOTDEF      <key is not defined>
743      : ++
744      : FACILITY:      SMG
745      : EXPLANATION:  An attempt was made to perform an operation, such as
746      :               SMG$GET_KEY_DEF, on a key which was not defined.
747      : USER ACTION:  Check your program to see if this key should have
748      :               been defined.
749      : --
00129008 750      :
751      : NOMOREKEYS     <no more keys defined>
752      : ++
753      : FACILITY:      SMG
754      : EXPLANATION:  SMG$LIST_KEY_DEFS, when called repeatedly, returns all
755      :               the key definitions in a key table. When there are no
756      :               more definitions, this error is returned.
757      : USER ACTION:  Modify your program to expect this condition, if necessary.
758      : --
00129010 759      :
760      : STRTERESC      <illegal escape sequence embedded in string>
761      : ++
762      : FACILITY:      SMG
763      : EXPLANATION:  An SMG output routine was passed an escape sequence

```



```

764      embedded in the output string. The output string was
765      written to the virtual display but the string was
766      terminated at the escape sequence.
767      USER ACTION: Check your output string to determine what escape
768      sequence was being passed. If you need the action
769      provided by this escape sequence, there is most
770      likely a SMG routine that provides that functionality.
771      --
00129018 772
773      GBLNOTCRE <global section not created>
774      ++
775      FACILITY: SMG
776      EXPLANATION: The system program that maps Termtable.exe as a global
777      section was unsuccessful.
778      USER ACTION: This message should be handled only by system managers.
779      If there is already an existing global section for
780      Termtable, the system must be rebooted in order to create
781      a new global section.
782      --
00129020 783
784      ! the following is used with GBLNOTCRE
785      DELEXIGBL <Termtable section already exists>
786      ++
787      FACILITY: SMG
788      EXPLANATION: The system program which maps Termtable as a global
789      section was unsuccessful. Before a new global section
790      can be created, the previous one must be deleted.
791      USER ACTION: The system must be rebooted in order to map a new
792      Termtable.exe as the global section.
793      --
794      .END
795
796 !      End of file SMGMSG.MSG

```

There were 0 errors, 0 warnings, and 0 informational messages issued.  
 MESSAGE/FILE\_NAME=SHRIMGMSG/LIS=LISS:SMGMSGPTR/OBJ=OBJ\$:SMGMSGPTR MSRC\$:SMGMSG

