



IBM DOS/VS COBOL

SC28-6479-4

**IBM DOS/VS COBOL Compiler and Library
Installation Reference Material**

Release 3.1



IBM DOS/VS COBOL

SC28-6479-4

**IBM DOS/VS COBOL Compiler and Library
Installation Reference Material**

Release 3.1

Fifth Edition (December 1990)

This edition replaces and makes obsolete the previous edition, SC28-6479-3.

This edition applies to Release 3.1 of the IBM DOS/VS Compiler and Library, Program Products 5746-CB1 and 5746-LM4, respectively, and to any subsequent releases until otherwise indicated in new editions or technical newsletters.

The changes for this edition are summarized under "Summary of Amendments" following the preface.

Changes are periodically made to the information herein; before using this publication in connection with the operation of IBM systems, consult the latest *IBM System/370, 30xx, 4300, and 9370 Processors Bibliography*, GC20-0001, for the editions that are applicable and current.

Requests for IBM publications should be made to your IBM representative or to the IBM branch office serving your locality. If you request publications from the address given below, your order will be delayed because publications are not stocked there.

A Reader's Comment Form is provided at the back of this publication. If the form has been removed, comments may be addressed to IBM Corporation, Department J58, P. O. Box 49023, San Jose, California, U.S.A. 95161-9023. IBM may use or distribute whatever information you supply in any way it believes appropriate without incurring any obligation to you.

© Copyright International Business Machines Corporation 1973, 1990. All rights reserved.

Note to U.S. Government Users — Documentation related to restricted rights — Use, duplication or disclosure is subject to restrictions set forth in GSA ADP Schedule Contract with IBM Corp.

Special Notices

References in this publication to IBM products, programs, or services do not imply that IBM intends to make these available in all countries in which IBM operates. Any references to an IBM product, program, or service is not intended to state or imply that only IBM's product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any of IBM's intellectual property rights or other legally protectible rights may be used instead of the IBM product, program, or service. Evaluation and verification of operation in conjunction with other products, programs, or services, except those expressly designated by IBM, are the user's responsibility.

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the IBM Director of Commercial Relations, IBM Corporation, Purchase, NY 10577.

The following terms, denoted by an asterisk where they first occur in this publication, are trademarks of the IBM Corporation in the United States and/or other countries:

DOS/VSE
IBM
VM/SP

About This Manual

This publication contains the system-related information needed to install the IBM DOS/VS COBOL Compiler and its associated COBOL Object-time Subroutine Library. These program products operate under control of the IBM DOS/VSE System and the Conversational Monitor System (CMS) component of VM/SP (Virtual Machine Facility/System Product).

This publication is designed to be used in conjunction with the DOS/VS COBOL Program Directory.

Program Product Installation is directed to the system programmer or planner responsible for the planning and/or implementation of system generation and maintenance. It contains information corresponding to that found in *DOS/VSE System Generation*. The operating system requirements, minimum machine configuration, work file requirements, and IOCS modules required for the DOS/VS compiler are described, as is the procedure for installing DOS/VS COBOL under DOS/VSE and VM/SP. This section also contains storage requirements for the compiler and the library.

CMS messages produced for DOS/VS COBOL are described in the "Using DOS COBOL Under CMS" section of *IBM CMS User's Guide for COBOL*, SC28-6469.

Additional Publications

Within the text, references are made to the following publications:

DOS/VSE System Management Guide, GC33-5371

DOS/VSE System Generation, GC33-5377

DOS/VSE System Control Statement, GC33-5376

DOS/VSE Maintain System History Program (MSHP) User's Guide, GC33-6060

IBM DOS/VS COBOL Compiler and Library Programmer's Guide, SC28-6478

Virtual Machine Facility/SP Planning and System Generation Guide, SC19-6203

Virtual Machine Facility/SP CMS User's Guide, SC19-6210

DOS/VS Sort/Merge Programmer's Guide, SC33-4044

DOS/VS Sort/Merge Installation Reference, SC33-4045.

Summary of Changes

Revision SC28-6479-4

New: Programming Feature

The MIGR compiler option flags major COBOL language elements that are no longer supported or are supported differently by the VS COBOL II compiler, Program number 5668-958.

Maintenance: Documentation

Service updates have been applied to DOS/VS COBOL Release 3.1.

Minor technical changes and additions have been made to the text.

Revision SC28-6479-3

New: Installation Procedures

DOS/VS COBOL Release 3 is installed by the Maintain System History Program (MSHP). The installation procedures have been rewritten to reflect the change.

TNL SN20-9293

New: Programming Feature

Support for fixed block devices is provided under DOS/VSE with VSE/Advanced Function, Release 1.



Contents

Introduction	1
Program Product Installation	2
System Requirements	2
Operating System Requirements	2
Machine Configuration for DOS/VSE	3
Execution-Time Considerations	4
Sort/Merge Feature Considerations	4
Symbolic Debug Considerations	4
FIPS Considerations	5
Machine Configuration for CMS	5
Execution-Time Considerations	6
Work File Requirements	6
FIPS Work Files	8
LIOCS Modules	8
Relocatable Module Naming Conventions	9
CDMOD	10
DAMOD	12
DRMOD	12
DUMOD	13
ISMOD	13
MTMOD	14
PRMOD	16
SDMOD	18
Required IOCS Modules	19
Installation Procedure	20
DOS/VS COBOL Installation—DOS/VSE	20
Libraries Required—DOS/VSE	20
Installation Process—DOS/VSE	20
Verifying Success—DOS/VS Compiler Installation	20
Application of Corrective Maintenance	20
DOS/VS COBOL Installation—VM/SP	21
Installation Process under VM/SP CMS	21
System Generation Considerations	21
Changing the Installation Defaults	22
CBL Statement—COBOL Option Control Statement	22
Storage Requirements	23
Virtual Storage	23
Core Image Library	24
Compiler Phases	24
Transient Routines	25
Library Phases	25
Relocatable Library	26
Compiler Modules	26
Subroutines	27
IOCS Modules	29
Appendix. Device Information	30
Index	31



Introduction

The IBM® DOS/VS COBOL Compiler (“the compiler”) and Library is a Program Product that operates under control of the IBM DOS/VSE® system or the Conversational Monitor System (CMS) component of VM/SP®. The product contains the COBOL compiler as well as the COBOL subroutines that, when required, are combined by the Linkage Editor with the object program produced by the compiler. It also contains a set of transient routines that can be fetched dynamically into the user’s storage area during program execution, and a special set of COBOL statements that can be used to process input from a 3886 Optical Character Reader. It accepts as input any program written in DOS/VS COBOL.

The DOS/VS COBOL Object-time Subroutine Library (“the library”) associated with the DOS/VS compiler is also available as a separate Program Product. The subroutine library also contains the COBOL subroutines and the set of transient routines that are described above.

Link-edited programs that have been compiled by the DOS/VS COBOL compiler (5746-CB1) all require the presence of the DOS/VS COBOL Library at execution time. Note that a separate library may not be needed. *The library packaged with the compiler can be used* if the programs are executing on the same processor as the one on which they are compiled or if they are executing under CMS; otherwise, there must be a separate library (5746-LM4) for each processor on which the programs are executing.

The CMS installation must order and install DOS/VSE (Advanced Function Release 3 or later). If the DOS/VS COBOL programs access any VSAM data sets, VSE/VSAM must also be installed. If the DOS/VS COBOL programs use SORT or MERGE, DOS/VSE Sort/Merge must be installed. Then, the CMS installation must install the DOS/VS COBOL compiler and library. The compiler must be link-edited in the background partition of DOS/VS, and all of the compiler’s relocatable modules must be link-edited using the ACTION REL CLEAR linkage editor control statement. The compiler and library may reside on the DOS/VSE system pack or on private libraries.

When the DOS/VS COBOL compiler is executed under CMS, it must be executed in the CMS DOS environment. Before invoking the DOS/VS COBOL compiler or executing DOS/VS COBOL programs under CMS, be sure that the CMS DOS environment has been previously generated into your CMS system and is active. Also, when the DOS/VS COBOL compiler and DOS/VS COBOL programs are executed under CMS, the DOS/VSE system pack or private libraries must be available to CMS.

Program Product Installation

This section contains the information you will need to add the IBM DOS/VS COBOL Compiler and its associated COBOL Object-time Subroutine library to your DOS/VSE System.

The first part of this section, "System Requirements" describes the operating system requirements, minimum machine configuration, work file requirements, and LIOCS module requirements for the compiler. The second part, "Installation Procedure" on page 20, gives instructions for adding the compiler and the library to the system. The third part, "Storage Requirements" on page 23, describes the amount of space required by the compiler and the library.

System Requirements

For DOS/VS, the compiler and the library operate under the control of the IBM Disk Operating System (DOS/VSE). A DOS/VSE Advanced Function Release 3 system is the minimum level required. The minimum machine configuration and the operating system requirements to support the compiler and the library are described in this section. Execution-time considerations and special requirements for use of the Sort feature and the Symbolic Debug feature are also discussed.

For CMS, the compiler and the library are controlled by the CMS DOS environment. A DOS/VSE system pack or the DOS/VSE private libraries must be available for CMS DOS use. CMS DOS requires a DOS/VSE Advanced Function Release 3 system as a minimum level. The minimum virtual machine configuration and the operating system requirements to support the compiler and the library under CMS are described in this section. Other execution-time considerations are also discussed in this section.

Operating System Requirements

If the SORT or MERGE verb is used in the source program under DOS/VSE, the DOS/VSE Sort/Merge Program Product, Program Number 5746-SM2, is required. For further information on this product, see *DOS/VS SORT/MERGE Programmer's Guide* and *DOS/VS SORT/MERGE Installation Reference Material*.

During link-editing, modules produced by the compiler require subroutines from the library. In addition, subroutines from the library may be required during execution. Therefore, the library must also be part of the system used to control program execution.

CMS requires access to the DOS/VSE System pack or to the private libraries that contain the DOS/VS COBOL compiler or subroutines. To make the system pack available at virtual address 195 as your C-disk, specify the filemode when the CMS DOS environment is invoked:

```
ACCESS 195      C
SET DOS ON     C
```

To make private libraries at address 193 available, access the disk specifying some CMS mode letter such as D, and issue ASSGN and DLBL commands after the CMS DOS environment is invoked:

```
ACCESS 193          D
SET DOS ON
ASSGN  SYSCLB      D
DLBL   IJSYSCL     D DSN ? (SYSCLB)
ASSGN  SYSRLB      D
DLBL   JJSYSKL     D DSN ? (SYSRLB)
```

Machine Configuration for DOS/VSE

The minimum DOS/VSE machine configuration required to use the DOS/VS COBOL compiler and library is:

1. A System/370, 303X or 4300 model supported by DOS/VSE. At least 128K bytes must be available to the compiler.
2. Six work files.

The system logical unit SYSLNK must be assigned to a single area (extent) on a 2311, 2314, 2319, 3330, 3340, 3350, 3375, or fixed block mass storage device.

Five programmer logical units (SYS001 through SYS005) must reside on 2400, 3410, or 3420 tape units, or on 2311, 2314, 2319, 3330, 3340, 3350, 3375, or fixed block mass storage devices. (Two programmer logical units, as well as the operating system, must reside on a mass storage device.)

If the four remaining logical units reside on tape, there must be a separate tape unit for each data set. If they reside on a mass storage device, there must be enough space on that device. See "Work File Requirements" on page 6 for further information.

Workfile assignments must be made as follows:

```
SYS001—disk unit
SYS002—disk or tape unit
SYS003—disk or tape unit
SYS004—disk or tape unit
SYS005—disk or tape unit (required when Symbolic Debug is requested
        at compile time)
SYS006—disk unit (required for FIPS).
```

Note that SYSLNK need not be assigned at compile time unless the CATAL or LINK option is in effect.

The filenames for SYSLNK and SYS001 through SYS006 on the TLBL or DLBL statements are IJSYSLN, IJSYS01, IJSYS02, IJSYS03, IJSYS04, IJSYS05, and IJSYS06, respectively.

3. A device for direct operator communication.
4. A device, such as a card reader, for the job input stream.
5. A device, such as a printer or a tape unit, for system output files.
6. The floating-point arithmetic feature, if floating point literals or calculations are used.

Note: All devices currently supported by previous IBM DOS COBOL compilers are supported by the IBM DOS/VS COBOL Compiler. These include: 3504/3505 (with OMR), 3525 (with RCE and combined function processing), 3410/3420 Tapes, 3881 Optical Mark Reader, and 3330 Disk. The DOS/VS compiler also supports the 5425

Multifunction Card Unit, 2560 Multifunction Card Machine, 3203 and 5203 Advanced Printers, 3886 Optical Character Reader, 3340 Disk Facility, 3344 Direct Access Storage, 3350 Direct Access Storage in 3330-1 compatibility mode, and 3540 Diskette Input/Output Unit.

Execution-Time Considerations

The amount of virtual storage must be sufficient to accommodate at least:

- The selected control program
- Support for the file processing techniques used
- The load module to be executed.

If execution statistics, VSAM, or the 3886 Optical Character Reader feature are requested, additional virtual storage must be available to accommodate its dynamic space requirements.

Use of the symbolic debugging, flow trace, statement number, execution statistics, option or the 3886 Optical Character Reader feature requires additional storage during execution. See *IBM DOS/VS COBOL Compiler and Library Programmer's Guide* for further information.

Sort/Merge Feature Considerations

The DOS/VS Sort/Merge Program Product, Program Number 5746-SM2, must be executed under the control of DOS/VSE. It requires the following minimum machine configuration.

1. The DOS/VS Sort/Merge Program Product uses 40K bytes; an additional 6K bytes are needed for DOS/VSE and for user-written routines.

Note: Performance often increases significantly if 50K bytes is available for operation of the Sort/Merge program. At the 100K-byte level, the performance could be even higher.

2. Standard instruction set.
3. At least one 2314, 2319, 3330, 3333, 3340, or 3350 work file. (System residence requirements may necessitate having an additional disk storage unit for sorting.)
4. One IBM 1403, 1443, 3203, 5203, or 3211 Printer, or one IBM operator communication device (for example, 3215).
5. One IBM 1442, 2501, 2520, 2540, 3505, 3525, or 2560 Card Reader, or one IBM 2400 or 3400 Series Magnetic Tape Unit (7- or 9-track) assigned to SYSIPT and SYSRDR.
6. Three IBM 2400 or 3400 Series Magnetic Tape Units for work files when tape units are to be used for intermediate storage. For a merge operation, no work units are required.

Symbolic Debug Considerations

To use the Symbolic Debug feature of the DOS/VS compiler, a fifth work file (SYS005) is required at compile time. When symbolic debugging is requested, the compiler records, in SYS005, the information needed to produce a symbolic formatted dump if the program terminates abnormally or if dynamic dumps are requested. Thus, the file assigned to SYS005 at compile time must also be assigned at execution time. This file need not necessarily be assigned to SYS005, but it must be assigned in the partition in which the program is executed.

SYS005 can be allocated with the other system work files (SYS001, SYS002, SYS003, SYS004) at system generation time. Each COBOL source program requesting symbolic debugging then uses the same work file. However, unique symbolic debugging work file assignments are required when several COBOL programs are to be compiled in the same job. If there is only one SYS005 allocated for use by all COBOL programs, information recorded on the file during compilation of one program is overlaid by information placed there during compilation of a subsequent program. Then, when the object modules are link-edited and executed, the information recorded during compilation will not be available if it has been overlaid.

To avoid the loss of the information needed to produce a symbolic formatted dump, assign a unique symbolic debugging work file for each COBOL source program to be compiled. On a mass storage device, these symbolic debugging work files must be assigned to non-overlapping extents. The following example shows how to use ASSGN statements to define the symbolic debugging work file on disk. Note that the compilation step assigns this data set to SYS005; at execution, it is assigned to SYS006.

```
// JOB SAMPLE
// OPTION SYM,NODECK,NOLISTX,NOXREF,LINK
// ASSGN SYS005,X'192'
// DLBL DEMOXX,99/101,SD
// EXTENT SYS005,111111,1,0,1100,50
// EXEC FCOBOL
      CBL SYMDMP
```

(COBOL source deck)

```
/*
// EXEC LNKEDT
// ASSGN SYS006,X'192'
// DLBL DEMOXX,99/101,SD
// EXTENT SYS006,111111,1,0,1100,50
// EXEC
```

(SYMDMP control cards)

```
/*
/&
```

If the symbolic debugging work file is defined as a tape, one physical reel is required. The file-protect ring must be in the tape reel during compilation *and* execution.

FIPS Considerations

SYS006 is required only for FIPS processing. After printing the header and any CBL card options on SYSLST, the compiler writes the compilation listing on SYS006 as input to the FIPS phases. The FIPS output is written on SYSLST.

Machine Configuration for CMS

The minimum CMS virtual machine configuration will support the DOS/VS COBOL compiler and library.

1. A CMS virtual machine with a minimum of 320K bytes of virtual storage and with the CMS DOS environment active is required. The compiler uses at least 60K bytes of CMS user storage.
2. System and Logical Units.

SYSIN/SYSIPT must be assigned to the device that contains the input source file. SYSIN/SYSIPT can be assigned to a reader, tape, or disk.

The user can issue the ASSGN command for the following units:

SYSPCH to tape, punch, disk, or IGN
SYSLST to tape, printer, disk, or IGN
SYSLOG to terminal
SYS001-SYS002 to disk
SYS003-SYS005 to tape or disk
SYS006 to disk.

Note: CMS allows "disk" to also be the 3350 in native mode. CMS does not support the 3540 diskette, the 2311 disks, or the 2321 datacell. If SYSIN/SYSIPT is unassigned at compilation time, the CMS DOS COBOL interface issues an error message and terminates the FCOBOL command.

If SYSPCH, SYSLST, SYSLOG, or SYS001-SYSnnn is unassigned at compilation time, the CMS DOS COBOL interface sends the output to the SYSIN disk (if SYSIN is assigned to a read/write disk) or to the user's A-disk.

Note: SYSLNK must not be assigned; it is not supported as a system logical unit under CMS DOS.

3. Device Support

The following devices, which are supported by DOS/VS, are *not* supported by CMS DOS:

- *Card Readers:* 1442, 2560P, 2560S, 2596, 3504, 5425P, and 5425S
- *Disks:* 3540, 2311, 2321
- *Printers:* 2560P, 2560S, 3203, 3525, 5203, 5425P, and 5425S
- *Other Devices:* 3881 OMR, 3886OCR.

Not all of the DOS/VSE LIOCS modules are supported in CMS DOS; see "LIOCS Modules" on page 8 for more information.

Execution-Time Considerations

If symbolic debugging is requested, an additional work file, SYS005, should be assigned at compile time. If the file is not assigned, the CMS DOS COBOL interface directs the output to the SYSIN disk (if SYSIN is assigned to a read/write disk) or to the user's A-disk.

The SORT verb is not supported in CMS DOS. Also, COBOL programs that use ISAM or segmentation cannot be executed under CMS DOS.

Work File Requirements

This section describes the work files required by the compiler. In addition to SYSRES and SYSLNK, which must be assigned to disk units, the compiler may require up to six work files: SYS001, SYS002, SYS003, SYS004, SYS005, and SYS006. SYS005 is required only when the Symbolic Debug feature is requested. SYS006 is required for FIPS.

Note: SYSLNK is not supported and must not be assigned for CMS DOS.

SYS001 and SYS006 must be assigned to a disk unit. Each of the other data sets (SYS002, SYS003, SYS004, and SYS005) can be assigned to either a tape unit or a disk unit.

If the work files are on tape, each must be assigned to a separate tape unit. If the work files are on disk, the amount of disk work space required depends mainly on the size of the source program. The approximate percentages of tracks that should be assigned to each work file are shown in Figures 1 through 6. Estimates are for programs of approximately 1000 and 2100 source records. The programs are assumed to request a cross-reference listing, the symbolic debug feature, and the source program library facility (COPY and/or BASIS). Source programs with the library facility require the LIB option on the COBOL option card (CBL card). Programs using NOLIB require considerably less SYS004 work space.

For DOS/VSE, work file assignments for the compiler must be made in each partition in which the compiler operates. For example, if the compiler can operate in either the background or the foreground 1 (F1) partition, work file assignments must be made in both the background and F1. The CMS DOS environment simulates only the background partition. CMS DOS does not support the 2311.

Number of Source Records	Total Tracks	SYS001 %	SYS002 %	SYS003 %	SYS004 %	SYS005 %
1000	92	22	24	14	34	6
2100	146	16	19	14	44	7

Figure 1. Approximate Allocation of Work File Space—IBM 2311

Number of Source Records	Total Tracks	SYS001 %	SYS002 %	SYS003 %	SYS004 %	SYS005 %
1000	44	21	18	14	38	9
2100	74	16	16	12	48	8

Figure 2. Approximate Allocation of Work File Space—IBM 2314

Number of Source Records	Total Tracks	SYS001 %	SYS002 %	SYS003 %	SYS004 %	SYS005 %
1000	28	18	22	14	39	7
2100	46	15	17	13	48	7

Figure 3. Approximate Allocation of Work File Space—IBM 3330

Number of Source Records	Total Tracks	SYS001 %	SYS002 %	SYS003 %	SYS004 %	SYS005 %
1000	43	19	19	14	39	9
2100	72	15	17	13	48	7

Figure 4. Approximate Allocation of Work File Space—IBM 3340

Number of Source Records	Total Tracks	SYS001 %	SYS002 %	SYS003 %	SYS004 %	SYS005 %
1000	20	19	19	15	40	7
2100	34	16	17	13	49	7

Figure 5. Approximate Allocation of Work File Space—IBM 3350

Number of Source Records	See Note Below	SYS001 %	SYS002 %	SYS003 %	SYS004 %	SYS005 %
1000	1020	18	18	15	41	8
2100	1700	16	16	13	48	7

Note: Total Fixed Block Device (512 Bytes). BUFSIZE equals 512.

Figure 6. Approximate Allocation of Work File Space—Fixed Block Device

FIPS Work Files

The number of tracks required for SYS006 (the FIPS input file) depends on the size of the source program and the compiler options specified. As basic output, each record contains a line of the compilation listing and is 121 characters in length. However, additional space is required whenever each of the following options is specified: SYM, LISTX or CLIST, XREF or SXREF. SYS006 also contains any error messages issued by the compiler.

LIOCS Modules

The following lists contain the names of the preassembled LIOCS modules used by the compiler. These modules are supplied by IBM as part of the relocatable library when the IBM DOS/VSE System is distributed. Be sure that the modules listed are included in the system to which the compiler is added.

Certain preassembled LIOCS modules are required when cataloging IBM components to the core image library. Do not delete these modules from the relocatable library until *after* all the IBM components have been cataloged to the core image library *and* all program products have been installed. These modules are listed in "Required IOCS Modules" on page 19.

Notes:

1. Additional LIOCS modules (for ASCII processing) are distributed with the DOS/VSE subroutines and are added to the relocatable library with the subroutines. These LIOCS modules are listed under "Relocatable Library" on page 26.
2. CMS DOS does not support all the DOS/VSE logical transients, nor all the operands of the transients it does support. The CMS DOS logical transient support is described in the *VM/SP User's Guide*.

The procedure for generating the compiler for use with CMS DOS is exactly the same as the procedure for generating it for use with DOS/VSE: the LIOCS modules required are the same. CMS DOS, during its open routines, checks that the file being opened is supported by CMS DOS.

Relocatable Module Naming Conventions

Each module has an 8-character name. The name consists of a 3-character prefix and a 5-character field corresponding to the option permitted in generation of the module. The following 3-character prefixes identify the preassembled modules shipped by IBM:

IJC	I/O Card (CDMOD)
IJD	I/O Printer (PRMOD)
IJF	I/O Magnetic Tape (MTMOD)
IJG	Sequential Direct Access (SDMOD)
IJH	Index Sequential Direct Access (ISMOD) ¹
IJI	Direct Access Method (DAMOD) ¹
IJJ	Device Independent Access Method (DIMOD)
IJN	3540 Access Method (DUMOD) ¹

¹ ISMOD, DAMOD, and DUMOD are not supported for the CMS DOS environment.

CDMOD

CDMOD name = IJcabcde

- a = F RECFORM=FIXUNB (always for INPUT and CMBND files)
 - = U RECFORM=UNDEF
 - = V RECFORM=VARUNB

- b = A CTLCHR=ASA (not specified CMBND)
 - = C CCNTROL=YES
 - = Y CTLCHR=YES
 - = Z neither CTLCHR nor CONTROL is specified

- c = B RONLY=YES and TYPEFLE=CMBND
 - = C TYPEFLE=CMBND
 - = H RONLY=YES and TYPEFLE=INPUT
 - = I TYPEFLE=INPUT
 - = N RONLY=YES and TYPEFLE=OUTPUT
 - = O TYPEFLE=OUTPUT

- d = B WORKA=YES and IOAREA2=YES
 - = I IOAREA2=YES
 - = W WORKA=YES
 - = Z neither WORKA nor IOAREA2 is specified
 - = Z WORKA is **not** specified (for CMBND files only)

- e = 0 DEVICE=2540
 - = 1 DEVICE=1442
 - = 2 DEVICE=2520
 - = 3 DEVICE=2501
 - = 4 DEVICE=2540 and CRDERR is specified
 - = 5 DEVICE=2520 and CRDERR is specified
 - = 6 DEVICE=3505
 - = 7 DEVICE=3525 and FUNC omitted or Func=R or P
 - = 8 DEVICE=2560 and FUNC omitted or Func=R or P
 - = 9 DEVICE=5425 and FUNC omitted or FUNC=R or P
 - = A DEVICE=3525 and FUNC=RP
 - = B DEVICE=3525 and FUNC=RW
 - = C DEVICE=3525 and FUNC=PW
 - = D DEVICE=3525 and FUNC=I
 - = E DEVICE=3525 and FUNC=RPW
 - = F DEVICE=2560 and FUNC=RP
 - = G DEVICE=2560 and FUNC=RW
 - = H DEVICE=2560 and FUNC=PW
 - = I DEVICE=2560 and FUNC=I
 - = J DEVICE=2560 and FUNC=RPW
 - = K DEVICE=5425 and FUNC=RP
 - = L DEVICE=5425 and FUNC=RW
 - = M DEVICE=5425 and FUNC=PW
 - = N DEVICE=5425 and FUNC=I
 - = O DEVICE=5425 and FUNC=RPW

CDMOD Names

IJCFAOI1	IJCFZO15	IJCUZO15	IJCVZO19
IJCFAOI4	IJCFZO17	IJCUZO17	
IJCFAOI5	IJCFZO18	IJCUZO18	
IJCFAOI7	IJCFZO19		IJCVZO21
IJCFAOI8	IJCFZOID	IJCUZO19	IJCVZO24
IJCFAOI9	IJCFZOZ1	IJCUZOZ1	IJCVZO25
IJCFAOZ1	IJCFZOZ4	IJCUZOZ4	IJCVZO27
IJCFAOZ4	IJCFZOZ5	IJCUZOZ5	IJCVZO28
	IJCFZOZ7	IJCUZOZ7	IJCVZO29
	IJCFZOZ8	IJCUZOZ8	IJCVZOZ1
IJCFAOZ5	IJCFZOZ9	IJCUZOZ9	IJCVZOZH
IJCFAOZ7	IJCFZOZA	IJCUZOZF	IJCVZOZI
IJCFAOZ8	IJCFZOZC	IJCUZOZH	IJCVZOZJ
IJCFAOZ9	IJCFZOZD	IJCUZOZ1	IJCVZOZK
IJCFAOZA	IJCFZOZE	IJCUZOZJ	IJCVZOZM
IJCFAOZC	IJCFZOZF	IJCUZOZK	IJCVZOZN
IJCFAOZE	IJCFZOZH	IJCUZOZM	IJCVZOZO
IJCFAOZF			
IJCFAOZH	IJCFZOZ1	IJCUZOZN	
IJCFAOZI	IJCFZOZJ	IJCUZOZO	
IJCFAOZJ	IJCFZOZK		
IJCFAOZK	IJCFZOZM		
IJCFAOZM	IJCFZOZN	IJCVAOI1	
IJCFAOZN	IJCFZOZO	IJCVAOI4	
IJCFAOZO			
IJCFCIZ0		IJCVAOI5	
IJCFCIZ1		IJCVAOI8	
IJCFCIZ2	IJCUAOI4	IJCVAOI9	
IJCFCIZ6	IJCUAOI5	IJCVAOZ1	
IJCFYOI0	IJCUAOI8	IJCVAOZ4	
IJCFYOI7	IJCUAOI9	IJCVAOZ5	
		IJCVAOZ8	
		IJCVAOZ9	
IJCFZ1I0	IJCUAOZ1		
IJCFZ1I1	IJCUAOZ4		
IJCFZ1I2	IJCUAOZ5	IJCVAOZF	
IJCFZ1I3	IJCUAOZ8	IJCVAOZH	
IJCFZ1I6	IJCUAOZ9	IJCVAOZ1	
IJCFZ1I7	IJCUAOZF	IJCVAOZJ	
IJCFZ1I8	IJCUAOZH	IJCVAOZK	
IJCFZ1I9	IJCUAOZ1	IJCVAOZM	
IJCFZIZ0	IJCUAOZJ	IJCVAOZN	
	IJCUAOZK	IJCVAOZO	
	IJCUAOZM		
	IJCUAOZN		
	IJCUAOZO		
IJCFZIZ1		IJCVZ1I8	
IJCFZIZ2		IJCVZ1I9	
IJCFZIZ3		IJCVZIZ8	
IJCFZIZ6		IJCVZIZ9	
IJCFZIZ7	IJCUZ1I8	IJCVZIZF	
IJCFZIZ8	IJCUZ1I9	IJCVZIZG	
IJCFZIZ9	IJCUZIZ8	IJCVZIZJ	
IJCFZIZA	IJCUZIZ9	IJCVZIZK	
IJCFZIZB	IJCUZIZF	IJCVZIZL	
IJCFZIZE	IJCUZIZG	IJCVZIZO	
IJCFZIZF	IJCUZIZJ		
IJCFZIZG	IJCUZIZK		
IJCFZIZJ	IJCUZIZL		
IJCFZIZK	IJCUZIZO	IJCVZO11	
IJCFZIZL		IJCVZO14	
IJCFZIZO		IJCVZO15	
IJCFZO11	IJCUZO11	IJCVZO17	
IJCFZO14	IJCUZO14	IJCVZO18	

DAMOD

DAMOD name = IJlabcde

a = B RECFORM=UNDEF (handles both UNDEF and FIXUNB)
= F RECFORM=FIXUNB
= S RECFORM=SPNUNB
= V RECFORM=VARUNB

b = A AFTER=YES
= Z AFTER is **not** specified

c = E IDLOC=YES and FEOVD=YES
= I IDLOC=YES
= R FEOVD=YES
= Z neither is specified

d = H ERREXT=YES and RELTRK=YES
= P ERREXT=YES
= R RELTRK=YES
= Z neither is specified

e = W HOLD=YES and RDONLY=YES
= X HOLD=YES
= Y RDONLY=YES
= Z neither is specified

DAMOD Names

IJIBAIRZ
IJIBAIZZ
IJIBAZRZ
IJIBAZZZ
IJIBZIRZ

IJIBZIZZ
IJIBZZRZ
IJIBZZZZ
IJIFAIRZ
IJIFAIZZ

IJIFAZRZ
IJIFAZZZ
IJIFZIRZ
IJIFZIZZ
IJIFZZRZ

IJIFZZZZ
IJISAIRZ
IJISAIZZ
IJISAZRZ
IJISAZZZ

IJISZIRZ
IJISZIZZ
IJISZZRZ
IJISZZZZ

DRMOD

DRMOD name = IJMZabD0

a = S SETDEV = YES
= Z SETDEV = NO

b = R RDONLY = YES
= Z RDONLY = NO

DRMOD Names

IJMZSRDO
IJMZSZDO
IJMZZRDO
IJMZZZDO

DUMOD

DUMOD name = IJNDabcZ

a = I input
= O output

b = C ERROPT=name

c = Z RONLY not specified

DUMOD Names

IJNDICZZ
IJNDOCZZ

ISMOD

ISMOD name = IJHabcde

a = A RECFORM=BOTH and IOROUT=ADD or ADDRTR
= B RECFORM=FIXBLK and IOROUT=ADD or ADDRTR
= U RECFORM=FIXUNB and IOROUT=ADD or ADDRTR
= Z RECFORM is **not** specified and IOROUT=LOAD or RETRVE

b = A IOROUT=ADDRTR
= I IOROUT=ADD
= L ICROUT=LOAD
= R IOROUT=RETRVE

c = B TYPEFLE=RANSEQ
= G IOAREA2=YES and TYPEFLE=SEQNTL or IOROUT=LOAD
= R TYPEFLE=RANDOM
= S TYPEFLE=SEQNTL
= Z neither is specified and IOROUT=LOAD or ADD

d = C CORINDX=YES
= Z CORINDX is **not** specified

e = F CORDATA=YES, ERREXT=YES, and RONLY=YES
= G CORDATA=YES and ERREXT=YES
= O CORDATA=YES and RONLY=YES
= P CORDATA=YES
= S ERREXT=YES and RONLY=YES
= T ERREXT=YES
= Y RONLY=YES
= Z nothing is specified

ISMOD Names

IJHAARCP	IJHUABZZ
IJHAARCZ	IJHUARCP
IJHAARZP	IJHUARCZ
IJHAARZZ	IJHUARZP
IJHBABCP	IJHUARZZ
IJHBABCZ	IJHZLGZZ
IJHBABZP	IJHZLZZZ
IJHBABZZ	IJHZRBCZ
IJHBARCP	IJHZRBZZ
IJHBARCZ	
IJHBARZP	IJHZRGZZ
IJHBARZZ	IJHZRRZZ
IJHUABCP	IJHZRSZZ
IJHUABCZ	
IJHUABZP	

MTMOD

MTMOD name = IJFabcde

- a = F RECFORM=FIXUNB or FIXBLK
- = S RECFORM=SPNUNB or SPNBLK
- = U RECFORM=UNDEF
- = V RECFORM=VARUNB or VARBLK

- = X ASCII RECFORM=FIXUNB or FIXBLK
- = N ASCII RECFORM=UNDEF
- = R ASCII RECFORM=VARUNB or VARBLK

- b = B READ=BACK
- = Z READ=FORWARD, or READ is **not** specified

- c = C CKPTREC=YES
- = Z CKPTREC is **not** specified

- d = W WORKA=YES
- = Z WORKA is **not** specified

- e = M ERREXT=YES and RONLY=YES
- = N ERREXT=YES
- = Y RONLY=YES
- = Z neither is specified

MTMOD Names

IJFFBZZN
IJFFZCZZ
IJFFZZZZ
IJFSZZWN
IJFUZZZN

IJFUZZZZ
IJFVZZZN
IJFVZZZZ

(See "IOCS Modules" on page 29 for additional MTMOD modules.)

Name list for workfile type modules (TYPEFLE = WORK):

MTMOD name = IJFabcde

a = W always

b = E ERROPT=YES
= Z ERROPT is **not** specified

c = N NOTEPNT=YES
= S NOTEPNT=POINTS
= Z NOTEPNT is **not** specified

d = Z always

e = M ERREXT=YES and RONLY=YES
= N ERREXT=YES
= Y RONLY=YES
= Z neither is specified

System I/O Modules: (See "Required IOCS Modules" on page 19 before deleting modules with the IJF prefix.)

IJFWEZZZ
IJFWZNZZ
IJFWZZZZ

PRMOD

PRMOD name = IJDabcde

- a = F RECFORM=FIXUNB
 - = V RECFORM=VARUNB
 - = U RECFORM=UNDEF

- b = A CTLCHR=ASA
 - = Y CTLCHR=YES
 - = C CONTROL=YES
 - = S STLIST=YES
 - = T DEVICE=3525 with 2-line printer
 - = U DEVICE=2560
 - = V DEVICE=5425
 - = Z neither CTLCHR nor CONTROL nor STLIST is specified

- c = P PRINTOV=YES, DEVICE not 3525
 - = I PRINTOV=YES, DEVICE=3525, and FUNC Omitted or FUNC=W[T]
 - = F PRINTOV=YES, DEVICE=3525, and FUNC=RW[T]
 - = C PRINTOV=YES, DEVICE=3525, and FUNC=PW[T]
 - = D PRINTOV=YES, DEVICE=3525, and FUNC=RPW[T]
 - = E ERROPT=YES and PRINTOV=YES not specified
 - = Z PRINTOV=YES not specified, and DEVICE not 3525
 - = O PRINTOV=YES not specified, DEVICE=3525, and FUNC omitted or FUNC=W[T]
 - = R PRINTOV=YES not specified, DEVICE=3525, and FUNC=RW[T]
 - = S PRINTOV=YES not specified, DEVICE=3525, and FUNC=PW[T]
 - = T PRINTOV=YES not specified, DEVICE=3525, and FUNC=RPW[T]
 - = U DEVICE=2560 or 5425 and FUNC=W or omitted
 - = V DEVICE=2560 or 5425 and FUNC=RW
 - = W DEVICE=2560 or 5425 and FUNC=PW
 - = X DEVICE=2560 or 5425 and FUNC=RPW

- d = I IOAREA2=YES
 - = Z IOAREA2 is **not** specified

- e = V RONLY=YES and WORKA=YES
 - = W WORKA=YES
 - = Y RONLY=YES
 - = Z neither is specified

PRMOD Names

IJDFAPIZ	IJDUZPIZ
IJDFAPZZ	IJDUZPZZ
IJDFYPIZ	IJDVAPIZ
IJDFYPZZ	IJDVAPZZ
IJDFZPIZ	IJDVYPIZ
IJDFZPZZ	IJDVYPZZ
IJDUAPIZ	IJDVZPIZ
IJDUAPZZ	IJDVZPZZ
IJDUYPIZ	
IJDUYPZZ	

IJDFUZZ
IJDFUIZ
IJDFUVZZ
IJDFUVIZ
IJDFUWZZ
IJDFUWIZ
IJDFUXZZ
IJDFUXIZ

IJDVUZZ
IJDVUIZ
IJDVUVZZ
IJDVUVIZ
IJDVUWZZ
IJDVUWIZ
IJDVUXZZ
IJDVUXIZ

IJDUUZZ
IJDUUIZ
IJDUUVZZ
IJDUUVIZ
IJDUWZZ
IJDUWIZ
IJDUXZZ
IJDUXIZ

IJDFAOIZ
IJDFAORIZ
IJDFAOIZ
IJDFAOIZ

IJDVAOIZ
IJDVARIZ
IJDVASIZ
IJDVATIZ

IJDUAOIZ
IJDUARIZ
IJDUASIZ
IJDUATIZ

IJDFAOZZ
IJDFAOZZ
IJDFAOZZ
IJDFAOZZ
IJDFAOZZ
IJDFAOZZ
IJDFAOZZ
IJDFAOZZ
IJDFAOZZ
IJDFAOZZ
IJDFAOZZ
IJDFAOZZ
IJDFAOZZ
IJDFAOZZ

IJDVAOZZ
IJDVARZZ
IJDVASZZ
IJDVATZZ
IJDVZOIZ
IJDVZRIZ
IJDVZSIZ
IJDVZTIZ
IJDVZOZZ
IJDVZRZZ
IJDVZSZZ
IJDVZTZZ

IJDUAOZZ
IJDUARZZ
IJDUASZZ
IJDUATZZ
IJDUZOIZ
IJDUZRIZ
IJDUZSIZ
IJDUZTIZ
IJDUZOZZ
IJDUZRZZ
IJDUZSZZ
IJDUZTZZ

IJDFAIIZ
IJDFAFIZ
IJDFAOIZ
IJDFAOIZ

IJDVAIIZ
IJDVAFIZ
IJDVACIZ
IJDVADIZ

IJDVAIIZ
IJDVAFIZ
IJDVACIZ
IJDVADIZ

IJDFZIIZ
IJDFZFIZ
IJDFZCIZ
IJDFZDIZ

IJDUZIIZ
IJDUZFIZ
IJDUZCIZ
IJDUZDIZ

IJDVZIIZ
IJDVZFIZ
IJDVZCIZ
IJDVZDIZ

IJDFYIIZ
IJDFYFIZ
IJDFYCIZ
IJDFYDIZ

IJDUYIIZ
IJDUYFIZ
IJDUYCIZ
IJDUYDIZ

IJDVYIIZ
IJDVYFIZ
IJDVYCIZ
IFDVYDIZ

IJDFVUZZ
IJDFVUIZ
IJDFVVZZ
IJDFVVIZ
IJDFVWZZ
IJDFVWIZ
IJDFVXZZ
IJDFVXIZ

IJDVVUZZ
IJDVVUIZ
IJDVVVZZ
IJDVVVIZ
IJDVVWZZ
IJDVVWIZ
IJDVVXZZ
IJDVVXIZ

IJDUVUZZ
IJDUVUIZ
IJDUVVZZ
IJDUVVIZ
IJDUVWZZ
IJDUVWIZ
IJDUVXZZ
IJDUVXIZ

SDMOD

SDMODxx name = IJGabcde

a = C RECFORM=FIXUNB or FIXBLK and HOLD=YES
= F RECFORM=FIXUNB or FIXBLK and HOLD is **not** specified
= P RECFORM=SPNUNB or SPNBLK and HOLD=YES
= Q RECFORM=SPNUNB or SPNBLK and HOLD is **not** specified
= R RECFORM=UNDEF and HOLD=YES
= S RECFORM=VARUNB or VARBLK and HOLD=YES
= U RECFORM=UNDEF and HOLD is **not** specified
= V RECFORM=VARUNB or VARBLK and HOLD is **not** specified

b = I SDMODxI
= O SDMODxO
= U SDMODxU

c = C ERROPT=YES and ERREXT=YES
= E ERROPT=YES
= Z neither is specified

d = M TRUNCS=YES and FEOVD=YES
= T TRUNCS=YES
= W FEOVD=YES
= Z neither is specified

e = B CONTROL=YES and RONLY=YES
= C CONTROL=YES
= Y RONLY=YES
= Z neither is specified

SDMOD Names

IJGFIEWZ
IJGFOEWZ
IJGFUEWZ
IJGQIEWZ
IJGQOEWZ

IJGQUEWZ
IJGUIEWZ
IJGUOEWZ
IJGUUEWZ
IJGVIEWZ

IJGVOEWZ
IJGVUEWZ

Name List for Workfile Type Modules (TYPEFLE = WORK)

SDMODxx name = IJGabcde

a = T SDMODW specifies HOLD=YES
= W SDMODW does **not** specify HOLD=YES

b = C ERROPT=YES and ERREXT=YES
= E ERROPT=YES
= Z neither is specified

c = N NOTEPNT=YES
= R NOTEPNT=POINTRW
= Z NOTEPNT is **not** specified

d = C CONTROL=YES
= Z CONTROL is **not** specified

e = T RONLY=YES and UPDATE=YES
= U UPDATE=YES
= Y RONLY=YES
= Z neither is specified

System I/O Modules: (See "Required IOCS Modules" before deleting modules with the IJG prefix.)

IJGWEZZU
IJGWEZZZ
IJGWZNZZ
IJGWZRZZ

Required IOCS Modules

The following preassembled IOCS modules are required when cataloging IBM components to the core image library. These modules are also required when installing program products.

Module Names

IJFWEZZZ	IJJCPD1N
IJFWZNZZ	IJJCPD2
IJFWZZZZ	IJJCPD3
IJGFIETZ	IJJCPV
IJGWEZZU	IJJCPV1

IJGWEZZZ	IJJCPV2
IJGWZNZZ	IJJCP0
IJGWZRZZ	IJJCP0N
IJJCPA1N	IJJCP1
IJJCPDV	IJJCP1N

IJJCPDV1	IJJCP2
IJJCPDV2	IJJCP3
IJJCPD0	
IJJCPD0N	
IJJCPD1	

Installation Procedure

The following sections show you the steps and the libraries that are required to install the DOS/VS COBOL Compiler and Library.

DOS/VS COBOL Installation—DOS/VSE

This section describes DOS/VS COBOL Compiler and Library installation under DOS/VSE. The steps that follow present a brief overview of the installation process.

Libraries Required—DOS/VSE

The three libraries needed are:

- Core image library
- Source statement library
- Relocatable library.

Installation Process—DOS/VSE

To install DOS/VS COBOL using MSHP (Maintain System History Program), take the following steps:

1. Use the INSTALL PRODUCT to install the compiler and/or library.
2. Optionally, code the CBL statement and place it in C.CBLOPTINS to change the compiler default options.

For complete details on the installation process under DOS/VSE, see the DOS/VS COBOL Program Directory.

Verifying Success—DOS/VS Compiler Installation

A sample DOS/VS COBOL program (TESTRUN) to verify the success of the compiler installation is available in the source statement library. The sample program will be placed in the source statement library during the installation process.

Application of Corrective Maintenance

Three link-edit books are supplied with the modules installed in the relocatable library:

- ILACBVS for the compiler phases
- ILBDSYML for the SYMDMP library phases
- ILBD\$LNK for the transient routines.

It is recommended that these be used when link-editing the appropriate phases.

Note: If user-written linkage editor control statements are used for linkage editing, ACTION CLEAR must be specified.

DOS/VS COBOL Installation—VM/SP

This section describes DOS/VS COBOL Compiler and Library installation under VM/SP. DOS/VS COBOL runs in the CMS DOS environment.

Installation Process under VM/SP CMS

To install DOS/VS COBOL under CMS, take the following steps:

1. Mount the distribution tape.
2. IPL the DOS/VSE system.
3. Run the DOS/VSE MSHP program to restore the private libraries (just as normal installation under DOS/VSE).

For complete details on the installation process under VM/SP, see the *DOS/VS COBOL Program Directory*.

System Generation Considerations

The compiler and the library can be used on a system only if the following parameters are specified for the SUPVR and FOPT macro instructions during system generation:

SUPVR:	SYSTEM = DISK ASCII = YES MPS = BJF	(required only when the ASCII features of the compiler are used) (required only when the compiler is to be executed in the foreground)
FOPT:	AB = YES PCIL = YES GETVIS = YES RELLDR = YES SYSFIL = YES	(for use of STATE, FLOW, STXIT, SYMDMP, and COUNT features) (required only when the compiler is to be executed in the foreground and RELDR = YES has not been specified) (required for use of 3886; forced by VSAM = YES, and required if COUNT option is specified) (if relocating loader is to be used) (if system files are to be on disk)
VSAM:	VSAM = YES	(required for use of the VSAM feature)

System options selected at system generation enable you to tailor the DOS/VSE compiler to fit your installation's needs. The system options that can be used to control compiler processing specify whether:

- Control statements are to be written on SYSLST.
- A dump is to be written on SYSLST if an abnormal termination occurs. (You may not want this if the SYMDMP, STATE, or FLOW features are used.)
- The object module produced by the compiler is to be link-edited.
- An object deck is to be punched.
- The COBOL source statements are to be written on SYSLST.
- A Procedure Division map, Data Division map, or cross-reference listing is to be written on SYSLST.
- Diagnostic messages for the source program are to be written on SYSLST.

Instructions for specifying these options are given in the publications *DOS/VSE System Generation* and *DOS/VS Compiler and Library Programmer's Guide*.

Changing the Installation Defaults

To change the compiler default values to suit your installation, a new member, C.CBLOPTNS, must be added to the source statement library. This module must contain CBL and LST option cards defining the desired defaults. These may be overridden at compilation time by supplying a CBL and/or LST statement in the compiler input stream. CMS DOS does not support the LST statement.

CBL Statement—COBOL Option Control Statement

Although most options for compilation are specified either at system generation time or in the OPTION control statement, the COBOL compiler provides an additional statement, the CBL statement, for the specification of compile-time options unique to COBOL.

The CBL statement must be placed between the EXEC FCOBOL statement and the first statement in the COBOL program. The CBL statement cannot be continued. However, if specification of options will continue past column 71, more than one CBL card image may be used.

The options shown in Figure 7 on page 23 may appear in any order. No embedded blanks may appear in the operand field. Underscoring indicates the default value. No comments should appear in the operand field.

For additional information on the CBL statement, see *DOS/VS COBOL Compiler and Library Programmer's Guide*.

CBL	[ADV NOADV]	[,APOST ,QUOTE]	[,BUF=nnnn]
	[,CATALR ,NOCATALR]	[,CLIST ,NOCLIST]	[,COUNT ,NOCOUNT]
	[,FLAGE ,FLAG]	[,FLOW[=nn]]	[,LANGLVL(1) ,LANGLVL(2)]
	[,LIB ,NOLIB]	[,LVL=A B C D ,NOLVL]	[,MIGR ,NOMIGR]
	[,OPTIMIZE ,OPT ,NOOPTIMIZE ,NOOPT]	[,PMAP=h]	[,SEQ ,NOSEQ]
	[,SPACE _n]	[,STATE ,NOSTATE]	[,STXIT ,NOSTXIT]
	[,SUPMAP ,NOSUPMAP]	[,SXREF ,NOSXREF]	[,SYMDMP[=filename]]
	[,SYNTAX ,CSYNTAX ,NOSYNTAX]	[,TRUNC ,NOTRUNC]	[,VERB ,NOVERB]
	[,VERBREF ,NOVERBREF]	[,VERBSUM ,NOVERBSUM]	[,ZWB ,NOZWB]

Figure 7. CBL Statement options

Storage Requirements

This section defines the partition size required by the DOS/VSE compiler alone and the storage required by the compiler together with the DOS/VSE subroutine library on the core image library. The storage needed for the compiler, subroutines, and required IOCS modules on the relocatable library is also given.

Virtual Storage

A minimum 64K bytes of virtual storage is required. The compiler needs added virtual storage if a BUF parameter is specified on the CBL card. Enough extra storage must be allocated to compensate for six buffers of that size.

Core Image Library

Number of Phases		Number of Library Blocks For AF3* (Physical Records)
Compiler	26	700
Transient routine	4	4
Library phases	14	32

*All devices supported by Advanced Function, Release 3.

Compiler Phases

FCOBOL00
FCOBOL04 (Note 5)
FCOBOL05
FCOBOL06 (Note 1)
FCOBOL08
FCOBOL10
FCOBOL11
FCOBOL12
FCOBOL20
FCOBOL21

FCOBOL22
FCOBOL25 (Note 2)
FCOBOL30
FCOBOL35 (Note 6)
FCOBOL40
FCOBOL45 (Note 7)
FCOBOL50
FCOBOL51
FCOBOL60 (Note 3)
FCOBOL62
FCOBOL63
FCOBOL64
FCOBOL65 (Note 2)
FCOBOL61
FCOBOL70
FCOBOL80 (Note 4)

Notes:

1. Phases FCOBOL05, FCOBOL06, and FCOBOL08 are executed only when the lister feature is used.
2. Phases FCOBOL25 and FCOBOL65 are executed only when symbolic debugging is used.
3. If optimization is *not* requested, phase FCOBOL60 is called instead of FCOBOL62, FCOBOL63, and FCOBOL64.
4. If FIPS processing is not requested, phase FCOBOL80 is not called, and compilation terminates after phase FCOBOL70.
5. Phase FCOBOL05 is executed only if LIB option is set.
6. Phase FCOBOL35 is executed only if USE FOR DEBUGGING is used.
7. Phase FCOBOL45 is executed only if UNSTRING is used.

Transient Routines

\$\$BCOBEM (Executed only when SYMDMP, FLOW, STATE, or COUNT is specified.)

\$\$BCOBER

\$\$BCOBR1

\$\$BFCMUL

Library Phases

Executed only when SYMDMP is specified.

ILBDMP01

ILBDMP02

ILBDMP04

ILBDMP10

ILBDMP11

ILBDMP12

ILBDMP13

ILBDMP14

ILBDMP20

ILBDMP21

ILBDMP22

ILBDMP23

ILBDMP24

ILBDMP25

Relocatable Library

Number of Modules		Number of Library Blocks (Physical Records)
Compiler	41	Approximately 3000
Library	95	Approximately 460
IOCS	7	Approximately 32

Compiler Modules

ILACBVS	ILACBL30	ILACBL80
ILACBL00	ILACBL35	ILACBL81
ILACBL01	ILACBL40	ILACBL82
ILACBL04	ILACBL45	ILACBL83
ILACBL05	ILACBL50	ILACBL84
ILACBL06	ILACBL51	ILACBL85
ILACBL08	ILACBL60	ILACBL86
ILACBL10		ILACBL87
ILACBL11	ILACBL62	ILACBL88
	ILACBL63	ILACBL89
ILACBL12	ILACBL64	ILACBL8A
ILACBL20	ILACBL65	ILACBL8B
ILACBL21	ILACBL61	ILACBL8C
ILACBL22	ILACBL70	ILACBL8D
ILACBL25		

Subroutines

Library Modules	Approximate Number of Bytes of Virtual Storage	Blocks
ILBDABX0	495	4
ILBDACP0	1050	7
ILBDACS0	242	2
ILBDADR0	350	4
ILBDANE0	325	3
ILBDANF0	110	2
ILBDASY0	90	2
ILBDATB0	260	2
ILBDBID0	115	2
ILBDBIE0	120	2
ILBDBII0	465	4
ILBDBUG0	1080	8
ILBDCKP0	850	6
ILBDCLK0	60	2
ILBDCLS0	150	2
ILBDCMM0	1032	7
ILBDCRD0	150	2
ILBDCT10	480	3
ILBDCVB0	1136	8
ILBDDAE0	345	4
ILBDDBG0	2805	16
ILBDDCI0	180	5
ILBDDIO0	720	5
ILBDDSP0	1330	9
ILBDDSR0	335	4
ILBDDSS0	810	6
ILBDDTE0	436	4
ILBDDUM0	2	2
ILBDEFLO	525	6
ILBDETBO	260	4
ILBDFLW0	1260	9
ILBDFMT0	185	3
ILBDFPW0	810	4
ILBDGDO0	160	2
ILBDGPW0	90	2
ILBDIDA0	400	3
ILBDIDB0	120	2
ILBDIDR0	1665	8
ILBDIDT0	695	4
ILBDIFB0	300	3
ILBDIFD0	160	5
ILBDIML0	90	2
ILBDINS0	1932	11
ILBDINT0	290	4
ILBDISE0	480	4
ILBDISM0	370	4
ILBDITB0	260	12
ILBDIVL0	75	2
ILBDMFT0	150	3
ILBDMNS0	375	4
ILBDMOV0	70	3

Library Modules	Approximate Number of Bytes of Virtual Storage	Blocks
ILBDMRG0	1150	3
ILBDMVE0	250	3
ILBDNSL0	620	5
ILBDOCR0	1925	10
ILBDASY0	135	3
ILBDRCR0	150	2
ILBDRDI0	410	4
ILBDRDS0	240	3
ILBDRFM0	135	2
ILBDSAE0	400	4
ILBDSCH0	745	4
ILBDSEM0	280	5
ILBDSET0	300	3
ILBDSIO0	2856	17
ILBDSMV0	60	2
ILBDSPA0	3824	20
ILBDSRT0	3720	19
ILBDSTR0	80	3
ILBDSSN0	300	3
ILBDSTG0	672	6
ILBDSTI0	600	4
ILBDSTN0	1740	8
ILBDTAB0	475	4
ILBDTC00	1170	7
ILBDTC20	500	3
ILBDTC30	4220	19
ILBDTEF0	600	6
ILBDTOD0	200	2
ILBDTRN0	260	2
ILBDUPS0	110	2
ILBDUSL0	365	3
ILBDUST0	2176	12
ILBDUTB0	260	12
ILBDVBL0	315	4
ILBDVCO0	515	3
ILBDVIO0	4660	22
ILBDVMO0	470	4
ILBDVOC0	4280	18
ILBDVTR0	140	2
ILBDWTB0	260	3
ILBDXDIO	275	3
ILBDXMU0	185	2
ILBDXPR0	670	6
ILBDXTN0	290	3

IOCS Modules

Needed when the ASCII Support Feature is used.

- IJFXBZZN
- IJFXBZZZ
- IJFXZZZZ
- IJFNZZZN
- IJFNZZZZ
- IJFRZZZN
- IJFRZZZZ

Appendix. Device Information

This appendix gives information regarding specific input/output devices that can be used with a DOS/VS COBOL program.

Minimum and Maximum Block Size Values

The minimum and maximum block sizes that can be specified for specific devices are shown in Figure 8.

Device Type	Fixed and Undefined Records Block Size (Bytes)		Variable Records Block Size (Bytes)	
	Minimum	Maximum	Minimum	Maximum
Card Reader	1	80	9	80
Card Punch	1	81	9	89
Print Line Length (1403, 3800, etc.)				
120 characters	1	121	9	129
132 characters	1	133	9	141
144 characters	1	145	9	153
150 characters	1	151	9	159
Magnetic Tape	18	32760	18	32760
Direct Access				
2314	1	7294	9	7294
3330	1	13030	9	18030
3340	1	8368	9	8368
3350	1	19069	9	19069
3375	1	32760	9	32760
Notes:				
1.	For DOS/VSE Fixed Block Architecture devices, see the manuals describing the devices you are using.			
2.	For direct access devices with the track overflow feature, the maximum is 32760 for each device.			

Figure 8. DOS/VS COBOL Devices—Minimum and Maximum Block Sizes

Index

A

- apostrophe, APOST option and 23
- arithmetic expressions with COMPUTATIONAL fields:
 - TRUNC/NOTRUNC option and 23
- ASCII collating sequence support
 - ASCII parameter required 21
 - IOCS modules required 29
 - Sort/Merge Program required 2

B

- background partition support by CMS 7
- BUF option (CBL statement)
 - format 23
 - virtual storage required when specified 23

C

- CATAL option, SYSLNK file and 3
- CATALR/NOCATALR option (CBL statement)
 - format 23
- CBL statement: COBOL option control
 - statement 22–23
- CDMOD module names 10–11
- CDMOD names
 - DAMOD names 12
 - DRMOD names 12
 - DUMOD names 13
 - introduction 8
 - ISMOD names 13
 - MTMOD names 14
 - naming conventions for relocatable library 9
 - PRMOD names 16–18
 - required 19
 - SDMOD names 18
 - system 15, 19
- changing the installation defaults 22–23
- CLIST/NOCLIST option (CBL statement)
 - format 23
- CMS considerations
 - background partition supported 7
 - device support 3, 6
 - execution-time requirements 1, 6
 - installation requirements 1, 5
 - LIOCS modules and 8
 - machine configuration 5
 - private library access 3
 - separate library not needed 1
 - SYSLNK not supported 6
 - system requirements 2, 3
 - work file requirements 6
- CMS requirements 5

- compiler
 - CBL statement options
 - formats 23
 - system options controlling 23
- compiler and library
 - contents 1
 - installation 21
 - storage required 23
- COMPUTATIONAL receiving fields, TRUNC/NOTRUNC option 23
- condensed listing, compiler, specified by CLIST option 23
- contents of DOS/VS COBOL compiler and library program product 1
- core image library
 - storage required for compiler, and library phases 23
- COUNT/NOCOUNT option (CBL statement)
 - format 23
 - installation parameter required 21
 - virtual storage required 4
- CSYNTAX/SYNTAX/NOSYNTAX option (CBL statement)
 - format 23
- C.CBLOPTNS source statement library member 22

D

- DAMOD module names 12
- debug (see SYMDMP option)
- default values of CBL statement options,
 - changing 22–23
- devices
 - compiler use 3–4
 - minimum and maximum block sizes 30
 - Sort/Merge Program requirements 4
 - storage requirements for 23
 - supported by CMS 6
- disk units, work file allocations to 5–7
- DOS/VS requirements 3
- DRMOD names 12
- DUMOD module names 13

E

- execution statistics: virtual storage required 4
- execution-time CMS requirements 1, 6
- execution-time considerations 4

F

- Federal Information Processing Standard (see FIPS)
- filenames (work files) 3, 6
- files, system: installation parameter required 21

- files, work (see work files)
- FIPS
 - considerations 5
 - flagger, LVL option specification of 23
 - work files
 - allocations required 7
 - contents 7
- fixed block devices 3, 8
- FLAGW/E option (CBL statement)
 - format 23
- FLOW option (CBL statement)
 - additional storage required 4
 - format 23
 - installation parameter required 21
- FOPT macro instruction, parameters required for 21

I

- installation procedure
 - changing option defaults 22
 - compiler and library—DOS/VSE 20
 - compiler and library—VM/SP 21
 - system generation considerations 21
- installation requirements for CMS 1
- IOCS modules
 - ASCII support 29
 - blocks required for storage 26
- ISMOD module names 13

L

- library
 - installation parameters governing partitions 21
 - object-time subroutine
 - contents 1
 - storage required 23–29
- LIB/NOLIB option (CBL statement)
 - format 23
- line-spacing on compiler output listing: SPACE_n option and 23
- LINK option (OPTION statement)
 - SYSLNK file and 3
- LIOCS modules and CMS 8
- lister feature: compiler phase names 24–25
- logical units: assignment for compiler use 3
- LST statement (lister feature)
 - CMS does not support 22
- LVL option (CBL statement)
 - format 23

M

- machine configuration
 - for CMS 5–6
 - for DOS/VS 3
- macro instruction parameters required for DOS/VS
 - compiler and library installation 21

- MIGR/NOMIGR option (CBL statement)
 - format 23
- module names
 - MTMOD 14–15
 - SDMOD 19
- MTMOD module names 14–15

O

- object-time subroutine library
 - contents 1
- operating system requirements 2–3
- OPTIMIZE/NOOPTIMIZE option (CBL statement)
 - format 23
- options
 - CBL statement
 - changing installation defaults 22
 - format 23
 - LST statement
 - format 23
 - system 21

P

- parameters required in SUPV, FOPT, and VSAM macro
 - instructions 21
- partitions, effect of on assignment 7
- phases, compiler
 - blocks required
 - core image library 23
 - relocatable library 26
 - listed 24
- PMAP=h option (CBL statement)
 - format 23
- private library
 - CMS access 2
 - core image, effect of macro instruction on 21
- PRMOD module names 16–18
- program logical units: required assignments 3, 6–8

Q

- quotation marks, QUOTE option and 23
- QUOTE/APOST option (CBL statement)
 - format 23

R

- relocatable library, blocks required for compiler,
 - library, and IOCS modules 26
- required IOCS modules 19

S

- sample program, using after installation 20
- SDMOD module names 18–19
- separate library unnecessary for CMS 1
- separately-signed numeric sort keys: Sort/Merge
 - program required 2

- SEQ/NOSEQ option (CBL statement)
 - format 23
- SORT verb operating system requirements
 - Sort/Merge feature
 - considerations 4
 - program produce required 2
- SPACE option (CBL statement) 23
- STATE/NOSTATE option (CBL statement)
 - additional storage required 4
 - format 23
 - installation parameter required 21
- statistics, execution: virtual storage required 4
- storage requirements
 - core image library 23–25
 - general description 3
 - partition size 23
 - relocatable library 26–29
 - Sort/Merge program 4
 - subroutines (each) 27–29
- STXIT/NOSTXIT option (CBL statement)
 - format 23
 - installation parameter required 21
- subroutines, object-time, storage required for each 27–29
- SUPMAP/NOSUPMAP option (CBL statement)
 - format 23
- SUPVR macro instruction, parameters required for compiler 21
- SXREF/NOSXREF option (CBL statement)
 - format 23
- symbolic debug considerations 4–5
- symbolic dump option (see SYMDMP option)
- SYMDMP option (CBL statement)
 - format 23
 - general considerations 4–6
 - installation parameter required 21
 - multiple COBOL compilations 4
 - work files 4–5
- SYNTAX/CSYNTAX/NOSYNTAX option (CBL statement)
 - format 23
- SYSLNK file
 - assignment for compiler use 3
 - CATAL and LINK options and 3
 - not supported for CMS 6
 - required 6
- SYSRES file assignment required 6
- system generation considerations 21–23
- system I/O module names
 - MTMOD 14–15
 - SDMOD 19
- system options 23
- system requirements
 - for CMS 2
 - for DOS/VSE 2
 - machine configuration
 - for CMS 5–6
 - for DOS/VSE 3–4

- system, DOS, minimum release level
 - required 2
- SYS00n work files: assignment for compiler use 3, 6
- SYS005 for symbolic debug feature 3, 6
- SYS006 FIPS work file 3, 5

T

- tape work file requirements 6
- transient routines
 - core image library storage required 23
 - listed 25
 - object-time library, in 1
- TRUNC/NOTRUNC option (CBL statement)
 - format 23

U

- units, logical: assignment for compiler
 - for CMS 5
 - for DOS/VSE 3–4
- using the sample program 20

V

- VERBREF/NOVERBREF option (CBL statement)
 - format 23
- VERBSUM/NOVERBSUM option (CBL statement)
 - format 23
- VERB/NOVERB option (CBL statement)
 - format 23
- VSAM macro instruction parameters
 - required 21

W

- work files, allocation, disk devices 6–8

Z

- ZWB/NOZWB option (CBL statement)
 - format 23

Numerics

- 2311 disk unit, work file allocations to 7
- 2314 disk device
 - core image library storage for 23
 - work file allocation to 7
- 3330 disk device
 - core image library storage for 23
 - used with Sort/Merge 4
 - work file allocation to 7
- 3340 disk unit, work file allocations to 7
- 3350 direct access storage
 - used with CMS 6
 - used with Sort/Merge 4
 - work files 3, 7

3886 Optical Character Reader
GETVIS parameter required 21
virtual storage required 4





Cut or Fold
Along Line


Fold and Tape

Please do not staple

Fold and Tape



NO POSTAGE
NECESSARY
IF MAILED IN THE
UNITED STATES



BUSINESS REPLY MAIL

FIRST CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

International Business Machines Corporation
Department J58
PO BOX 49023
SAN JOSE CA 95161-9945



Fold and Tape

Please do not staple

Fold and Tape

Cut or Fold
Along Line



Cut or Fold
Along Line


Fold and Tape

Please do not staple

Fold and Tape



NO POSTAGE
NECESSARY
IF MAILED IN THE
UNITED STATES



BUSINESS REPLY MAIL

FIRST CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

International Business Machines Corporation
Department J58
PO BOX 49023
SAN JOSE CA 95161-9945



Fold and Tape

Please do not staple

Fold and Tape

Cut or Fold
Along Line



Cut or Fold
Along Line

Fold and Tape

Please do not staple

Fold and Tape



NO POSTAGE
NECESSARY
IF MAILED IN THE
UNITED STATES



BUSINESS REPLY MAIL

FIRST CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

International Business Machines Corporation
Department J58
PO BOX 49023
SAN JOSE CA 95161-9945



Fold and Tape

Please do not staple

Fold and Tape

Cut or Fold
Along Line



Program Numbers
5746-CB1
5746-LM4

File Number
S370-34

SC28-6479-4

